

Process Management Interface for Exascale (PMIx) Standard

Version 5.0 (Draft)

Created on February 16, 2021

This document describes the Process Management Interface for Exascale (PMIx) Standard, version 5.0 (Draft).

Comments: Please provide comments on the PMIx Standard by filing issues on the document repository https://github.com/pmix/pmix-standard/issues or by sending them to the PMIx Community mailing list at https://groups.google.com/forum/#!forum/pmix. Comments should include the version of the PMIx standard you are commenting about, and the page, section, and line numbers that you are referencing. Please note that messages sent to the mailing list from an unsubscribed e-mail address will be ignored.

Copyright © 2018-2020 PMIx Administrative Steering Committee (ASC). Permission to copy without fee all or part of this material is granted, provided the PMIx ASC copyright notice and the title of this document appear, and notice is given that copying is by permission of PMIx ASC.



Contents

1	Intro	duction				1
١.	1.1.	Background				
						1
	1.2.	PMIx Architecture Overview		•		1
	1.3.	Portability of Functionality				3
		1.3.1. Attributes in PMIx			•	3
2.	PMIx	Terms and Conventions				6
	2.1.	Notational Conventions				8
	2.2.	Semantics				9
	2.3.	Naming Conventions				10
	2.4.	Procedure Conventions				10
3.	Data	Structures and Types				12
	3.1.	Constants				13
		3.1.1. PMIx Return Status Constants				14
		3.1.1.1. User-Defined Error and Event Constants				15
	3.2.	Data Types				16
		3.2.1. Key Structure				16
		3.2.1.1. Key support macros				16
		3.2.2. Namespace Structure				17
		3.2.2.1. Namespace support macros				18
		3.2.3. Rank Structure				19
		3.2.3.1. Rank support macros				19
		3.2.4. Process Structure				20
						20
		ria.			•	
		3.2.5. Process State Structure				23
		3.2.6. Process Information Structure				24
		3.2.6.1. Process information structure support macros				25
		3.2.7. Job State Structure				27

	3.2.8.	Value Structure	27
		3.2.8.1. Value structure support macros	28
	3.2.9.	Info Structure	32
		3.2.9.1. Info structure support macros	32
		3.2.9.2. Info structure list macros	35
	3.2.10.	Info Type Directives	37
		3.2.10.1. Info Directive support macros	38
	3.2.11.	Environmental Variable Structure	41
		3.2.11.1. Environmental variable support macros	41
	3.2.12.	Byte Object Type	43
		3.2.12.1. Byte object support macros	43
	3.2.13.	Data Array Structure	44
		3.2.13.1. Data array support macros	44
	3.2.14.	Argument Array Macros	46
	3.2.15.	Set Environment Variable	50
3.3.	Genera	alized Data Types Used for Packing/Unpacking	50
3.4.	Genera	al Callback Functions	52
	3.4.1.	Release Callback Function	52
	3.4.2.	Op Callback Function	53
	3.4.3.	Value Callback Function	53
	3.4.4.	Info Callback Function	54
	3.4.5.	Handler registration callback function	55
3.5.	PMIx 1	Datatype Value String Representations	55
Clier	nt Initia	lization and Finalization	59
4.1.	PMIx_	_Initialized	59
4.2.	PMIx_	Get_version	60
4.3.	PMIx_	_Init	60
	4.3.1.	Initialization events	63
	4.3.2.	Initialization attributes	63
		4.3.2.1. Connection attributes	63
		4.3.2.2. Programming model attributes	64
4.4.	PMIx_	_Finalize	65
		Finaline attailmts	65

	4.5.	PMIx_Progress	65
5.	Sync	chronization and Data Access Operations	67
	5.1.	PMIx_Fence	67
	5.2.	PMIx_Fence_nb	69
		5.2.1. Fence-related attributes	71
	5.3.	PMIx_Get	72
		5.3.1. PMIx_Get_nb	74
		5.3.2. Retrieval attributes	77
	5.4.	Query	78
		5.4.1. PMIx_Resolve_peers	79
		5.4.2. PMIx_Resolve_nodes	7 9
		5.4.3. PMIx_Query_info	80
		5.4.4. PMIx_Query_info_nb	85
		5.4.5. Query-specific constants	89
		5.4.6. Query attributes	90
		5.4.7. Query Structure	92
		5.4.7.1. Query structure support macros	93
	5.5.	Using Get vs Query	95
	5.6.	Accessing attribute support information	95
_	_		
6.		erved Keys	98
	6.1.	Data realms	98
		6.1.1. Session realm attributes	99
		6.1.2. Job realm attributes	101
		6.1.3. Application realm attributes	103
		6.1.4. Process realm attributes	104
		6.1.5. Node realm keys	106
	6.2.	Retrieval rules for reserved keys	107
		6.2.1. Accessing information: examples	107
		6.2.1.1. Session-level information	108
		6.2.1.2. Job-level information	109
		6.2.1.3. Application-level information	109
		6.2.1.4. Process-level information	110

		6.2.1.5. Node-level information	110
7.	Proc	ess-Related Non-Reserved Keys	112
	7.1.	Posting Key/Value Pairs	113
		7.1.1. PMIx_Put	113
		7.1.1.1. Scope of Put Data	114
		7.1.2. PMIx_Store_internal	114
		7.1.3. PMIx_Commit	115
	7.2.	Retrieval rules for non-reserved keys	116
8	Publ	ish/Lookup Operations	118
٥.	8.1.	PMIx_Publish	118
	8.2.	PMIx_Publish_nb	120
	8.3.	Publish-specific constants	121
	8.4.	Publish-specific attributes	121
	8.5.	Publish-Lookup Datatypes	122
	0.5.	8.5.1. Range of Published Data	122
		8.5.2. Data Persistence Structure	122
	8.6.	PMIx_Lookup	123
	8.7.	PMIx_Lookup_nb	125
		8.7.1. Lookup Returned Data Structure	127
		8.7.1.1. Lookup data structure support macros	127
		8.7.2. Lookup Callback Function	130
	8.8.	Retrieval rules for published data	130
	8.9.	PMIx_Unpublish	131
	8.10.	PMIx_Unpublish_nb	133
_			
		nt Notification	135
	9.1.	Notification and Management	135
		9.1.1. Events versus status constants	137
		9.1.2. PMIx_Register_event_handler	137
		9.1.3. Event registration constants	140
		9.1.4. System events	141
		9.1.5. Event handler registration and notification attributes	141
		9.1.5.1. Fault tolerance event attributes	142

	9	2.1.5.2. Hybrid programming event attributes	142
	9.1.6.	Notification Function	143
	9.1.7.	PMIx_Deregister_event_handler	144
	9.1.8.	PMIx_Notify_event	145
	9.1.9.	Notification Handler Completion Callback Function	149
	9	2.1.9.1. Completion Callback Function Status Codes	149
10. Data	Packing	g and Unpacking	150
10.1.	Data Bu	ffer Type	150
10.2.	Support	Macros	151
10.3.	General	Routines	152
	10.3.1.	PMIx_Data_pack	152
	10.3.2.	PMIx_Data_unpack	154
	10.3.3.	PMIx_Data_copy	156
	10.3.4.	PMIx_Data_print	156
	10.3.5.	PMIx_Data_copy_payload	157
11.Proc	ess Mar	nagement	159
11.1.	Abort .		159
	11.1.1.	PMIx_Abort	159
11.2.	Process	Creation	160
	11.2.1.	PMIx_Spawn	160
	11.2.2.	PMIx_Spawn_nb	166
	11.2.3.	Spawn-specific constants	171
	11.2.4.	Spawn attributes	171
	11.2.5.	Application Structure	175
	1	1.2.5.1. App structure support macros	175
	1	1.2.5.2. Spawn Callback Function	177
11.3.	Connect	ing and Disconnecting Processes	178
	11.3.1.	PMIx_Connect	179
	11.3.2.	PMIx_Connect_nb	181
	11.3.3.	PMIx_Disconnect	182
	11.3.4.	PMIx_Disconnect_nb	184

11.4.	Process Locality	186
	11.4.1. PMIx_Load_topology	186
	11.4.2. PMIx_Get_relative_locality	187
	11.4.2.1. Topology description	187
	11.4.2.2. Topology support macros	188
	11.4.2.3. Relative locality of two processes	189
	11.4.2.4. Locality keys	189
	11.4.3. PMIx_Parse_cpuset_string	189
	11.4.4. PMIx_Get_cpuset	190
	11.4.4.1. Binding envelope	190
	11.4.5. PMIx_Compute_distances	191
	11.4.6. PMIx_Compute_distances_nb	192
	11.4.7. Device Distance Callback Function	193
	11.4.8. Device type	193
	11.4.9. Device Distance Structure	194
	11.4.10. Device distance support macros	195
	11.4.11. Device distance attributes	196
12 .lob l	Management and Reporting	197
	Allocation Requests	197
12.11	12.1.1. PMIx_Allocation_request	197
	12.1.2. PMIx_Allocation_request_nb	200
	12.1.3. Job Allocation attributes	203
	12.1.4. Job Allocation Directives	205
12.2.	Job Control	205
	12.2.1. PMIx_Job_control	206
	12.2.2. PMIx_Job_control_nb	208
	12.2.3. Job control constants	211
	12.2.4. Job control events	212
	12.2.5. Job control attributes	212
12.3.	Process and Job Monitoring	213
	12.3.1. PMIx_Process_monitor	213
	12.3.2. PMIx_Process_monitor_nb	216
	1233 PMTx Heartheat	218

	12.3.4.	Monitoring events	218
	12.3.5.	Monitoring attributes	218
12.4.	Logging		219
	12.4.1.	PMIx_Log	219
	12.4.2.	PMIx_Log_nb	222
	12.4.3.	Log attributes	225
13. Proc	ess Sets	s and Groups	227
		Sets	227
	13.1.1.	Process Set Constants	228
	13.1.2.	Process Set Attributes	229
13.2.	Process	Groups	229
	13.2.1.	Relation to the host environment	229
	13.2.2.	Construction procedure	230
	13.2.3.	Destruct procedure	231
	13.2.4.	Process Group Events	231
	13.2.5.	Process Group Attributes	232
	13.2.6.	PMIx_Group_construct	234
	13.2.7.	PMIx_Group_construct_nb	237
	13.2.8.	PMIx_Group_destruct	240
	13.2.9.	PMIx_Group_destruct_nb	241
	13.2.10.	PMIx_Group_invite	243
	13.2.11.	PMIx_Group_invite_nb	246
	13.2.12.	PMIx_Group_join	249
	13.2.13.	PMIx_Group_join_nb	251
	1	3.2.13.1. Group accept/decline directives	252
	13.2.14.	PMIx_Group_leave	252
	13.2.15.	PMIx_Group_leave_nb	254
14. Fabri	ic Supp	ort Definitions	256
		upport Events	259
		upport Datatypes	259
2.	14.2.1.		259
		Fabric endpoint support macros	260

	14.2.3.	Fabric Coordinate Structure	261
	14.2.4.	Fabric coordinate support macros	261
	14.2.5.	Fabric Geometry Structure	263
	14.2.6.	Fabric geometry support macros	263
	14.2.7.	Fabric Coordinate Views	265
	14.2.8.	Fabric Link State	265
	14.2.9.	Fabric Operation Constants	266
	14.2.10.	Fabric registration structure	266
	1	4.2.10.1. Initialize the fabric structure	269
14.3.	Fabric S	Support Attributes	269
14.4.	Fabric S	Support Functions	272
	14.4.1.	PMIx_Fabric_register	273
	14.4.2.	PMIx_Fabric_register_nb	275
	14.4.3.	PMIx_Fabric_update	275
	14.4.4.	PMIx_Fabric_update_nb	276
	14.4.5.	PMIx_Fabric_deregister	277
	14.4.6.	PMIx_Fabric_deregister_nb	277
15. Secu	•		279
15.1.		ng Credentials	279
		PMIx_Get_credential	280
	15.1.2.	PMIx_Get_credential_nb	281
	15.1.3.	Credential Attributes	282
15.2.		ng Credentials	283
		PMIx_Validate_credential	283
	15.2.2.	PMIx_Validate_credential_nb	284
16. Serv	er-Spec	ific Interfaces	287
		nitialization and Finalization	287
		PMIx server init	287
		PMIx_server_finalize	291
	16.1.3.	Server Initialization Attributes	291
16.2		Support Functions	292
10.2.		PMTv gonorato rogov	202

	16.2.2.	PMIx_generate_ppn 2	294
	16.2.3.	PMIx_server_register_nspace	294
	1	6.2.3.1. Namespace registration attributes	305
	1	6.2.3.2. Assembling the registration information	306
	16.2.4.	PMIx_server_deregister_nspace	315
	16.2.5.	PMIx_server_register_resources 3	315
	16.2.6.	PMIx_server_deregister_resources	316
	16.2.7.	PMIx_server_register_client	317
	16.2.8.	PMIx_server_deregister_client	319
	16.2.9.	PMIx_server_setup_fork 3	319
	16.2.10.	PMIx_server_dmodex_request 3	320
	1	6.2.10.1. Server Direct Modex Response Callback Function	321
	16.2.11.	PMIx_server_setup_application	322
	1	6.2.11.1. Server Setup Application Callback Function	325
	1	6.2.11.2. Server Setup Application Attributes	326
	16.2.12.	PMIx_Register_attributes	326
	1	6.2.12.1. Attribute registration constants	328
	1	6.2.12.2. Attribute registration structure	328
	1	6.2.12.3. Attribute registration structure descriptive attributes	329
	1	6.2.12.4. Attribute registration structure support macros	329
	16.2.13.	PMIx_server_setup_local_support 3	331
	16.2.14.	PMIx_server_IOF_deliver	333
	16.2.15.	PMIx_server_collect_inventory	334
	16.2.16.	PMIx_server_deliver_inventory	335
	16.2.17.	PMIx_server_generate_locality_string 3	336
	16.2.18.	PMIx_server_generate_cpuset_string	337
	1	6.2.18.1. Cpuset Structure	338
	1	6.2.18.2. Cpuset support macros	338
	16.2.19.	PMIx_server_define_process_set	339
4	16.2.20.	PMIx_server_delete_process_set	340
	Server F	Function Pointers	340
	16.3.1.	pmix_server_module_t Module	341
	1622	main source alient sourceted for t	242

16.3.3. pmix_server_client_connected2_fn_t	343
16.3.4. pmix_server_client_finalized_fn_t	345
16.3.5. pmix_server_abort_fn_t	346
16.3.6. pmix_server_fencenb_fn_t	348
16.3.6.1. Modex Callback Function	351
16.3.7. pmix_server_dmodex_req_fn_t	351
16.3.7.1. Dmodex attributes	353
16.3.8. pmix_server_publish_fn_t	353
16.3.9. pmix_server_lookup_fn_t	355
16.3.10. pmix_server_unpublish_fn_t	358
16.3.11. pmix_server_spawn_fn_t	360
16.3.11.1. Server spawn attributes	365
16.3.12. pmix_server_connect_fn_t	365
16.3.13. pmix_server_disconnect_fn_t	367
16.3.14. pmix_server_register_events_fn_t	369
16.3.15. pmix_server_deregister_events_fn_t	371
16.3.16. pmix_server_notify_event_fn_t	373
16.3.17. pmix_server_listener_fn_t	374
16.3.17.1. PMIx Client Connection Callback Function	375
16.3.18. pmix_server_query_fn_t	376
16.3.19. pmix_server_tool_connection_fn_t	378
16.3.19.1. Tool connection attributes	381
16.3.19.2. PMIx Tool Connection Callback Function	381
16.3.20. pmix_server_log_fn_t	381
16.3.21. pmix_server_alloc_fn_t	383
16.3.22. pmix_server_job_control_fn_t	386
16.3.23. pmix_server_monitor_fn_t	389
16.3.24. pmix_server_get_cred_fn_t	392
16.3.24.1. Credential callback function	393
16.3.25. pmix_server_validate_cred_fn_t	394
16.3.26. Credential validation callback function	396
16.3.27. pmix_server_iof_fn_t	397
16.2.27.1 IOE delivery function	400

	16.3.28.	<pre>pmix_server_stdin_fn_t</pre>	401
	16.3.29.	pmix_server_grp_fn_t	402
	1	6.3.29.1. Group Operation Constants	405
	16.3.30.	pmix_server_fabric_fn_t	405
		ebuggers	407
17.1.	Connect	ion Mechanisms	407
	17.1.1.	Rendezvousing with a local server	410
	17.1.2.	Connecting to a remote server	411
	17.1.3.	Attaching to running jobs	412
	17.1.4.	Tool initialization attributes	412
	17.1.5.	Tool initialization environmental variables	413
	17.1.6.	Tool connection attributes	413
17.2.	Launchi	ng Applications with Tools	414
	17.2.1.	Direct launch	414
	17.2.2.	Indirect launch	418
	17.2.3.	Tool spawn-related attributes	421
	17.2.4.	Tool rendezvous-related events	422
17.3.	IO Forw	varding	423
	17.3.1.	Forwarding stdout/stderr	423
	17.3.2.	Forwarding stdin	425
	17.3.3.	IO Forwarding Channels	426
	17.3.4.	IO Forwarding constants	427
	17.3.5.	IO Forwarding attributes	427
17.4.	Debugge	er Support	428
	17.4.1.	Co-Location of Debugger Daemons	430
	17.4.2.	Co-Spawn of Debugger Daemons	432
	17.4.3.	Debugger Agents	433
	17.4.4.	Tracking the job lifecycle	434
		7.4.4.1. Job lifecycle events	435
	*	7.4.4.2. Job lifecycle attributes	436
	17.4.5.	Debugger-related constants	436
	17.4.6.	Debugger attributes	436
	- /	=	

17.5.	Tool-Specific APIs	438
	17.5.1. PMIx_tool_init	438
	17.5.2. PMIx_tool_finalize	441
	17.5.3. PMIx_tool_disconnect	442
	17.5.4. PMIx_tool_attach_to_server	443
	17.5.5. PMIx_tool_get_servers	445
	17.5.6. PMIx_tool_set_server	445
	17.5.7. PMIx_IOF_pull	446
	17.5.8. PMIx_IOF_deregister	448
	17.5.9. PMIx_IOF_push	449
A D. 46	on Dindings	450
-	on Bindings	452
A.1.	Design Considerations	452
	A.1.1. Error Codes vs Python Exceptions	452
4.2	A.1.2. Representation of Structured Data	452
A.2.	Datatype Definitions	453
4.2	A.2.1. Example	459
A.3.	Callback Function Definitions	460
	A.3.1. IOF Delivery Function	460
	A.3.2. Event Handler	460
	A.3.3. Server Module Functions	461
	A.3.3.1. Client Connected	461
	A.3.3.2. Client Finalized	462
	A.3.3.3. Client Aborted	462
	A.3.3.4. Fence	463
	A.3.3.5. Direct Modex	464
	A.3.3.6. Publish	464
	A.3.3.7. Lookup	465
	A.3.3.8. Unpublish	465
	A.3.3.9. Spawn	466
	A.3.3.10. Connect	466
	A.3.3.11. Disconnect	467
	A.3.3.12. Register Events	467
	A.3.3.13. Deregister Events	468

	A	A.3.3.14. Notify Event	468
	A	A.3.3.15. Query	468
	A	A.3.3.16. Tool Connected	469
	A	A.3.3.17. Log	469
	A	A.3.3.18. Allocate Resources	470
	A	A.3.3.19. Job Control	470
	A	A.3.3.20. Monitor	471
	A	A.3.3.21. Get Credential	471
	A	A.3.3.22. Validate Credential	472
	A	A.3.3.23. IO Forward	473
	A	A.3.3.24. IO Push	473
	A	A.3.3.25. Group Operations	474
	A	A.3.3.26. Fabric Operations	474
A.4.	PMIxCl	ient	475
	A.4.1.	Client.init	475
	A.4.2.	Client.initialized	475
	A.4.3.	Client.get_version	476
	A.4.4.	Client.finalize	476
	A.4.5.	Client.abort	476
	A.4.6.	Client.store_internal	477
	A.4.7.	Client.put	477
	A.4.8.	Client.commit	478
	A.4.9.	Client.fence	478
	A.4.10.	Client.get	479
	A.4.11.	Client.publish	479
	A.4.12.	Client.lookup	480
	A.4.13.	Client.unpublish	480
	A.4.14.	Client.spawn	481
	A.4.15.	Client.connect	481
	A.4.16.	Client.disconnect	482
	A.4.17.	Client.resolve_peers	482
	A.4.18.	Client.resolve_nodes	483
	Δ / 10	Client query	483

A.4.20.	Client.log	484
A.4.21.	Client.allocation_request	484
A.4.22.	Client.job_ctrl	485
A.4.23.	Client.monitor	485
A.4.24.	Client.get_credential	486
A.4.25.	Client.validate_credential	486
A.4.26.	Client.group_construct	487
A.4.27.	Client.group_invite	488
A.4.28.	Client.group_join	488
A.4.29.	Client.group_leave	489
A.4.30.	Client.group_destruct	489
A.4.31.	Client.register_event_handler	490
A.4.32.	Client.deregister_event_handler	490
A.4.33.	Client.notify_event	491
A.4.34.	Client.fabric_register	491
A.4.35.	Client.fabric_update	492
A.4.36.	Client.fabric_deregister	492
A.4.37.	Client.load_topology	492
A.4.38.	Client.get_relative_locality	493
A.4.39.	Client.get_cpuset	493
A.4.40.	Client.parse_cpuset_string	494
A.4.41.	Client.compute_distances	494
A.4.42.	Client.error_string	495
A.4.43.	Client.proc_state_string	495
A.4.44.	Client.scope_string	496
A.4.45.	Client.persistence_string	496
A.4.46.	Client.data_range_string	497
A.4.47.	Client.info_directives_string	497
A.4.48.	Client.data_type_string	497
A.4.49.	Client.alloc_directive_string	498
A.4.50.	Client.iof_channel_string	498
A.4.51.	Client.job_state_string	499
A.4.52.	Client.get_attribute_string	499

	A.4.53.	Client.get_attribute_name	499
	A.4.54.	Client.link_state_string	5 00
	A.4.55.	Client.device_type_string	5 00
	A.4.56.	Client.progress	501
A.5.	PMIxSe	rver	5 01
	A.5.1.	Server.init	501
	A.5.2.	Server.finalize	501
	A.5.3.	Server.generate_regex	502
	A.5.4.	Server.generate_ppn	502
	A.5.5.	Server.generate_locality_string	503
	A.5.6.	Server.generate_cpuset_string	503
	A.5.7.	Server.register_nspace	504
	A.5.8.	Server.deregister_nspace	504
	A.5.9.	Server.register_resources	505
	A.5.10.	Server.deregister_resources	505
	A.5.11.	Server.register_client	506
	A.5.12.	Server.deregister_client	506
	A.5.13.	Server.setup_fork	506
	A.5.14.	Server.dmodex_request	507
	A.5.15.	Server.setup_application	507
	A.5.16.	Server.register_attributes	508
	A.5.17.	Server.setup_local_support	508
	A.5.18.	Server.iof_deliver	509
	A.5.19.	Server.collect_inventory	509
	A.5.20.	Server.deliver_inventory	510
	A.5.21.	Server.define_process_set	510
	A.5.22.	Server.delete_process_set	511
4	A.5.23.	Server.register_resources	511
	A.5.24.	Server.deregister_resources	512
A.6.	PMIxTo	ol	512
	A.6.1.	Tool.init	512
	A.6.2.	Tool.finalize	513
	162	Tool disconnect	512

		A.6.4.	Tool.attach_to_server	514
		A.6.5.	Tool.get_servers	514
		A.6.6.	Tool.set_server	514
		A.6.7.	Tool.iof_pull	515
		A.6.8.	Tool.iof_deregister	516
		A.6.9.	Tool.iof_push	516
	A.7.	Example	le Usage	516
		A.7.1.	Python Client	517
		A.7.2.	Python Server	519
		_		
В.	Use-	Cases		523
	B.1.		ss Card Exchange for Process-to-Process Wire-up	
		B.1.1.	Use Case Summary	
		B.1.2.	Use Case Details	
	B.2.	Debugg	ging	527
		B.2.1.	Terminology	
		E	B.2.1.1. Tools vs Debuggers	
		E	B.2.1.2. Parallel Launching Methods	528
		F	B.2.1.3. Process Synchronization	528
		F	B.2.1.4. Process Acquisition	528
		B.2.2.	Use Case Details	528
		F	B.2.2.1. Direct-Launch Debugger Tool	528
		H	B.2.2.2. Indirect-Launch Debugger Tool	532
		F	B.2.2.3. Attaching to a Running Job	537
		I	B.2.2.4. Tool Interaction with RM	540
		E	B.2,2.5. Environmental Parameter Directives for Applications and Launche	ers542
	B.3.	Hybrid l	Programming Models	543
		B.3.1.	Use Case Summary	543
		B.3.2.	Use Case Details	543
		E	B.3.2.1. Identifying Active Programming Models	543
		E	B.3.2.2. Coordinating at Runtime	545
		E	B.3.2.3. Coordinating at Runtime with Multiple Event Handlers	547

C.	Revi	sion His	story	551
	C.1.	Version	1.0: June 12, 2015	551
	C.2.	Version	2.0: Sept. 2018	552
		C.2.1.	Removed/Modified Application Programming Interfaces (APIs)	552
		C.2.2.	Deprecated constants	552
		C.2.3.	Deprecated attributes	553
	C.3.	Version	2.1: Dec. 2018	553
	C.4.	Version	2.2: Jan 2019	554
	C.5.	Version	3.0: Dec. 2018	554
		C.5.1.	Removed constants	555
		C.5.2.	Deprecated attributes	555
		C.5.3.	Removed attributes	555
	C.6.	Version	3.1: Jan. 2019	556
	C.7.	Version	3.2: Oct. 2020	556
		C.7.1.	Deprecated constants	557
		C.7.2.	Deprecated attributes	558
	C.8.	Version	4.0: Dec. 2020	559
		C.8.1.	Added Constants	561
		C.8.2.	Added Attributes	564
		C.8.3.	Added Environmental Variables	577
		C.8.4.	Added Macros	577
		C.8.5.	Deprecated APIs	577
		C.8.6.	Deprecated constants	578
		C.8.7.	Removed constants	578
		C.8.8.	Deprecated attributes	579
		C.8.9.	Removed attributes	580
D.		owledg		582
	D.1.		4.0	582
	D.2.	*	3.0	583
	D.3.		2.0	584
	D.4.	Version	1.0	585
Bil	bliogr	aphy		587

ndex	588
ndex of APIs	590
ndex of Support Macros	598
ndex of Data Structures	602
ndex of Constants	604
ndex of Environmental Variables	613
ndex of Attributes	614

CHAPTER 1

Introduction

Process Management Interface - Exascale (PMIx) is an application programming interface standard that provides libraries and programming models with portable and well-defined access to commonly needed services in distributed and parallel computing systems. A typical example of such a service is the portable and scalable exchange of network addresses to establish communication channels between the processes of a parallel application or service. As such, PMIx gives distributed system software providers a better understanding of how programming models and libraries can interface with and use system-level services. As a standard, PMIx provides APIs that allow for portable access to these varied system software services and the functionalities they offer. Although these services can be defined and implemented directly by the system software components providing them, the community represented by the ASC feels that the development of a shared standard better serves the community. As a result, PMIx enables programming languages and libraries to focus on their core competencies without having to provide their own system-level services.

1.1 Background

The Process Management Interface (PMI) has been used for quite some time as a means of exchanging wireup information needed for inter-process communication. Two versions (PMI-1 and PMI-2 [2]) have been released as part of the MPICH effort, with PMI-2 demonstrating better scaling properties than its PMI-1 predecessor.

PMI-1 and PMI-2 can be implemented using PMIx though PMIx is not a strict superset of either. Since its introduction, PMIx has expanded on earlier PMI efforts by providing an extended version of the PMI APIs which provide necessary functionality for launching and managing parallel applications and tools at scale.

The increase in adoption has motivated the creation of this document to formally specify the intended behavior of the PMIx APIs.

More information about the PMIx standard and affiliated projects can be found at the PMIx web site: https://pmix.org

1.2 PMIx Architecture Overview

The presentation of the PMIx APIs within this document makes some basic assumptions about how these APIs are used and implemented. These assumptions are generally made only to simplify the presentation and explain PMIx with the expectation that most readers have similar concepts on how

computing systems are organized today. However, ultimately this document should only be assumed to define a set of APIs.

A concept that is fundamental to PMIx is that a PMIx implementation might operate primarily as a *messenger*, and not a *doer* — i.e., a PMIx implementation might rely heavily or fully on other software components to provide functionality [1]. Since a PMIx implementation might only deliver requests and responses to other software components, the API calls include ways to provide arbitrary information to the backend components that actually implement the functionality. Also, because PMIx implementations generally rely heavily on other system software, a PMIx implementation might not be able to guarantee that a feature is available on all platforms the implementation supports. These aspects are discussed in detail in the remainder of this chapter.




Figure 1.1.: PMIx-SMS Interactions

Fig. 1.1 shows a typical PMIx implementation in which the application is built against a PMIx client library that contains the client-side APIs, attribute definitions, and communication support for interacting with the local PMIx server. PMIx clients are processes which are started through the PMIx infrastructure, either by the PMIx implementation directly or through a System Management Software stack (SMS) component, and have registered as clients. A PMIx client is created in such a way that the PMIx client library will be have sufficient information available to authenticate with the PMIx server. The PMIx server will have sufficient knowledge about the process which it created, either directly or through other SMS, to authenticate the process and provide information the process requests such as its identity and the identity of its peers.

As clients invoke PMIx APIs, it is possible that some client requests can be handled at the client level. Other requests might require communication with the local PMIx server, which subsequently might request services from the host SMS (represented here by a Resource Manager (RM) daemon). The interaction between the PMIx server and SMS are achieved using callback functions registered during server initialization. The host SMS can indicate its lack of support for any

operation by simply providing a *NULL* for the associated callback function, or can create a function entry that returns *not supported* when called.

Recognizing the burden this places on SMS vendors, the PMIx community has included interfaces by which the host SMS (containing the local PMIx service instance) can request support from local SMS elements via the PMIx API. Once the SMS has transferred the request to an appropriate location, a PMIx server interface can be used to pass the request between SMS subsystems. For example, a request for network traffic statistics can utilize the PMIx networking abstractions to retrieve the information from the Fabric Manager. This reduces the portability and interoperability issues between the individual subsystems by transferring the burden of defining the interoperable interfaces from the SMS subsystems to the PMIx community, which continues to work with those providers to develop the necessary support.

Fig. 1.1 shows how tools can interact with the PMIx architecture. Tools, whether standalone or embedded in job scripts, are an exception to the normal client registration process. A process can register as a tool, provided the PMIx client library has adequate rendezvous information to connect to the appropriate PMIx server (either hosted on the local machine or on a remote machine). This allows processes which were not created by the PMIx infrastructure to request access to PMIx functionality.

1.3 Portability of Functionality

It is difficult to define a portable API that will provide access to the many and varied features underlying the operations for which PMIx provides access. For example, the options and features provided to request the creation of new processes varied dramatically between different systems existing at the time PMIx was introduced. Many RMs provide rich interfaces to specify the resources assigned to processes. As a result, PMIx is faced with the challenge of attempting to meet the seamingly conflicting goals of creating an API which allows access to these diverse features while being portable across a wide range of existing software environments. In addition, the functionalities required by different clients vary greatly. Producing a PMIx implementation which can provide the needs of all possible clients on all of its target systems could be so burdensome as to discourage PMIx implementations.

To help address this issue, the PMIx APIs are designed to allow resource managers and other system management stack components to decide on support of a particular function and allow client applications to query and adjust to the level of support available. PMIx clients should be written to account for the possibility that a PMIx API might return an error code indicating that the call is not supported. The PMIx community continues to look at ways to assist SMS implementers in their decisions on what functionality to support by highlighting functions and attributes that are critical to basic application execution (e.g., PMIx_Get) for certain classes of applications.

1.3.1 Attributes in PMIx

An area where differences between support on different systems can be challenging is regarding the attributes that provide information to the client process and/or control the behavior of a PMIx API.

1 M 2 ke 3 be

 Most PMIx API calls can accept additional information or attributes specified in the form of key/value pairs. These attributes provide information to the PMIx implementation that influence the behavior of the API call. In addition to API calls being optional, support for the individual attributes of an API call can vary between systems or implementations.

An application can adapt to the attribute support on a particular system in one of two ways. PMIx provides an API to enable an application to query the attributes supported by a particular API (See 5.6). Through this API, the PMIx implementation can provide detailed information about the attributes supported on a system for each API call queried. Alternatively, the application can mark attributes as required using a flag within the <code>pmix_info_t</code> (See 3.2.9). If the required attribute is not available on the system or the desired value for the attribute is not available, the call will return the error code for *not supported*.

For example, the **PMIX_TIMEOUT** attribute can be used to specify the time (in seconds) before the requested operation should time out. The intent of this attribute is to allow the client to avoid "hanging" in a request that takes longer than the client wishes to wait, or may never return (e.g., a **PMIX_Fence** that a blocked participant never enters).

The application can query the attribute support for **PMIx_Fence** and search whether **PMIX_TIMEOUT** is listed as a supported attribute. The application can also set the required flag in the **pmix_info_t** for that attribute when making the **PMIx_Fence** call. This will return an error if this attribute is not supported. If the required flag is not set, the library and SMS host are allowed to treat the attribute as optional, ignoring it if support is not available.

It is therefore critical that users and application implementers:

- a) consider whether or not a given attribute is required, marking it accordingly; and
- b) check the return status on all PMIx function calls to ensure support was present and that the request was accepted. Note that for non-blocking APIs, a return of **PMIX_SUCCESS** only indicates that the request had no obvious errors and is being processed the eventual callback will return the status of the requested operation itself.

PMIx clients (e.g., tools, parallel programming libraries) may find that they depend only on a small subset of interfaces and attributes to work correctly. PMIx clients are strongly advised to define a document itemizing the PMIx interfaces and associated attributes that are required for correct operation, and are optional but recommended for full functionality. The PMIx standard cannot define this list for all given PMIx clients, but such a list is valuable to RMs desiring to support these clients.

A PMIx implementation may be able to support only a subset of the PMIx API and attributes on a particular system due to either its own limitations or limitations of the SMS with which it interfaces. A PMIx implementation may also provide additional attributes beyond those defined herein in order to allow applications to access the full features of the underlying SMS. PMIx implementations are strongly advised to document the PMIx interfaces and associated attributes they support, with any annotations about behavior limitations. The PMIx standard cannot define this support for implementations, but such documentation is valuable to PMIx clients desiring to support a broad range of systems.

While a PMIx library implementer, or an SMS component server, may choose to support a particular PMIx API, they are not required to support every attribute that might apply to it. This would pose a significant barrier to entry for an implementer as there can be a broad range of applicable attributes to a given API, at least some of which may rarely be used.

Note that an environment that does not include support for a particular attribute/API pair is not "incomplete" or of lower quality than one that does include that support. Vendors must decide where to invest their time based on the needs of their target markets, and it is perfectly reasonable for them to perform cost/benefit decisions when considering what functions and attributes to support.

Attributes in this document are organized according to their primary usage, either grouped with a specific API or included in an appropriate functional chapter. Attributes in the PMIx Standard all start with "PMIX" in their name, and many include a functional description as part of their name (e.g., the use of "PMIX_FABRIC_" at the beginning of fabric-specific attributes). The PMIx Standard also defines an attribute that can be used to indicate that an attribute variable has not yet been set:

PMIX_ATTR_UNDEF "pmix.undef" (NULL)

A default attribute name signifying that the attribute field of a PMIx structure (e.g., a pmix_info_t) has not yet been defined.

CHAPTER 2

PMIx Terms and Conventions

In this chapter we describe some common terms and conventions used throughout this document. The PMIx Standard has adopted the widespread use of key-value *attributes* to add flexibility to the functionality expressed in the existing APIs. Accordingly, the ASC has chosen to require that the definition of each standard API include the passing of an array of attributes. These provide a means of customizing the behavior of the API as future needs emerge without having to alter or create new variants of it. In addition, attributes provide a mechanism by which researchers can easily explore new approaches to a given operation without having to modify the API itself.

In an effort to maintain long-term backward compatibility, PMIx does not include large numbers of APIs that each focus on a narrow scope of functionality, but instead relies on the definition of fewer generic APIs that include arrays of key-value attributes for "tuning" the function's behavior. Thus, modifications to the PMIx standard primarily consist of the definition of new attributes along with a description of the APIs to which they relate and the expected behavior when used with those APIs.

The following terminology is used throughout this document:

- session refers to a pool of resources with a unique identifier (a.k.a., the session ID) assigned by the WorkLoad Manager (WLM) that has been reserved for one or more users. Historically, High Performance Computing (HPC) sessions have consisted of a static allocation of resources e.g., a block of nodes assigned to a user in response to a specific request and managed as a unified collection. However, this is changing in response to the growing use of dynamic programming models that require on-the-fly allocation and release of system resources. Accordingly, the term session in this document refers to a potentially dynamic entity, perhaps comprised of resources accumulated as a result of multiple allocation requests that are managed as a single unit by the WLM.
- *job* refers to a set of one or more *applications* executed as a single invocation by the user within a session with a unique identifier (a.k.a, the *job ID*) assigned by the RM or launcher. For example, the command line "*mpiexec -n 1 app1 : -n 2 app2*" generates a single Multiple Program Multiple Data (MPMD) job containing two applications. A user may execute multiple *jobs* within a given session, either sequentially or in parallel.
- namespace refers to a character string value assigned by the RM or launcher (e.g., mpiexec) to a job. All applications executed as part of that job share the same namespace. The namespace assigned to each job must be unique within the scope of the governing RM and often is implemented as a string representation of a numerical job ID. The namespace and job terms will be used interchangeably throughout the document.
- application refers to a single executable (binary, script, etc.) member of a job.

- process refers to an operating system process, also commonly referred to as a heavyweight process. A process is often comprised of multiple lightweight threads, commonly known as simply threads.
 client refers to a process that was registered with the PMIx server prior to being started, and connects to that PMIx server via PMIx_Init using its assigned namespace and rank with the information required to connect to that server being provided to the process at time of start of
 - *clone* refers to a process that was directly started by a PMIx client (e.g., using *fork/exec*) and calls **PMIx_Init**, thus connecting to its local PMIx server using the same namespace and rank as its parent process.
 - rank refers to the numerical location (starting from zero) of a process within the defined scope. Thus, job rank is the rank of a process within its job and is synonymous with its unqualified rank, while application rank is the rank of that process within its application.
 - *peer* refers to another process within the same *job*.

 execution.

- workflow refers to an orchestrated execution plan frequently involving multiple jobs carried out under the control of a workflow manager process. An example workflow might first execute a computational job to generate the flow of liquid through a complex cavity, followed by a visualization job that takes the output of the first job as its input to produce an image output.
- *scheduler* refers to the component of the SMS responsible for scheduling of resource allocations. This is also generally referred to as the *system workflow manager* for the purposes of this document, the *WLM* acronym will be used interchangeably to refer to the scheduler.
- resource manager is used in a generic sense to represent the subsystem that will host the PMIx server library. This could be a vendor-supplied resource manager or a third-party agent such as a programming model's runtime library.
- *host environment* is used interchangeably with *resource manager* to refer to the process hosting the PMIx server library.
- *node* refers to a single operating system instance. Note that this may encompass one or more physical objects.
- package refers to a single object that is either soldered or connected to a printed circuit board via a mechanical socket. Packages may contain multiple chips that include (but are not limited to) processing units, memory, and peripheral interfaces.
- processing unit, or PU, is the electronic circuitry within a computer that executes instructions. Depending upon architecture and configuration settings, it may consist of a single hardware thread or multiple hardware threads collectively organized as a core.
- *fabric* is used in a generic sense to refer to the networks within the system regardless of speed or protocol. Any use of the term *network* in the document should be considered interchangeable with *fabric*.

- fabric device (or fabric devices) refers to an operating system fabric interface, which may be physical or virtual. Any use of the term Network Interface Card (NIC) in the document should be considered interchangeable with fabric device.
- fabric plane refers to a collection of fabric devices in a common logical or physical configuration. Fabric planes are often implemented in HPC clusters as separate overlay or physical networks controlled by a dedicated fabric manager.
- attribute refers to a key-value pair comprised of a string key (represented by a pmix key t structure) and an associated value containing a PMIx data type (e.g., boolean, integer, or a more complex PMIx structure). Attributes are used both as directives when passed as qualifiers to APIs (e.g., in a pmix_info_t array), and to identify the contents of information (e.g., to specify that the contents of the corresponding pmix_value_t in a pmix_info_t represent the PMIX UNIV SIZE).
- key refers to the string component of a defined attribute. The PMIx Standard will often refer to passing of a key to an API (e.g., to the PMIx Query info or PMIx Get APIs) as a means of identifying requested information. In this context, the data type specified in the attribute's definition indicates the data type the caller should expect to receive in return. Note that not all attributes can be used as keys as some have specific uses solely as API qualifiers.
- instant on refers to a PMIx concept defined as: "All information required for setup and communication (including the address vector of endpoints for every process) is available to each process at start of execution"

The following sections provide an overview of the conventions used throughout the PMIx Standard document.

Notational Conventions 2.1

24	Some sections of this document describe programming language specific examples or APIs. Text
25	that applies only to programs for which the base language is C is shown as follows:
	C
26	C specific text
27	<pre>int foo = 42;</pre>
	C —
28	Some text is for information only, and is not part of the normative specification. These take several
29	forms, described in their examples below:
30	Note: General text

1 2

3 4

5

6 7

8

9

10

11 12

13

14

15 16

17 18

19

20 21

22

----- Rationale -Throughout this document, the rationale for the design choices made in the interface specification is 1 2 set off in this section. Some readers may wish to skip these sections, while readers interested in interface design may want to read them carefully. 3 Advice to users 4 Throughout this document, material aimed at users and that illustrates usage is set off in this section. Some readers may wish to skip these sections, while readers interested in programming 5 6 with the PMIx API may want to read them carefully. Advice to PMIx library implementers -7 Throughout this document, material that is primarily commentary to PMIx library implementers is 8 set off in this section. Some readers may wish to skip these sections, while readers interested in 9 PMIx implementations may want to read them carefully. Advice to PMIx server hosts -Throughout this document, material that is primarily commentary aimed at host environments (e.g., 10 11 RMs and RunTime Environments (RTEs)) providing support for the PMIx server library is set off in 12 this section. Some readers may wish to skip these sections, while readers interested in integrating PMIx servers into their environment may want to read them carefully. 13 Attributes added in this version of the standard are shown in *magenta* to distinguish them from 14 15 those defined in prior versions, which are shown in **black**. Deprecated attributes are shown in green 16 and may be removed in a future version of the standard. 2.2 **Semantics** 18 The following terms will be taken to mean: 19 • shall, must and will indicate that the specified behavior is required of all conforming implementations 20 21 • should and may indicate behaviors that a complete implementation would include, but are not 22 required of all conforming implementations

2.3 Naming Conventions

- 2 The PMIx standard has adopted the following conventions:
 - PMIx constants and attributes are prefixed with **PMIX**.
 - Structures and type definitions are prefixed with pmix.
 - Underscores are used to separate words in a function or variable name.
 - Lowercase letters are used in PMIx client APIs except for the PMIx prefix (noted below) and the first letter of the word following it. For example, **PMIx_Get_version**.
 - PMIx server and tool APIs are all lower case letters following the prefix e.g.,
 PMIx_server_register_nspace.
 - The **PMIx** prefix is used to denote functions.
 - The pmix_ prefix is used to denote function pointer and type definitions.
 - Users should not use the "PMIX", "PMIx", or "pmix" prefixes in their applications or libraries so as to avoid symbol conflicts with current and later versions of the PMIx Standard.

4 2.4 Procedure Conventions

While the current APIs are based on the C programming language, it is not the intent of the PMIx Standard to preclude the use of other languages. Accordingly, the procedure specifications in the PMIx Standard are written in a language-independent syntax with the arguments marked as IN, OUT, or INOUT. The meanings of these are:

- IN: The call may use the input value but does not update the argument from the perspective of the caller at any time during the calls execution,
- OUT: The call may update the argument but does not use its input value
- INOUT: The call may both use and update the argument.

Many PMIx interfaces, particularly nonblocking interfaces, use a (void*) callback data object passed to the function that is then passed to the associated callback. On the client side, the callback data object is an opaque, client-provided context that the client can pass to a non-blocking call. When the nonblocking call completes, the callback data object is passed back to the client without modification by the PMIx library, thus allowing the client to associate a context with that callback. This is useful if there are many outstanding nonblocking calls.

A similar model is used for the server module functions (see 16.3.1). In this case, the PMIx library is making an upcall into its host via the PMIx server module callback function and passing a specific callback function pointer and callback data object. The PMIx library expects the host to call the cbfunc with the necessary arguments and pass back the original callback data obect upon completing the operation. This gives the server-side PMIx library the ability to associate a context

with the call back (since multiple operations may be outstanding). The host has no visibility into the contents of the callback data object object, nor is permitted to alter it in any way.

1



CHAPTER 3

Data Structures and Types

This chapter defines PMIx standard data structures (along with macros for convenient use), types, and constants. These apply to all consumers of the PMIx interface. Where necessary for clarification, the description of, for example, an attribute may be copied from this chapter into a section where it is used.

A PMIx implementation may define additional attributes beyond those specified in this document.

Advice to PMIx library implementers –

Structures, types, and macros in the PMIx Standard are defined in terms of the C-programming language. Implementers wishing to support other languages should provide the equivalent definitions in a language-appropriate manner.

If a PMIx implementation chooses to define additional attributes they should avoid using the "PMIX" prefix in their name or starting the attribute string with a "pmix" prefix. This helps the end user distinguish between what is defined by the PMIx standard and what is specific to that PMIx implementation, and avoids potential conflicts with attributes defined by the Standard.

Advice to users -

Use of increment/decrement operations on indices inside PMIx macros is discouraged due to unpredictable behavior. For example, the following sequence:

```
PMIX_INFO_LOAD(&array[n++], "mykey", &mystring, PMIX_STRING);
PMIX_INFO_LOAD(&array[n++], "mykey2", &myint, PMIX_INT);
```

will load the given key-values into incorrect locations if the macro is implemented as:

```
define PMIX_INFO_LOAD(m, k, v, t)
    do {
        if (NULL != (k)) {
            pmix_strncpy((m)->key, (k), PMIX_MAX_KEYLEN);
        }
        (m)->flags = 0;
        pmix_value_load(&((m)->value), (v), (t));
    } while (0)
```

since the index is cited more than once in the macro. The PMIx standard only governs the existence and syntax of macros - it does not specify their implementation. Given the freedom of implementation, a safer call sequence might be as follows:

Users are also advised to use the macros for creating, loading, and releasing PMIx structures to avoid potential issues with release of memory. For example, pointing a <code>pmix_envar_t</code> element at a static string variable and then using <code>PMIX_ENVAR_DESTRUCT</code> to clear it would generate an error as the static string had not been allocated.

3.1 Constants

PMIx defines a few values that are used throughout the standard to set the size of fixed arrays or as a means of identifying values with special meaning. The community makes every attempt to minimize the number of such definitions. The constants defined in this section may be used before calling any PMIx library initialization routine. Additional constants associated with specific data structures or types are defined in the section describing that data structure or type.

PMIX_MAX_NSLEN Maximum namespace string length as an integer.

Advice to PMIx library implementers

PMIX_MAX_NSLEN should have a minimum value of 63 characters. Namespace arrays in PMIx defined structures must reserve a space of size **PMIX_MAX_NSLEN+1** to allow room for the **NULL** terminator

PMIX_MAX_KEYLEN Maximum key string length as an integer.

Advice to PMIx library implementers -

PMIX_MAX_KEYLEN should have a minimum value of 63 characters. Key arrays in PMIx defined structures must reserve a space of size **PMIX_MAX_KEYLEN**+1 to allow room for the **NULL** terminator

PMIX_APP_WILDCARD A value to indicate that the user wants the data for the given key from every application that posted that key, or that the given value applies to all applications within the given namespace.

3.1.1 PMIx Return Status Constants

 The pmix_status_t structure is an int type for return status. The tables shown in this section define the possible values for pmix_status_t. PMIx errors are required to always be negative, with 0 reserved for PMIX_SUCCESS. Values in the list that were deprecated in later standards are denoted as such. Values added to the list in this version of the standard are shown in magenta.

- Advice to PMIx library implementers -

A PMIx implementation must define all of the constants defined in this section, even if they will never return the specific value to the caller.

Advice to users

Other than **PMIX_SUCCESS** (which is required to be zero), the actual value of any PMIx error constant is left to the PMIx library implementer. Thus, users are advised to always refer to constant by name, and not a specific implementation's value, for portability between implementations and compatibility across library versions.

The following values are general constants used in a variety of places.

PMIX SUCCESS Success.

PMIX ERROR General Error.

PMIX_ERR_EXISTS Requested operation would overwrite an existing value - typically returned when an operation would overwrite an existing file or directory.

PMIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a *scope* (see Section 7.1.1.1) that does not include the requester

PMIX_ERR_INVALID_CRED Invalid security credentials.

PMIX_ERR_WOULD_BLOCK Operation would block.

PMIX_ERR_UNKNOWN_DATA_TYPE The data type specified in an input to the PMIx library is not recognized by the implementation.

PMIX_ERR_TYPE_MISMATCH The data type found in an object does not match the expected data type as specified in the API call - e.g., a request to unpack a **PMIX_BOOL** value from a buffer that does not contain a value of that type in the current unpack location.

PMIX_ERR_UNPACK_INADEQUATE_SPACE Inadequate space to unpack data - the number of values in the buffer exceeds the specified number to unpack.

PMIX_ERR_UNPACK_READ_PAST_END_OF_BUFFER Unpacking past the end of the provided buffer - the number of values in the buffer is less than the specified number to unpack, or a request was made to unpack a buffer beyond the buffer's end.

PMIX ERR UNPACK FAILURE The unpack operation failed for an unspecified reason.

PMIX ERR PACK FAILURE The pack operation failed for an unspecified reason.

PMIX_ERR_NO_PERMISSIONS The user lacks permissions to execute the specified operation.

PMIX ERR TIMEOUT Either a user-specified or system-internal timeout expired.

1 The specified target server or client process is not reachable - i.e., a PMIX_ERR_UNREACH 2 suitable connection either has not been or can not be made. PMIX ERR BAD PARAM 3 One or more incorrect parameters (e.g., passing an attribute with a 4 value of the wrong type), or multiple parameters containing conflicting directives (e.g., 5 multiple instances of the same attribute with different values, or different attributes specifying 6 conflicting behaviors), were passed to a PMIx API. PMIX ERR RESOURCE BUSY 7 Resource busy - typically seen when an attempt to establish a connection to another process (e.g., a PMIx server) cannot be made due to a communication 8 9 failure. PMIX_ERR_OUT_OF_RESOURCE Resource exhausted. 10 PMIX ERR INIT Error during initialization. 11 PMIX ERR NOMEM 12 Out of memory. 13 PMIX ERR NOT FOUND The requested information was not found. PMIX ERR NOT SUPPORTED The requested operation is not supported by either the PMIx 14 15 implementation or the host environment. PMIX ERR PARAM VALUE NOT SUPPORTED The requested operation is supported by the 16 PMIx implementation and (if applicable) the host environment. However, at least one 17 supplied parameter was given an unsupported value, and the operation cannot therefore be 18 executed as requested. 19 20 PMIX ERR COMM FAILURE Communication failure - a message failed to be sent or received, but the connection remains intact. 21 PMIX_ERR_LOST_CONNECTION Lost connection between server and client or tool. 22 23 PMIX ERR INVALID OPERATION The requested operation is supported by the 24 implementation and host environment, but fails to meet a requirement (e.g., requesting to 25 disconnect from processes without first connecting to them, inclusion of conflicting directives, or a request to perform an operation that conflicts with an ongoing one). 26 PMIX OPERATION IN PROGRESS A requested operation is already in progress - the 27 28 duplicate request shall therefore be ignored. PMIX OPERATION SUCCEEDED The requested operation was performed atomically - no 29 30 callback function will be executed. PMIX ERR PARTIAL SUCCESS The operation is considered successful but not all elements 31 32 of the operation were concluded (e.g., some members of a group construct operation chose 33 not to participate). 3.1.1.1 User-Defined Error and Event Constants 34 PMIx establishes a boundary for constants defined in the PMIx standard. Negative values larger 35 (i.e., more negative) than this (and any positive values greater than zero) are guaranteed not to 36 conflict with PMIx values. 37 38 PMIX EXTERNAL ERR BASE A starting point for user-level defined error and event constants. Negative values that are more negative than the defined constant are guaranteed not 39 40 to conflict with PMIx values. Definitions should always be based on the PMIX EXTERNAL ERR BASE constant and not a specific value as the value of the constant 41 may change. 42

3.2 Data Types

2 This section defines various data types used by the PMIx APIs. The version of the standard in 3 which a particular data type was introduced is shown in the margin. 3.2.1 **Key Structure** 5 The pmix_key_t structure is a statically defined character array of length 6 PMIX_MAX_KEYLEN+1, thus supporting keys of maximum length PMIX_MAX_KEYLEN while 7 preserving space for a mandatory **NULL** terminator. PMIx v2.0 8 typedef char pmix_key_t[PMIX_MAX_KEYLEN+1]; Characters in the key must be standard alphanumeric values supported by common utilities such as 9 10 strcmp. Advice to users 11 References to keys in PMIx v1 were defined simply as an array of characters of size 12 **PMIX MAX KEYLEN+1.** The **pmix key t** type definition was introduced in version 2 of the 13 standard. The two definitions are code-compatible and thus do not represent a break in backward 14 compatibility. 15 Passing a pmix_key_t value to the standard size of utility can result in compiler warnings of incorrect returned value. Users are advised to avoid using sizeof(pmix_key_t) and instead rely on 16 17 the PMIX_MAX_KEYLEN constant. 3.2.1.1 **Key support macros** The following macros are provided for convenience when working with PMIx keys. 19 Check key macro 20 Compare the key in a **pmix_info_t** to a given value. 21 PMIx v3.0 22 PMIX_CHECK_KEY(a, b) IN 23 Pointer to the structure whose key is to be checked (pointer to pmix info t) 24 IN 25

String value to be compared against (char*)

Returns **true** if the key matches the given value

1		Check reserved key macro
2		Check if the given key is a PMIx <i>reserved</i> key as described in Chapter 6.
	PMIx v4.0	C
3		PMIX_CHECK_RESERVED_KEY(a)
Ü		C
4		IN a
5		String value to be checked (char*)
6		Returns true if the key is reserved by the Standard.
7		Load key macro
8		Load a key into a pmix_info_t.
Ü		Load a key into a pairx_into_c.
	<i>PMIx v4.0</i>	
9		PMIX_LOAD_KEY(a, b)
		C
10		IN a
11		Pointer to the structure whose key is to be loaded (pointer to pmix_info_t)
12		IN b
13		String value to be loaded (char*)
14		No return value.
	200	Namaanaa Churchuu
15	3.2.2	Namespace Structure
16		The pmix_nspace_t structure is a statically defined character array of length
17		PMIX_MAX_NSLEN+1, thus supporting namespaces of maximum length PMIX_MAX_NSLEN
18		while preserving space for a mandatory NULL terminator.
	PMIx v2.0	C
19		<pre>typedef char pmix_nspace_t[PMIX_MAX_NSLEN+1];</pre>
		cypeact char phant_hepace_o[thini_thin_heat.]/
20		Characters in the namespace must be standard alphanumeric values supported by common utilities
21		such as stremp.

		Advice to users
1 2 3 4		References to namespace values in PMIx v1 were defined simply as an array of characters of size PMIX_MAX_NSLEN+1 . The pmix_nspace_t type definition was introduced in version 2 of the standard. The two definitions are code-compatible and thus do not represent a break in backward compatibility.
5 6 7		Passing a pmix_nspace_t value to the standard <i>sizeof</i> utility can result in compiler warnings of incorrect returned value. Users are advised to avoid using <i>sizeof(pmix_nspace_t)</i> and instead rely on the PMIX_MAX_NSLEN constant.
8	3.2.2.1	Namespace support macros
9 10		The following macros are provided for convenience when working with PMIx namespace structures.
11 12		Check namespace macro Compare the string in a pmix_nspace_t to a given value.
	PMIx v3.0	
13		PMIX_CHECK_NSPACE(a, b)
14		IN a
15		Pointer to the structure whose value is to be checked (pointer to pmix_nspace_t)
16		IN b
17		String value to be compared against (char*)
18		Returns true if the namespace matches the given value
19		Load namespace macro
20		Load a namespace into a pmix_nspace_t.
	PMIx v4.0	C
21		PMIX_LOAD_NSPACE(a, b)
		C
22		IN a
23		Pointer to the target structure (pointer to pmix_nspace_t)
24		IN b
25		String value to be loaded - if NULL is given, then the target structure will be initialized to
26		zero's (char*)

No return value.

1 3.2.3 Rank Structure

2		The pmix_rank_t structure is a uint32_t type for rank values.
	PMIx v1.0	<u> </u>
3		<pre>typedef uint32_t pmix_rank_t;</pre>
4 5 6		The following constants can be used to set a variable of the type <code>pmix_rank_t</code> . All definitions were introduced in version 1 of the standard unless otherwise marked. Valid rank values start at zero.
7 8 9 10		<pre>PMIX_RANK_UNDEF</pre>
11 12 13 14		from every rank that posted that key. PMIX_RANK_LOCAL_NODE Special rank value used to define groups of ranks. This constant defines the group of all ranks on a local node. PMIX_RANK_LOCAL_PEERS Special rank value used to define groups of ranks. This
15 16 17		constant defines the group of all ranks on a local node within the same namespace as the current process. PMIX_RANK_INVALID An invalid rank value.
18		PMIX_RANK_VALID Define an upper boundary for valid rank values.
19	3.2.3.1	Rank support macros
20		The following macros are provided for convenience when working with PMIx ranks.
21 22	PMIx v4.0	Check rank macro Check two ranks for equality, taking into account wildcard values C
23		PMIX_CHECK_RANK(a, b)
24 25 26 27	, 4	IN a Rank to be checked (pmix_rank_t) IN b Rank to be checked (pmix_rank_t)
28		Returns true if the ranks are equal, or at least one of the ranks is PMIX_RANK_WILDCARD

3.2.4 Process Structure

```
2
               The pmix proc t structure is used to identify a single process in the PMIx universe. It contains
 3
               a reference to the namespace and the pmix_rank_t within that namespace.
   PMIx v1.0
 4
               typedef struct pmix_proc {
 5
                     pmix_nspace_t nspace;
 6
                     pmix_rank_t rank;
 7
                } pmix_proc_t;
    3.2.4.1
               Process structure support macros
 9
               The following macros are provided to support the pmix_proc_t structure.
               Initialize the proc structure
10
11
               Initialize the pmix_proc_t fields.
   PMIx v1.0
12
               PMIX_PROC_CONSTRUCT (m)
13
               IN
                    Pointer to the structure to be initialized (pointer to pmix_proc_t)
14
15
               Destruct the proc structure
16
               Destruct the pmix_proc_t fields.
17
               PMIX_PROC_DESTRUCT (m)
18
               IN
                    Pointer to the structure to be destructed (pointer to pmix_proc_t)
19
20
               There is nothing to release here as the fields in pmix_proc_t are either a statically-declared array
               (the namespace) or a single value (the rank). However, the macro is provided for symmetry in the
21
22
               code and for future-proofing should some allocated field be included some day.
```

1		Create a proc array
2		Allocate and initialize an array of pmix_proc_t structures.
	<i>PMIx v1.0</i>	<u> </u>
3		PMIX_PROC_CREATE (m, n)
4		INOUT m
5		Address where the pointer to the array of pmix_proc_t structures shall be stored (handle)
6		IN n
7		Number of structures to be allocated (size_t)
_		
8		Free a proc structure
9		Release a pmix_proc_t structure.
	PMIx v4.0	C -
10		PMIX_PROC_RELEASE (m)
		C
11		IN m
12		Pointer to a pmix_proc_t structure (handle)
13		Free a proc array
14		Release an array of pmix_proc_t structures.
17		Release an array of parts_proc_c structures.
	<i>PMIx v1.0</i>	
15		PMIX_PROC_FREE(m, n)
		C
40		IN m
16 17		
18		Pointer to the array of pmix_proc_t structures (handle) IN n
19		Number of structures in the array (size_t)
19		Number of structures in the array (SIZE_C)
20		Load a proc structure
21		Load values into a pmix_proc_t.
	PMIx v2.0	

```
1
               PMIX PROC LOAD (m, n, r)
               IN
 2
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
 3
               IN
 4
 5
                    Namespace to be loaded (pmix_nspace_t)
               IN
 6
 7
                    Rank to be assigned (pmix_rank_t)
               No return value. Deprecated in favor of PMIX_LOAD_PROCID
 8
               Compare identifiers
 9
               Compare two pmix_proc_t identifiers.
10
   PMIx v3.0
11
               PMIX CHECK PROCID(a, b)
               IN
12
13
                    Pointer to a structure whose ID is to be compared (pointer to pmix_proc_t)
               IN
14
                    Pointer to a structure whose ID is to be compared (pointer to pmix_proc_t)
15
16
               Returns true if the two structures contain matching namespaces and:
17
               • the ranks are the same value
               • one of the ranks is PMIX_RANK_WILDCARD
18
               Load a procID structure
19
               Load values into a pmix proc t.
20
   PMIx v4.0
21
               PMIX_LOAD_PROCID(m, n, r)
               IN
22
23
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
24
               IN
25
                    Namespace to be loaded (pmix_nspace_t)
26
               IN
27
                    Rank to be assigned (pmix_rank_t)
```

Construct a multi-cluster namespace 1 Construct a multi-cluster identifier containing a cluster ID and a namespace. 2 PMIx v4.0 3 PMIX MULTICLUSTER NSPACE CONSTRUCT (m, n, r) IN 4 pmix_nspace_t structure that will contain the multi-cluster identifier (pmix_nspace_t) 5 6 IN 7 Cluster identifier (char*) 8 IN 9 Namespace to be loaded (pmix_nspace_t) Combined length of the cluster identifier and namespace must be less than PMIX MAX NSLEN-2. 10 Parse a multi-cluster namespace 11 Parse a multi-cluster identifier into its cluster ID and namespace parts. 12 PMIx v4.013 PMIX_MULTICLUSTER_NSPACE_PARSE(m, n, r) 14 IN pmix_nspace_t structure containing the multi-cluster identifier (pointer to 15 16 pmix_nspace_t) IN 17 18 Location where the cluster ID is to be stored (pmix nspace t) IN 19 Location where the namespace is to be stored (pmix_nspace_t) 20 3.2.5 **Process State Structure** The pmix_proc_state_t structure is a uint8_t type for process state values. The following 22 PMIx v2.023 constants can be used to set a variable of the type pmix_proc_state_t. Advice to users 24 The fine-grained nature of the following constants may exceed the ability of an RM to provide 25 updated process state values during the process lifetime. This is particularly true of states for short-lived processes. 26

```
Undefined process state.
 1
               PMIX_PROC_STATE_UNDEF
 2
               PMIX_PROC_STATE_PREPPED
                                                Process is ready to be launched.
 3
               PMIX_PROC_STATE_LAUNCH_UNDERWAY
                                                          Process launch is underway.
                                                Process is ready for restart.
 4
               PMIX PROC STATE RESTART
 5
               PMIX PROC STATE TERMINATE
                                                   Process is marked for termination.
                                                Process has been locally fork'ed by the RM.
 6
               PMIX PROC STATE RUNNING
 7
               PMIX PROC STATE CONNECTED
                                                   Process has connected to PMIx server.
                                                      Define a "boundary" between the terminated states
8
               PMIX_PROC_STATE_UNTERMINATED
9
                   and PMIX_PROC_STATE_CONNECTED so users can easily and quickly determine if a
10
                   process is still running or not. Any value less than this constant means that the process has not
11
                   terminated.
                                                    Process has terminated and is no longer running.
12
               PMIX PROC STATE TERMINATED
               PMIX_PROC_STATE_ERROR
                                             Define a boundary so users can easily and quickly determine if
13
14
                   a process abnormally terminated. Any value above this constant means that the process has
15
                   terminated abnormally.
16
               PMIX_PROC_STATE_KILLED_BY_CMD
                                                        Process was killed by a command.
                                                Process was aborted by a call to PMIx_Abort.
               PMIX_PROC_STATE_ABORTED
17
                                                          Process failed to start.
18
               PMIX_PROC_STATE_FAILED_TO_START
19
               PMIX PROC STATE ABORTED BY SIG
                                                         Process aborted by a signal.
               PMIX PROC STATE TERM WO SYNC
                                                      Process exited without calling PMIx Finalize.
20
                                                     Process communication has failed.
21
               PMIX_PROC_STATE_COMM_FAILED
22
               PMIX_PROC_STATE_SENSOR_BOUND_EXCEEDED
                                                                  Process exceeded a specified sensor
23
                   limit.
24
               PMIX_PROC_STATE_CALLED_ABORT
                                                      Process called PMIx Abort.
               PMIX_PROC_STATE_HEARTBEAT_FAILED
                                                            Frocess failed to send heartbeat within
25
26
                   specified time limit.
                                                  Process failed and is waiting for resources before
27
               PMIX_PROC_STATE_MIGRATING
28
                   restarting.
               PMIX_PROC_STATE_CANNOT_RESTART
                                                         Process failed and cannot be restarted.
29
30
               PMIX PROC STATE TERM NON ZERO
                                                        Process exited with a non-zero status.
31
               PMIX PROC STATE FAILED TO LAUNCH
                                                            Unable to launch process.
```

3.2.6 Process Information Structure

The **pmix_proc_info_t** structure defines a set of information about a specific process including it's name, location, and state.

PMIx v2.0

33

```
1
             typedef struct pmix proc info {
 2
                  /** Process structure */
 3
                  pmix_proc_t proc;
                  /** Hostname where process resides */
                  char *hostname;
 5
6
                  /** Name of the executable */
 7
                  char *executable name;
8
                  /** Process ID on the host */
9
                  pid_t pid;
10
                  /** Exit code of the process. Default: 0 */
                  int exit code;
11
                  /** Current state of the process */
12
13
                  pmix_proc_state_t state;
              } pmix_proc_info_t;
14
   3.2.6.1
             Process information structure support macros
             The following macros are provided to support the pmix_proc_info_t structure.
16
             Initialize the process information structure
17
             Initialize the pmix_proc_info_t fields.
18
   PMIx v2.0
19
             PMIX PROC INFO CONSTRUCT (m)
             IN
20
21
                 Pointer to the structure to be initialized (pointer to pmix_proc_info_t)
             Destruct the process information structure
22
23
             Destruct the pmix_proc_info_t fields.
   PMIx v2.0
             PMIX_PROC_INFO_DESTRUCT (m)
24
25
26
                  Pointer to the structure to be destructed (pointer to pmix proc info t)
```

1	Create a process information array
2	Allocate and initialize a pmix_proc_info_t array.
PMIx v2.0	▼ C
	DMIN DDOG INEO CDEAME ()
3	PMIX_PROC_INFO_CREATE(m, n)
4	INOUT m
5	Address where the pointer to the array of pmix_proc_info_t structures shall be stored
6	(handle)
7	IN n
8	Number of structures to be allocated (size_t)
9	Free a process information structure
10	Release a pmix_proc_info_t structure.
PMIx v2.0	C
11	PMIX_PROC_INFO_RELEASE (m)
• •	FMIX_FROC_INFO_REDEASE (III)
12	IN m
13	Pointer to a pmix_proc_info_t structure (handle)
14	Free a process information array
15	Release an array of pmix_proc_info_t structures.
PMIx v2.0	C
16	PMIX_PROC_INFO_FREE(m, n)
17	IN m
18	Pointer to the array of <pre>pmix_proc_info_t</pre> structures (handle)
19	IN n
20	Number of structures in the array (size_t)

3.2.7 Job State Structure

The pmix_job_state_t structure is a uint8_t type for job state values. The following 2 PMIx v4.0constants can be used to set a variable of the type **pmix_job_state_t**.

Advice to users

The fine-grained nature of the following constants may exceed the ability of an RM to provide updated job state values during the job lifetime. This is particularly true for short-lived jobs.

```
4
 5
 6
               PMIX_JOB_STATE_UNDEF
                                               Undefined job state.
 7
                                                           Job is waiting for resources to be allocated to it.
               PMIX_JOB_STATE_AWAITING_ALLOC
                                                            Job launch is underway.
 8
               PMIX_JOB_STATE_LAUNCH_UNDERWAY
 9
                                                 All processes in the job have been spawned and are executing.
               PMIX JOB STATE RUNNING
10
               PMIX JOB STATE SUSPENDED
                                                    All processes in the job have been suspended.
               PMIX JOB STATE CONNECTED
                                                    All processes in the job have connected to their PMIx
11
12
                    server.
13
               PMIX JOB STATE UNTERMINATED
                                                        Define a "boundary" between the terminated states
14
                    and PMIX JOB STATE TERMINATED so users can easily and quickly determine if a job is
15
                    still running or not. Any value less than this constant means that the job has not terminated.
               PMIX JOB STATE TERMINATED
                                                     All processes in the job have terminated and are no
16
                    longer running - typically will be accompanied by the job exit status in response to a query.
17
18
               PMIX JOB STATE TERMINATED WITH ERROR Define a boundary so users can easily
                    and quickly determine if a job abnormally terminated - typically will be accompanied by a
19
20
                    job-related error code in response to a query Any value above this constant means that the job
21
                    terminated abnormally.
```

Value Structure 3.2.8

The pmix value t structure is used to represent the value passed to PMIx Put and retrieved by **PMIx** Get, as well as many of the other PMIx functions.

A collection of values may be specified under a single key by passing a pmix_value_t containing an array of type pmix data array t, with each array element containing its own object. All members shown below were introduced in version 1 of the standard unless otherwise marked.

PMIx v1.0

23

24

25

26

27

```
1
            typedef struct pmix value {
2
                pmix_data_type_t type;
3
                union {
4
                    bool flag;
5
                    uint8_t byte;
6
                    char *string;
7
                    size t size;
8
                    pid_t pid;
9
                     int integer;
10
                     int8_t int8;
                     int16 t int16;
11
12
                     int32 t int32;
13
                    int64 t int64;
14
                    unsigned int uint;
15
                    uint8 t uint8;
16
                    uint16 t uint16;
17
                    uint32 t uint32;
18
                    uint64 t uint64;
19
                     float fval:
20
                    double dval;
21
                    struct timeval tv;
22
                    time t time; // version 2.0
23
                    pmix_status_t status; // version 2.0
24
                    pmix_rank_t rank; // version 2.0
                    pmix_proc_t *proc; // version 2.0
25
26
                    pmix_byte_object_t bo;
27
                    pmix_persistence_t persist; // version 2.0
                    pmix_scope_t scope; // version 2.0
28
29
                    pmix_data_range_t range; // version 2.0
                    pmix_proc_state_t state; // version 2.0
30
                    pmix_proc_info_t *pinfo; // version 2.0
31
32
                    pmix_data_array_t *darray; // version 2.0
33
                    void *ptr; // version 2.0
34
                    pmix_alloc_directive_t adir; // version 2.0
35
                } data;
36
              pmix value t;
```

3.2.8.1 Value structure support macros

The following macros are provided to support the **pmix_value_t** structure.

1	Initialize the value structure
2 PMIx v.	Initialize the pmix_value_t fields.
3	PMIX_VALUE_CONSTRUCT (m)
4 5	<pre>IN m Pointer to the structure to be initialized (pointer to pmix_value_t)</pre>
6 7	Destruct the value structure Destruct the pmix_value_t fields.
PMIx v.	PMIX_VALUE_DESTRUCT (m)
9 10	IN m Pointer to the structure to be destructed (pointer to pmix_value_t)
11 12	Create a value array Allocate and initialize an array of pmix_value_t structures.
<i>PMIx v</i> .	PMIX_VALUE_CREATE(m, n)
14 15 16 17	INOUT m Address where the pointer to the array of pmix_value_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)
18 19	Free a value structure Release a pmix_value_t structure.
<i>PMIx v</i> ₄ 20	PMIX_VALUE_RELEASE (m)
21 22	IN m Pointer to a pmix_value_t structure (handle)

1 2	Free a value array
_	Release an array of pmix_value_t structures.
<i>PMIx v1.0</i>	PMIX_VALUE_FREE (m, n)
4 5 6	<pre>IN m Pointer to the array of pmix_value_t structures (handle) IN n Number of structures in the energy (air a. t.)</pre>
8 9	Number of structures in the array (size_t) Load a value structure Load data into a pmix_value_t structure.
<i>PMIx v2.0</i> 10	PMIX_VALUE_LOAD(v, d, t);
11 12	IN v The pmix_value_t into which the data is to be loaded (pointer to pmix_value_t)
13 14	IN d Pointer to the data value to be loaded (handle)
15 16	IN t Type of the provided data value (pmix_data_type_t)
17 18	This macro simplifies the loading of data into a pmix_value_t by correctly assigning values to the structure's fields. Advice to users
19 20	The data will be copied into the <code>pmix_value_t</code> - thus, any data stored in the source value can be modified or free'd without affecting the copied data once the macro has completed.

```
Unload a value structure
 1
 2
               Unload data from a pmix value t structure.
   PMIx v2.2
 3
               PMIX VALUE UNLOAD (r, v, d, t);
               OUT r
 4
 5
                    Status code indicating result of the operation pmix_status_t
 6
               IN
 7
                    The pmix_value_t from which the data is to be unloaded (pointer to pmix_value_t)
 8
               INOUT d
 9
                    Pointer to the location where the data value is to be returned (handle)
10
               INOUT t
                    Pointer to return the data type of the unloaded value (handle)
11
               This macro simplifies the unloading of data from a pmix value t.
12
                                                   Advice to users
               Memory will be allocated and the data will be in the pmix_value_t returned - the source
13
14
               pmix value t will not be altered.
               Transfer data between value structures
15
               Transfer the data value between two pmix_value_t structures.
16
   PMIx v2.0
               PMIX_VALUE_XFER(r, d, s);
17
18
               OUT r
                    Status code indicating success or failure of the transfer (pmix status t)
19
               IN
20
                    Pointer to the pmix_value_t destination (handle)
21
22
               IN
                    Pointer to the pmix_value_t source (handle)
23
24
               This macro simplifies the transfer of data between two pmix_value_t structures, ensuring that
               all fields are properly copied.
25
                                                   Advice to users
26
                The data will be copied into the destination pmix_value_t - thus, any data stored in the source
27
               value can be modified or free'd without affecting the copied data once the macro has completed.
```

```
Retrieve a numerical value from a value struct
 1
2
               Retrieve a numerical value from a pmix value t structure.
   PMIx v3.0
 3
               PMIX VALUE GET NUMBER(s, m, n, t)
               OUT s
4
5
                   Status code for the request (pmix status t)
6
               IN
 7
                   Pointer to the pmix_value_t structure (handle)
8
               OUT n
9
                   Variable to be set to the value (match expected type)
10
               IN
                   Type of number expected in m (pmix_data_type_t)
11
               Sets the provided variable equal to the numerical value contained in the given pmix_value_t,
12
13
               returning success if the data type of the value matches the expected type and
14
               PMIX_ERR_BAD_PARAM if it doesn't
            Info Structure
    3.2.9
               The pmix_info_t structure defines a key/value pair with associated directive. All fields were
16
               defined in version 1.0 unless otherwise marked.
17
   PMIx v1.0
18
               typedef struct pmix_info_t {
                    pmix_key_t key;
19
                    pmix_info_directives_t flags; // version 2.0
20
                    pmix_value_t value;
21
22
               } pmix info t;
    3.2.9.1
              Info structure support macros
23
               The following macros are provided to support the pmix info t structure.
               Initialize the info structure
25
               Initialize the pmix info t fields.
26
   PMIx v1.0
27
               PMIX INFO CONSTRUCT (m)
               IN
28
29
                   Pointer to the structure to be initialized (pointer to pmix info t)
```

1 2		Destruct the info structure Destruct the pmix_info_t fields.
	PMIx v1.0	C
3		PMIX_INFO_DESTRUCT (m)
4 5		<pre>IN m Pointer to the structure to be destructed (pointer to pmix_info_t)</pre>
6 7		Create an info array Allocate and initialize an array of info structures.
	PMIx v1.0	C -
8		PMIX_INFO_CREATE(m, n)
9 10 11 12		<pre>INOUT m</pre>
13 14		Free an info array Release an array of pmix_info_t structures.
	PMIx v1.0	
15		PMIX_INFO_FREE (m, n)
16 17 18		<pre>IN m Pointer to the array of pmix_info_t structures (handle) IN n Number of structures in the array (size_t)</pre>
20	DMI1 ()	Load key and value data into a info struct

	V
1	PMIX_INFO_LOAD(v, k, d, t);
	C
2	IN v
3	Pointer to the pmix_info_t into which the key and data are to be loaded (pointer to
4	pmix_info_t)
5	IN k
6	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length
7	(handle)
8	IN d
9	Pointer to the data value to be loaded (handle)
0	IN t
1	Type of the provided data value (pmix_data_type_t)
2	This macro simplifies the loading of key and data into a pmix_info_t by correctly assigning
3	values to the structure's fields.
	Advice to users
4	Both key and data will be copied into the pmix_info_t - thus, the key and any data stored in the
5	source value can be modified or free'd without affecting the copied data once the macro has
6	completed.
7	Copy data between info structures
8	Copy all data (including key, value, and directives) between two pmix_info_t structures.
PMIx v2.0	C
9	PMIX_INFO_XFER(d, s);
9	PMIX_INFO_XFER(d, S),
.0	IN d
:1	Pointer to the destination <pre>pmix_info_t</pre> (pointer to <pre>pmix_info_t</pre>)
2	IN s
3	Pointer to the source <pre>pmix_info_t</pre> (pointer to <pre>pmix_info_t</pre>)
4	This macro simplifies the transfer of data between twopmix_info_t structures.
1	
	Advice to users —
25	All data (including key, value, and directives) will be copied into the destination pmix_info_t -
26	thus, the source pmix_info_t may be free'd without affecting the copied data once the macro
27	has completed.
	A

1		Test a boolean info struct
2	PMIx v2.0	A special macro for checking if a boolean pmix_info_t is true. C
3		PMIX_INFO_TRUE (m)
4 5		IN m Pointer to a pmix_info_t structure (handle)
6		A pmix_info_t structure is considered to be of type PMIX_BOOL and value true if:
7 8		 the structure reports a type of PMIX_UNDEF, or the structure reports a type of PMIX_BOOL and the data flag is true
9	3.2.9.2	Info structure list macros
10 11		Constructing an array of pmix_info_t is a fairly common operation. The following macros are provided to simplify this construction.
12 13 14		Start a list of pmix_info_t structures Initialize a list of pmix_info_t structures. The actual list is opaque to the caller and is implementation-dependent.
15	PMIx v4.0	PMIX_INFO_LIST_START (m)
16 17		IN m A void* pointer (handle)
18 19		Note that the pointer will be initialized to an opaque structure whose elements are implementation-dependent. The caller must not modify or dereference the object.
20 21		Add a pmix_info_t structure to a list Add a pmix_info_t structure containing the specified value to the provided list.
	PMIx v4.0	

	v
1	PMIX_INFO_LIST_ADD(rc, m, k, d, t)
	C
2	INOUT rc
3	Return status for the operation (pmix_status_t)
4	IN m
5	A void* pointer initialized via PMIX_INFO_LIST_START (handle)
6	IN k
7	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length
8	(handle)
9	IN d
10	Pointer to the data value to be loaded (handle)
11	IN t
12	Type of the provided data value (pmix_data_type_t)
	✓ Advice to users
13	Both key and data will be copied into the pmix_info_t on the list - thus, the key and any data
14	stored in the source value can be modified or free'd without affecting the copied data once the
15	macro has completed.
	_
16	Transfer a pmix_info_t structure to a list
17	Transfer the information in a pmix_info_t structure to the provided list.
PMIx v4.	\mathbf{c}
18	PMIX_INFO_LIST_XFER(rc, m, s)
	C
19	INOUT rc
20	Return status for the operation (pmix_status_t)
21	IN m
22	A void* pointer initialized via PMIX_INFO_LIST_START (handle)
23	IN s
24	Pointer to the source pmix_info_t (pointer to pmix_info_t)
	Advice to users
	Advice to users
25	All data (including key, value, and directives) will be copied into the destination pmix_info_t
26	on the list - thus, the source pmix_info_t may be free'd without affecting the copied data once
27	the macro has completed.

1 2	Convert a pmix_info_t list to an array Transfer the information in the provided pmix_info_t list to a pmix_data_array_t array
- <i>PMIx v4.0</i>	C
3	PMIX_INFO_LIST_CONVERT(rc, m, d)
4 5 6 7 8 9	INOUT rc Return status for the operation (pmix_status_t) IN m A void* pointer initialized via PMIX_INFO_LIST_START (handle) IN d Pointer to an instantiated pmix_data_array_t structure where the pmix_info_t array is to be stored (pointer to pmix_data_array_t)
11 12 <i>PMIx v4.0</i>	Release a pmix_info_t list Release the provided pmix_info_t list
13	PMIX_INFO_LIST_RELEASE (m)
14 15	IN m A void* pointer initialized via PMIX_INFO_LIST_START (handle)
16 17	Information contained in the <code>pmix_info_t</code> on the list shall be released in addition to whatever backing storage the implementation may have allocated to support construction of the list.
18 3.2.10	Info Type Directives
19 <i>PMIx v2.0</i> 20 21	The pmix_info_directives_t structure is a uint32_t type that defines the behavior of command directives via pmix_info_t arrays. By default, the values in the pmix_info_t array passed to a PMIx are <i>optional</i> .
	Advice to users
22 23 24 25 26 27 28	A PMIx implementation or PMIx-enabled RM may ignore any <code>pmix_info_t</code> value passed to a PMIx API that it does not support or does not recognize if it is not explicitly marked as <code>PMIX_INFO_REQD</code> . This is because the values specified default to optional, meaning they can be ignored in such circumstances. This may lead to unexpected behavior when porting between environments or PMIx implementations if the user is relying on the behavior specified by the <code>pmix_info_t</code> value. Users relying on the behavior defined by the <code>pmix_info_t</code> are advised to set the <code>PMIX_INFO_REQD</code> flag using the <code>PMIX_INFO_REQUIRED</code> macro.

Advice	to	PMIY	library	, imn	lemen'	ters
Auvice	ιυ	I IVIIA	libiai	יקווו ע	ici ile il	เษาง

The top 16-bits of the <code>pmix_info_directives_t</code> are reserved for internal use by PMIx library implementers - the PMIx standard will *not* specify their intent, leaving them for customized use by implementers. Implementers are advised to use the provided <code>PMIX_INFO_IS_REQUIRED</code> macro for testing this flag, and must return <code>PMIX_ERR_NOT_SUPPORTED</code> as soon as possible to the caller if the required behavior is not supported.

The following constants were introduced in version 2.0 (unless otherwise marked) and can be used to set a variable of the type **pmix_info_directives_t**.

PMIX_INFO_REQD The behavior defined in the **pmix_info_t** array is required, and not optional. This is a bit-mask value.

PMIX_INFO_REQD_PROCESSED Mark that this required attribute has been processed. A required attribute can be handled at any level - the PMIx client library might take care of it, or it may be resolved by the PMIx server library, or it may pass up to the host environment for handling. If a level does not recognize or support the required attribute, it is required to pass it upwards to give the next level an opportunity to process it. Thus, the host environment (or the server library if the host does not support the given operation) must know if a lower level has handled the requirement so it can return a PMIX_ERR_NOT_SUPPORTED error status if the host itself cannot meet the request. Upon processing the request, the level must therefore mark the attribute with this directive to alert any subsequent levels that the requirement has been met.

PMIX_INFO_ARRAY_END Mark that this **pmix_info_t** struct is at the end of an array created by the **PMIX_INFO_CREATE** macro. This is a bit-mask value.

PMIX_INFO_DIR_RESERVED A bit-mask identifying the bits reserved for internal use by implementers - these currently are set as **0xffff0000**.

Advice to PMIx server hosts -

Host environments are advised to use the provided **PMIX_INFO_IS_REQUIRED** macro for testing this flag and must return **PMIX_ERR_NOT_SUPPORTED** as soon as possible to the caller if the required behavior is not supported.

3.2.10.1 Info Directive support macros

The following macros are provided to support the setting and testing of **pmix_info_t** directives.

```
Mark an info structure as required
 1
2
               Set the PMIX INFO REQD flag in a pmix info t structure.
   PMIx v2.0
3
               PMIX INFO REQUIRED (info);
               IN
                    info
 4
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
 5
               This macro simplifies the setting of the PMIX_INFO_REQD flag in pmix_info_t structures.
 6
               Mark an info structure as optional
 8
               Unsets the PMIX_INFO_REQD flag in a pmix_info_t structure.
   PMIx v2.0
9
               PMIX INFO OPTIONAL (info);
               IN
                    info
10
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
11
12
               This macro simplifies marking a pmix info t structure as optional.
               Test an info structure for required directive
13
               Test the PMIX_INFO_REQD flag in a pmix_info_t structure, returning true if the flag is set.
14
   PMIx v2.0
               PMIX INFO IS REQUIRED (info);
15
               IN
16
                    info
17
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
18
               This macro simplifies the testing of the required flag in pmix_info_t structures.
               Test an info structure for optional directive
19
20
               Test a pmix info t structure, returning true if the structure is optional.
   PMIx v2.0
21
               PMIX INFO IS OPTIONAL (info);
               IN
22
                    info
23
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
               Test the PMIX_INFO_REQD flag in a pmix_info_t structure, returning true if the flag is not
24
25
               set.
```

```
Mark a required attribute as processed
 1
               Mark that a required pmix info t structure has been processed.
2
   PMIx v4.0
3
               PMIX INFO PROCESSED (info);
               IN
 4
                    info
                    Pointer to the pmix_info_t (pointer to pmix_info_t)
 5
               Set the PMIX_INFO_REQD_PROCESSED flag in a pmix_info_t structure indicating that is
 6
 7
               has been processed.
8
               Test if a required attribute has been processed
9
               Test that a required pmix_info_t structure has been processed.
   PMIx v4.0
10
               PMIX_INFO_WAS_PROCESSED(info);
               IN
11
                    info
12
                   Pointer to the pmix info t (pointer to pmix info t)
               Test the PMIX_INFO_REQD_PROCESSED flag in a pmix_info_t structure.
13
               Test an info structure for end of array directive
14
               Test a pmix info t structure, returning true if the structure is at the end of an array created by
15
               the PMIX INFO CREATE macro.
16
   PMIx v2.2
               PMIX_INFO_IS_END(info);
17
               IN
                    info
18
                   Pointer to the pmix_info_t (pointer to pmix_info_t)
19
20
               This macro simplifies the testing of the end-of-array flag in pmix info t structures.
```

3.2.11 Environmental Variable Structure

```
Define a structure for specifying environment variable modifications. Standard environment
   PMIx v3.0
 3
                variables (e.g., PATH, LD LIBRARY PATH, and LD PRELOAD) take multiple arguments
 4
                separated by delimiters. Unfortunately, the delimiters depend upon the variable itself - some use
                semi-colons, some colons, etc. Thus, the operation requires not only the name of the variable to be
 5
                modified and the value to be inserted, but also the separator to be used when composing the
 6
 7
                aggregate value.
 8
                typedef struct {
 9
                     char *envar;
                     char *value;
10
11
                     char separator;
                } pmix envar t;
12
                 Environmental variable support macros
    3.2.11.1
14
                The following macros are provided to support the pmix_envar_t structure.
                Initialize the envar structure
15
16
                Initialize the pmix envar t fields.
   PMIx v3.0
17
                PMIX ENVAR CONSTRUCT (m)
                IN
18
19
                    Pointer to the structure to be initialized (pointer to pmix_envar_t)
                Destruct the envar structure
20
21
                Clear the pmix_envar_t fields.
   PMIx v3.0
22
                PMIX ENVAR DESTRUCT (m)
23
                IN
24
                    Pointer to the structure to be destructed (pointer to pmix envar t)
```

```
Create an envar array
 1
 2
               Allocate and initialize an array of pmix_envar_t structures.
   PMIx v3.0
 3
               PMIX ENVAR CREATE (m, n)
 4
               INOUT m
                    Address where the pointer to the array of pmix_envar_t structures shall be stored (handle)
 5
               IN
 6
 7
                    Number of structures to be allocated (size t)
               Free an envar array
 8
               Release an array of pmix_envar_t structures.
 9
   PMIx v3.0
10
               PMIX ENVAR FREE (m, n)
               IN
11
                    Pointer to the array of pmix_envar_t structures (handle)
12
13
               IN
14
                    Number of structures in the array (size t)
               Load an envar structure
15
16
               Load values into a pmix_envar_t.
   PMIx v2.0
17
               PMIX ENVAR LOAD (m, e, v, s)
               IN
18
                    Pointer to the structure to be loaded (pointer to pmix_envar_t)
19
               IN
20
                    Environmental variable name (char*)
21
22
               IN
                    Value of variable (char*)
23
24
               IN.
                    Separator character (char)
25
```

3.2.12 Byte Object Type

```
2
               The pmix_byte_object_t structure describes a raw byte sequence.
   PMIx v1.0
 3
               typedef struct pmix_byte_object {
 4
                    char *bytes;
                    size_t size;
 5
               } pmix_byte_object_t;
 6
    3.2.12.1
                Byte object support macros
               The following macros support the pmix_byte_object_t structure.
 8
 9
               Initialize the byte object structure
10
               Initialize the pmix_byte_object_t fields.
   PMIx v2.0
               PMIX BYTE OBJECT CONSTRUCT (m)
11
               IN
12
                   m
                   Pointer to the structure to be initialized (pointer to pmix_byte_object_t)
13
               Destruct the byte object structure
14
               Clear the pmix byte object t fields.
15
   PMIx v2.0
               PMIX BYTE OBJECT DESTRUCT (m)
16
               IN
17
18
                   Pointer to the structure to be destructed (pointer to pmix_byte_object_t)
               Create a byte object structure
19
20
               Allocate and intitialize an array of pmix byte object t structures.
   PMIx v2.0
21
               PMIX BYTE OBJECT CREATE (m, n)
               INOUT m
22
                   Address where the pointer to the array of pmix_byte_object_t structures shall be stored
23
                   (handle)
24
               IN
25
                    n
26
                   Number of structures to be allocated (size_t)
```

```
Free a byte object array
1
2
              Release an array of pmix byte object t structures.
   PMIx v2.0
3
              PMIX BYTE OBJECT FREE (m, n)
              IN
4
                   Pointer to the array of pmix_byte_object_t structures (handle)
 5
6
              IN
 7
                   Number of structures in the array (size t)
              Load a byte object structure
8
9
              Load values into a pmix_byte_object_t.
   PMIx v2.0
10
              PMIX_BYTE_OBJECT_LOAD(b, d, s)
              IN
11
12
                   Pointer to the structure to be loaded (pointer to pmix_byte_object_t)
              IN
13
                   Pointer to the data to be loaded (char*)
14
              IN
15
16
                   Number of bytes in the data array (size t)
    3.2.13
              Data Array Structure
              The pmix_data_array_t structure defines an array data structure.
18
   PMIx v2.0
19
              typedef struct pmix_data_array {
                   pmix_data_type_t type;
20
21
                   size t size;
22
                   void *array;
23
              } pmix_data_array_t;
    3.2.13.1
               Data array support macros
25
              The following macros support the pmix_data_array_t structure.
```

1	Initialize a data array structure
2	Initialize the pmix_data_array_t fields, allocating memory for the array of the indicated type.
<i>PMIx v2.2</i>	▼ C —
3	PMIX_DATA_ARRAY_CONSTRUCT(m, n, t)
	C
4	IN m
5	Pointer to the structure to be initialized (pointer to pmix_data_array_t)
6	IN n
7	Number of elements in the array (size_t)
8	IN t
9	PMIx data type of the array elements (pmix_data_type_t)
10	Destruct a data array structure
11	Destruct the pmix_data_array_t , releasing the memory in the array.
PMIx v2.2	C
12	PMIX_DATA_ARRAY_CONSTRUCT (m)
	C
13	IN m
14	Pointer to the structure to be destructed (pointer to pmix_data_array_t)
4.5	Create a data arrest atritatura
15 16	Create a data array structure Allocate memory for the pmix_data_array_t object itself, and then allocate memory for the
17	array of the indicated type.
PMIx v2.2	C
18	PMIX DATA ARRAY CREATE (m, n, t)
10	FMIX_DATA_ARRAI_CREATE (III, 11, t)
19	INOUT m
20 21	Variable to be set to the address of the structure (pointer to <pre>pmix_data_array_t</pre> IN n
22	Number of elements in the array (size_t)
23	IN t
24	PMIx data type of the array elements (pmix_data_type_t)

1	Free a data array structure
2	Release the memory in the array, and then release the pmix_data_array_t object itself.
PMIx v2.2	C —
3	PMIX_DATA_ARRAY_FREE (m)
	C
4	IN m
5	Pointer to the structure to be released (pointer to pmix_data_array_t)
6 3.2.1 4	Argument Array Macros
7 8	The following macros support the construction and release of NULL -terminated argv arrays of strings.
9	Argument array extension
0	Append a string to a NULL-terminated, argv-style array of strings.
	C
1	PMIX_ARGV_APPEND(r, a, b);
	C
2	OUT r
3	Status code indicating success or failure of the operation (pmix_status_t)
4	INOUT a
5	Argument list (pointer to NULL-terminated array of strings)
6	IN b
7	Argument to append to the list (string)
8	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for querying, or other places where argv-style string arrays are required.
	Advice to users
20	The provided argument is copied into the destination array - thus, the source string can be free'd
21	without affecting the array once the macro has completed.

1 2	Argument array prepend Prepend a string to a NULL-terminated, argy-style array of strings.
_	C
3	PMIX_ARGV_PREPEND(r, a, b);
4	OUT r
5	Status code indicating success or failure of the operation (pmix_status_t) INOUT a
6 7	Argument list (pointer to NULL-terminated array of strings)
8	IN b
9	Argument to append to the list (string)
0 1	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for querying, or other places where argv-style string arrays are required.
	Advice to users
2 3	The provided argument is copied into the destination array - thus, the source string can be free'd without affecting the array once the macro has completed.
4 5 6	Argument array extension - unique Append a string to a NULL-terminated, argv-style array of strings, but only if the provided argument doesn't already exist somewhere in the array.
7	PMIX_ARGV_APPEND_UNIQUE(r, a, b);
•	OUT
8 9	OUT r Status code indicating success or failure of the operation (pmix_status_t)
20	INOUT a
21	Argument list (pointer to NULL-terminated array of strings)
22	IN b
23	Argument to append to the list (string)
24	This function helps the caller build the argv portion of pmix_app_t structure, arrays of keys for
25	querying, or other places where argy-style string arrays are required.
	Advice to users
26 27	The provided argument is copied into the destination array - thus, the source string can be free'd without affecting the array once the macro has completed.

1 2	Argument array release Free an argy-style array and all of the strings that it contains.
2	C
3	PMIX_ARGV_FREE(a);
4 5	IN a Argument list (pointer to NULL-terminated array of strings)
6	This function releases the array and all of the strings it contains.
7 8	Argument array split Split a string into a NULL-terminated argv array.
9	PMIX_ARGV_SPLIT(a, b, c);
0	OUT a
1	Resulting argv-style array (char**)
2	IN b String to be split (char*)
4	IN c
5	Delimiter character (char)
6 7	Split an input string into a NULL-terminated argv array. Do not include empty strings in the resulting array.
	Advice to users
8 9 20	All strings are inserted into the argy array by value; the newly-allocated array makes no references to the src_string argument (i.e., it can be freed after calling this function without invalidating the output argy array)

```
Argument array join
 1
 2
                Join all the elements of an argy array into a single newly-allocated string.
 3
                PMIX_ARGV_JOIN(a, b, c);
                OUT a
 4
                     Resulting string (char*)
 5
                IN
 6
 7
                     Argy-style array to be joined (char**)
 8
               IN
                     Delimiter character (char)
 9
10
                Join all the elements of an argy array into a single newly-allocated string.
                Argument array count
11
                Return the length of a NULL-terminated argv array.
12
13
                PMIX_ARGV_COUNT(r, a);
                OUT r
14
15
                     Number of strings in the array (integer)
                IN
16
                     Argy-style array (char**)
17
18
                Count the number of elements in an argy array
                Argument array copy
19
               Copy an argy array, including copying all of its strings.
20
                PMIX_ARGV_COPY(a, b);
21
22
                OUT a
                    New argy-style array (char**)
23
24
25
                     Argy-style array (char**)
                Copy an argy array, including copying all of its strings.
26
```

3.2.15 Set Environment Variable

Summarv 3 Set an environment variable in a **NULL**-terminated, env-style array. 4 PMIX SETENV(r, name, value, env); OUT r 5 6 Status code indicating success or failure of the operation (pmix status t) 7 8 Argument name (string) IN 9 value 10 Argument value (string) INOUT env 11 Environment array to update (pointer to array of strings) 12 **Description** 13 Similar to setenv from the C API, this allows the caller to set an environment variable in the 14 15 specified **env** array, which could then be passed to the **pmix** app t structure or any other 16 destination. Advice to users 17 The provided name and value are copied into the destination environment array - thus, the source strings can be free'd without affecting the array once the macro has completed. 18 Generalized Data Types Used for Packing/Unpacking 3.3 20 The pmix_data_type_t structure is a uint16_t type for identifying the data type for 21 packing/unpacking purposes. New data type values introduced in this version of the Standard are 22 shown in magenta. Advice to PMIx library implementers ————— 23 The following constants can be used to set a variable of the type pmix_data_type_t. Data types in the PMIx Standard are defined in terms of the C-programming language. Implementers 24 wishing to support other languages should provide the equivalent definitions in a 25

language-appropriate manner. Additionally, a PMIx implementation may choose to add additional

types.

26

```
Undefined.
 1
              PMIX_UNDEF
 2
              PMIX_BOOL
                             Boolean (converted to/from native true/false) (bool).
 3
              PMIX BYTE
                             A byte of data (uint8_t).
                                NULL terminated string (char*).
 4
              PMIX STRING
 5
              PMIX SIZE
                             Size size t.
 6
              PMIX PID
                            Operating Process IDentifier (PID) (pid t).
 7
              PMIX INT
                            Integer (int).
8
                             8-byte integer (int8_t).
              PMIX_INT8
9
              PMIX_INT16
                              16-byte integer (int16_t).
10
              PMIX INT32
                              32-byte integer (int32_t).
                              64-byte integer (int64_t).
11
              PMIX INT64
12
                             Unsigned integer (unsigned int).
              PMIX UINT
13
              PMIX UINT8
                              Unsigned 8-byte integer (uint8 t).
14
              PMIX UINT16
                                Unsigned 16-byte integer (uint16 t).
15
                                Unsigned 32-byte integer (uint32_t).
              PMIX UINT32
                                Unsigned 64-byte integer (uint 64_t).
16
              PMIX_UINT64
17
                              Float (float).
              PMIX FLOAT
18
              PMIX DOUBLE
                                Double (double).
19
                                 Time value (struct timeval).
              PMIX TIMEVAL
20
              PMIX TIME
                             Time (time t).
                                Status code pmix_status_t.
21
              PMIX STATUS
22
              PMIX VALUE
                              Value (pmix_value_t).
23
                             Process (pmix_proc_t).
              PMIX_PROC
24
              PMIX_APP
                            Application context.
25
              PMIX INFO
                             Info object.
                              Pointer to data.
26
              PMIX PDATA
27
              PMIX BUFFER
                                Buffer.
              PMIX_BYTE_OBJECT
28
                                      Byte object (pmix_byte_object_t).
29
                             Key/value pair.
              PMIX KVAL
30
                                 Persistance (pmix_persistence_t).
              PMIX PERSIST
31
              PMIX POINTER
                                 Pointer to an object (void*).
32
              PMIX SCOPE
                              Scope (pmix_scope_t).
                                     Range for data (pmix_data_range_t).
33
              PMIX DATA RANGE
                                 PMIx command code (used internally).
34
              PMIX COMMAND
35
              PMIX INFO DIRECTIVES
                                           Directives flag for pmix info t
36
                   (pmix info directives t).
37
                                   Data type code (pmix_data_type_t).
              PMIX DATA TYPE
                                     Process state (pmix_proc_state_t).
38
              PMIX_PROC_STATE
                                   Process information (pmix_proc_info_t).
              PMIX PROC INFO
39
40
              PMIX DATA ARRAY
                                     Data array (pmix_data_array_t).
                                   Process rank (pmix_rank_t).
41
              PMIX_PROC_RANK
```

```
1
                                Query structure (pmix_query_t).
               PMIX_QUERY
2
               PMIX COMPRESSED STRING
                                                String compressed with zlib (char*).
                                                      Byte object whose bytes have been compressed with
 3
               PMIX COMPRESSED BYTE OBJECT
 4
                    zlib (pmix_byte_object_t).
 5
               PMIX_ALLOC_DIRECTIVE
                                             Allocation directive (pmix_alloc_directive_t).
6
               PMIX IOF CHANNEL
                                        Input/output forwarding channel (pmix iof channel t).
 7
               PMIX ENVAR
                                Environmental variable structure (pmix envar t).
8
               PMIX COORD
                                Structure containing fabric coordinates (pmix coord t).
9
                                   Structure supporting attribute registrations (pmix regattr t).
               PMIX REGATTR
10
               PMIX REGEX
                                Regular expressions - can be a valid NULL-terminated string or an arbitrary
                   array of bytes.
11
12
               PMIX_JOB_STATE
                                     Job state (pmix_job_state_t).
               PMIX_LINK_STATE
                                      Link state (pmix_link_state_t).
13
14
               PMIX PROC CPUSET
                                        Structure containing the binding bitmap of a process
15
                    (pmix_cpuset_t).
                                    Geometry structure containing the fabric coordinates of a specified
16
               PMIX GEOMETRY
17
                    device.(pmix_geometry_t).
18
               PMIX DEVICE DIST
                                        Structure containing the minimum and maximum relative distance
19
                    from the caller to a given fabric device. (pmix device distance t).
20
                                    Structure containing an assigned endpoint for a given fabric device.
               PMIX ENDPOINT
21
                    (pmix endpoint t).
22
               PMIX TOPO
                               Structure containing the topology for a given node. (pmix topology t).
23
                                   Bitmask containing the types of devices being referenced.
               PMIX DEVTYPE
24
                    (pmix device type t).
                                   Bitmask describing the relative location of another process.
25
               PMIX LOCTYPE
26
                    (pmix locality t).
27
               PMIX DATA TYPE MAX
                                          A starting point for implementer-specific data types. Values above
                    this are guaranteed not to conflict with PMIx values. Definitions should always be based on
28
29
                    the PMIX_DATA_TYPE_MAX constant and not a specific value as the value of the constant
30
                    may change.
```

3.4 General Callback Functions

PMIx provides blocking and nonblocking versions of most APIs. In the nonblocking versions, a callback is activated upon completion of the operation. This section describes many of those callbacks.

3.4.1 Release Callback Function

Summary

The pmix_release_cbfunc_t is used by the pmix_modex_cbfunc_t and pmix_info_cbfunc_t operations to indicate that the callback data may be reclaimed/freed by the caller.

32

33

34

36 37

38

```
Format
1
   PMIx v1.0
2
              typedef void (*pmix_release_cbfunc_t)
 3
                    (void *cbdata);
              INOUT chdata
4
                   Callback data passed to original API call (memory reference)
 5
              Description
 6
              Since the data is "owned" by the host server, provide a callback function to notify the host server
 7
 8
              that we are done with the data so it can be released.
             Op Callback Function
   3.4.2
              Summary
10
              The pmix_op_cbfunc_t is used by operations that simply return a status.
11
   PMIx v1.0
12
              typedef void (*pmix_op_cbfunc_t)
13
                    (pmix status t status, void *cbdata);
14
              IN
                  status
15
                   Status associated with the operation (handle)
              IN
16
                   Callback data passed to original API call (memory reference)
17
              Description
18
19
              Used by a wide range of PMIx API's including PMIx_Fence_nb,
              pmix_server_client_connected2_fn_t, PMIx_server_register_nspace. This
20
              callback function is used to return a status to an often nonblocking operation.
21
             Value Callback Function
    3.4.3
              Summary
23
              The pmix value cbfunc t is used by PMIx Get nb to return data.
24
   PMIx v1.0
25
              typedef void (*pmix value cbfunc t)
26
                    (pmix status t status,
27
                    pmix value t *kv, void *cbdata);
```

3.4.5 Handler registration callback function

```
Summary
              Callback function for calls to register handlers, e.g., event notification and IOF requests.
 3
              Format
   PMIx v3.0
5
              typedef void (*pmix_hdlr_reg_cbfunc_t)
6
                    (pmix_status_t status,
 7
                     size_t refid,
8
                     void *cbdata);
9
              IN
                    status
10
                   PMIX_SUCCESS or an appropriate error constant (pmix_status_t)
11
                   reference identifier assigned to the handler by PMIx, used to deregister the handler (size_t)
12
              IN
                   cbdata
13
                   object provided to the registration call (pointer)
14
              Description
15
16
              Callback function for calls to register handlers, e.g., event notification and IOF requests.
            PMIx Datatype Value String Representations
    3.5
18
              Provide a string representation for several types of values. Note that the provided string is statically
19
              defined and must NOT be free'd.
              Summary
20
21
              String representation of a pmix status t.
   PMIx v1.0
22
              const char*
              PMIx_Error_string(pmix_status_t status);
23
24
               Summary
25
              String representation of a pmix_proc_state_t.
   PMIx v2.0
26
              const char*
27
              PMIx Proc state string(pmix proc state t state);
```

```
Summary
1
2
             String representation of a pmix scope t.
   PMIx v2.0
3
             const char*
4
             PMIx Scope string(pmix scope t scope);
             Summary
5
6
             String representation of a pmix_persistence_t.
   PMIx v2.0
 7
             const char*
             PMIx_Persistence_string(pmix_persistence_t persist);
8
9
             Summary
             String representation of a pmix_data_range_t.
10
   PMIx v2.0
11
             const char*
12
             PMIx Data range string (pmix data range t range);
             Summary
13
14
             String representation of a pmix_info_directives_t.
   PMIx v2.0
15
             const char*
             PMIx_Info_directives_string(pmix_info_directives_t directives);
16
17
             Summary
18
             String representation of a pmix_data_type_t.
   PMIx v2.0
19
             const char*
20
             PMIx Data type string(pmix data type t type);
```

```
Summary
1
2
             String representation of a pmix alloc directive t.
   PMIx v2.0
3
             const char*
 4
             PMIx_Alloc_directive_string(pmix_alloc_directive_t directive);
             Summary
5
             String representation of a pmix_iof_channel_t.
6
   PMIx v3.0
 7
             const char*
             PMIx_IOF_channel_string(pmix_iof_channel_t channel);
8
9
             Summary
             String representation of a pmix_job_state_t.
10
   PMIx v4.0
11
             const char*
12
             PMIx_Job_state_string(pmix_job_state_t state);
             Summary
13
14
             String representation of a PMIx attribute.
   PMIx v4.0
15
             const char*
             PMIx_Get_attribute_string(char *attributename);
16
17
             Summary
18
             Return the PMIx attribute name corresponding to the given attribute string.
   PMIx v4.0
19
             const char*
20
             PMIx Get attribute name(char *attributestring);
```

```
Summary
1
2
            String representation of a pmix_link_state_t.
  PMIx v4.0
3
            const char*
4
            PMIx_Link_state_string(pmix_link_state_t state);
            Summary
5
            String representation of a pmix_device_type_t.
6
  PMIx v4.0
7
            const char*
8
            PMIx_Device_type_string(pmix_device_type_t type);
```

CHAPTER 4

23

Client Initialization and Finalization

The PMIx library is required to be initialized and finalized around the usage of most PMIx functions or macros. The APIs that may be used outside of the initialized and finalized region are 2 noted. All other APIs must be used inside this region. 3 There are three sets of initialization and finalization functions depending upon the role of the process in the PMIx Standard - those associated with the PMIx *client* are defined in this chapter. 5 Similar functions corresponding to the roles of server and tool are defined in Chapters 16 and 17, 6 respectively. 8 Note that a process can only call *one* of the initialization/finalization functional pairs from the set of 9 three - e.g., a process that calls the client initialization function cannot also call the tool or server initialization functions, and must call the corresponding client finalization function. Regardless of 10 the role assumed by the process, all processes have access to the client APIs. Thus, the server and 11 12 tool roles can be considered supersets of the PMIx client. 4.1 PMIx Initialized Summary 14 15 Determine if the PMIx library has been initialized. This function may be used outside of the initialized and finalized region, and is usable by servers and tools in addition to clients. 16 **Format** 17 PMIx v1.0 18 int PMIx Initialized (void) A value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) otherwise. 19 ----- Rationale -----20 The return value is an integer for historical reasons as that was the signature of prior PMI libraries. **Description** 21 Check to see if the PMIx library has been initialized using any of the init functions: **PMIx_Init**,

PMIx server init, or PMIx tool init.

4.2 PMIx_Get_version

```
2
               Summary
               Get the PMIx version information. This function may be used outside of the initialized and
 3
               finalized region, and is usable by servers and tools in addition to clients.
 4
               Format
 5
   PMIx v1.0
               const char* PMIx Get version(void)
 6
               Description
 7
               Get the PMIx version string. Note that the provided string is statically defined and must not be
 8
 9
               free'd.
            PMIx Init
               Summary
11
12
               Initialize the PMIx client library
               Format
13
   PMIx v1.2
14
               pmix_status_t
15
               PMIx_Init(pmix_proc_t *proc,
                            pmix_info_t info[], size_t ninfo)
16
17
               INOUT proc
                    proc structure (handle)
18
               IN
                    info
19
                    Array of pmix_info_t structures (array of handles)
20
21
               IN
                    ninfo
22
                    Number of elements in the info array (size t)
23
               Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
```

	→ Optional Attributes
1	The following attributes are optional for implementers of PMIx libraries:
2 3 4	PMIX_USOCK_DISABLE "pmix.usock.disable" (bool) Disable legacy UNIX socket (usock) support. If the library supports Unix socket connections, this attribute may be supported for disabling it.
5 6 7	PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.
8 9 10 11	PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool) Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport. If the library supports multiple methods for clients to connect to servers, this attribute may be supported for disabling all but one of them.
12 13 14 15	<pre>PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) If provided, directs that the TCP Uniform Resource Identifier (URI) be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute may be supported for reporting the URI.</pre>
16 17 18 19	<pre>PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) Comma-delimited list of devices and/or Classless Inter-Domain Routing (CIDR) notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used.</pre>
20 21 22 23	PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are <i>not</i> to be used.
24 25 26	<pre>PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int) The IPv4 port to be used. If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used.</pre>
27 28 29	<pre>PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used.</pre>
30 31 32	PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it.
33 34 35	PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it.

PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)

1	The host shall progress the PMIx library via calls to PMIx_Progress
2 3 4 5 6 7 8	PMIX_EVENT_BASE "pmix.evbase" (void*) Pointer to an event_base to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base <i>must</i> be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.
9 10	If provided, the following attributes are used by the event notification system for inter-library coordination:
11 12	PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*) Programming model being initialized (e.g., "MPI" or "OpenMP").
13 14	<pre>PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*) Programming model implementation ID (e.g., "OpenMPI" or "MPICH").</pre>
15 16	<pre>PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*) Programming model version string (e.g., "2.1.1").</pre>
17 18	<pre>PMIX_THREADING_MODEL "pmix.threads" (char*) Threading model used (e.g., "pthreads").</pre>
19 20	<pre>PMIX_MODEL_NUM_THREADS "pmix.mdl.nthrds" (uint64_t) Number of active threads being used by the model.</pre>
21 22	<pre>PMIX_MODEL_NUM_CPUS "pmix.mdl.ncpu" (uint64_t) Number of cpus being used by the model.</pre>
23 24	<pre>PMIX_MODEL_CPU_TYPE "pmix.mdl.cputype" (char*) Granularity - "hwthread", "core", etc.</pre>
25 26 27 28	<pre>PMIX_MODEL_AFFINITY_POLICY "pmix.mdl.tap" (char*) Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread located on cpu close to master thread), "spread" (threads load-balanced across available cpus).</pre>

1 Description

2

3

5

6

7

8

9

10

11 12

13 14

15

16

17

18

19

23

24

25

27

29

30

31 32

33 34

35

Initialize the PMIx client, returning the process identifier assigned to this client's application in the provided **pmix_proc_t** struct. Passing a value of **NULL** for this parameter is allowed if the user wishes solely to initialize the PMIx system and does not require return of the identifier at that time.

When called, the PMIx client shall check for the required connection information of the local PMIx server and establish the connection. If the information is not found, or the server connection fails, then an appropriate error constant shall be returned.

If successful, the function shall return **PMIX_SUCCESS** and fill the *proc* structure (if provided) with the server-assigned namespace and rank of the process within the application. In addition, all startup information provided by the resource manager shall be made available to the client process via subsequent calls to **PMIx_Get**.

The PMIx client library shall be reference counted, and so multiple calls to PMIx_Init are allowed by the standard. Thus, one way for an application process to obtain its namespace and rank is to simply call PMIx_Init with a non-NULL proc parameter. Note that each call to PMIx_Init must be balanced with a call to PMIx_Finalize to maintain the reference count.

Each call to **PMIx_Init** may contain an array of **pmix_info_t** structures passing directives to the PMIx client library as per the above attributes.

Multiple calls to **PMIx_Init** shall not include conflicting directives. The **PMIx_Init** function will return an error when directives that conflict with prior directives are encountered.

20 4.3.1 Initialization events

21 The following events are typically associated with calls to **PMIx_Init**:

22 **PMIX MODEL DECLARED** Model declared.

PMIX_MODEL_RESOURCES Resource usage by a programming model has changed.

PMIX_OPENMP_PARALLEL_ENTERED An OpenMP parallel code region has been entered.

PMIX_OPENMP_PARALLEL_EXITED An OpenMP parallel code region has completed.

6 4.3.2 Initialization attributes

The following attributes influence the behavior of **PMIx Init**.

4.3.2.1 Connection attributes

These attributes are used to describe a TCP socket for rendezvous with the local RM by passing them into the relevant initialization API - thus, they are not typically accessed via the **PMIx_Get** API.

```
PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*)
```

If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename.

PMIX_TCP_URI "pmix.tcp.uri" (char*)

1		The URI of the PMIx server to connect to, or a file name containing it in the form of
2		file: <name containing="" file="" it="" of="">.</name>
3		<pre>PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*)</pre>
4		Comma-delimited list of devices and/or CIDR notation to include when establishing the
5		TCP connection.
6		<pre>PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*)</pre>
7		Comma-delimited list of devices and/or CIDR notation to exclude when establishing the
8		TCP connection.
9		PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int)
0		The IPv4 port to be used
11		PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int)
12		The IPv6 port to be used.
13		PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool)
14		Set to true to disable IPv4 family of addresses.
15		PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool)
16		Set to true to disable IPv6 family of addresses.
17	4.3.2.2	Programming model attributes
8		These attributes are associated with programming models.
19		PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*)
20		Programming model being initialized (e.g., "MPI" or "OpenMP").
21		PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)
22		Programming model implementation ID (e.g., "OpenMPI" or "MPICH").
23		PMIX_MODEL_LIBRARY_VERSION "pmix.mld.vrs" (char*)
24		Programming model version string (e.g., "2.1.1").
25		PMIX_THREADING_MODEL "pmix.threads" (char*)
26		Threading model used (e.g., "pthreads").
27		PMIX_MODEL_NUM_THREADS "pmix.mdl.nthrds" (uint64_t)
28		Number of active threads being used by the model.
29		PMIX_MODEL_NUM_CPUS "pmix.mdl.ncpu" (uint64_t)
30		Number of cpus being used by the model.
31		PMIX_MODEL_CPU_TYPE "pmix.mdl.cputype" (char*)
32		Granularity - "hwthread", "core", etc.
33		PMIX_MODEL_PHASE_NAME "pmix.mdl.phase" (char*)
34		User-assigned name for a phase in the application execution (e.g., "cfd reduction").
35		PMIX_MODEL_PHASE_TYPE "pmix.mdl.ptype" (char*)
36		Type of phase being executed (e.g., "matrix multiply").
37		<pre>PMIX_MODEL_AFFINITY_POLICY "pmix.mdl.tap" (char*)</pre>
88		Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread
39		located on cpu close to master thread), "spread" (threads load-balanced across available
10		cpus).

1 4.4 PMIx_Finalize

2		Summary
3		Finalize the PMIx client library.
4		Format
	<i>PMIx v1.0</i>	- C
5		pmix_status_t
6		PMIx_Finalize(const pmix_info_t info[], size_t ninfo)
		<u> </u>
7		IN info
8		Array of pmix_info_t structures (array of handles)
9		IN ninfo Number of elements in the <i>info</i> array (size_t)
1		Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
		▼ Optional Attributes
2		The following attributes are optional for implementers of PMIx libraries:
3		PMIX_EMBED_BARRIER "pmix.embed.barrier" (bool)
4		Execute a blocking fence operation before executing the specified operation.
5		PMIx_Finalize does not include an internal barrier operation by default. This attribute
6		directs PMIx_Finalize to execute a barrier as part of the finalize operation.
7		Description
8		Decrement the PMIx client library reference count. When the reference count reaches zero, the
9		library will finalize the PMIx client, closing the connection with the local PMIx server and
20		releasing all internally allocated memory.
	4.4.1	Finalize attributes
21	4.4.1	rinalize attributes
2		The following attribute influences the behavior of PMIx_Finalize .
23		PMIX_EMBED_BARRIER "pmix.embed.barrier" (bool)
24		Execute a blocking fence operation before executing the specified operation.
25		PMIx_Finalize does not include an internal barrier operation by default. This attribute
26		directs PMIx_Finalize to execute a barrier as part of the finalize operation.
27	4.5 E	MIx_Progress
8.9		Summary Progress the DMIs library
9		Progress the PMIx library.

1	Format	0	
<i>PMIx v4.0</i>	V	C	<u> </u>
2	void		
3	PMIx_Progress(void)		
		C	
4	Description		
5	Progress the PMIx library. Note that	special care must be taken to avo	oid deadlocking in PMIx
6	callback functions and acpAPI.		

CHAPTER 5

1

3

4

5 6

7 8

9

10

Synchronization and Data Access Operations

Applications may need to synchronize their operations at various points in their execution. Depending on a variety of factors (e.g., the programming model and where the synchronization point lies), the application may choose to execute the operation using PMIx. This is particularly useful in situations where communication by other means is not yet available since PMIx relies on the host environment's infrastructure for such operations.

Synchronization operations also offer an opportunity for processes to exchange data at a known point in their execution. Where required, this can include information on communication endpoints for subsequent wireup of various messaging protocols.

This chapter covers both the synchronization and data retrieval functions provided under the PMIx Standard.

5.1 PMIx_Fence

Summary 12 Execute a blocking barrier across the processes identified in the specified array, collecting 13 information posted via PMIx_Put as directed. 14 15 **Format** PMIx v1.0 16 pmix status t PMIx Fence(const pmix proc t procs[], size t nprocs, 17 const pmix_info_t info[], size_t ninfo); 18 19 IN procs 20 Array of pmix proc t structures (array of handles) IN 21 Number of elements in the *procs* array (integer) 22 23 IN Array of info structures (array of handles) 24 IN 25 ninfo 26 Number of elements in the *info* array (integer) 27 Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

PMIx_Commit, making the collection locally available to each participant at the end of to operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute. PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool) Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection. Optional Attributes The following attributes are optional for PMIx implementations: PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int)		→
Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of to operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute. PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool) Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection. Optional Attributes The following attributes are optional for PMIx implementations: PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions	1	The following attributes are required to be supported by all PMIx libraries:
Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively usin the PMIx_Fence operation with this directive, or can be retrieved one peer at a time usin PMIx_Get without first having performed the job-wide collection. Optional Attributes The following attributes are optional for PMIx implementations: PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions	3 4 5	Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO
The following attributes are optional for PMIx implementations: PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions	9 10 11 12 13	Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using
PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions		Optional Attributes
All <i>clones</i> of the calling process must participate in the collective operation. The following attributes are optional for host environments: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions	15	The following attributes are optional for PMIx implementations:
19 PMIX_TIMEOUT "pmix.timeout" (int) 20 Time in seconds before the specified operation should time out (zero indicating infinite) ar 21 return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions		
Time in seconds before the specified operation should time out (zero indicating infinite) are return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions	18	The following attributes are optional for host environments:
	20 21	Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions

Description

1

3

4

5

6

7

8

9

10

11

12

13

15 16

17

Passing a **NULL** pointer as the *procs* parameter indicates that the fence is to span all processes in the client's namespace. Each provided **pmix_proc_t** struct can pass **PMIX_RANK_WILDCARD** to indicate that all processes in the given namespace are participating.

The *info* array is used to pass user directives regarding the behavior of the fence operation. Note that for scalability reasons, the default behavior for **PMIx_Fence** is to not collect data posted by the operation's participants.

Advice to PMIx library implementers

PMIx_Fence and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

14 5.2 PMIx_Fence_nb

Summary

Execute a nonblocking **PMIx_Fence** across the processes identified in the specified array of processes, collecting information posted via **PMIx_Put** as directed.

1		Format
	PMIx v1.0	
2		pmix_status_t
3		PMIx_Fence_nb(const pmix_proc_t procs[], size_t nprocs,
4		<pre>const pmix_info_t info[], size_t ninfo,</pre>
5		<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
6		IN procs
7		Array of pmix_proc_t structures (array of handles)
8		IN nprocs
9		Number of elements in the <i>procs</i> array (integer)
10		IN info
11		Array of info structures (array of handles)
12		IN ninfo
13		Number of elements in the <i>info</i> array (integer)
14		IN cbfunc
15		Callback function (function reference)
16		IN cbdata
17		Data to be passed to the callback function (memory reference)
18		Returns one of the following:
19		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
20		will be returned in the provided cbfunc. Note that the library must not invoke the callback
21		function prior to returning from the API.
22		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
23		returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called. This can occur if the collective involved only
24		processes on the local node.
25		• a PMIx error constant indicating either an error in the input or that the request was immediately
26		processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
20		
		Required Attributes
27		The following attributes are required to be supported by all PMIx libraries:
28		PMIX_COLLECT_DATA "pmix.collect" (bool)
29		Collect all data posted by the participants using PMIx_Put that has been committed via
30		PMIx_Commit, making the collection locally available to each participant at the end of the
31		operation. By default, this will include all job-level information that was locally generated
32		by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO
33		attribute.
34		PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)

1 Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx 2 servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should 3 4 remote processes need to access the information, it can either be obtained collectively using 5 the **PMIx** Fence operation with this directive, or can be retrieved one peer at a time using 6 **PMIx_Get** without first having performed the job-wide collection. Optional Attributes 7 The following attributes are optional for PMIx implementations: 8 PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool) 9 All *clones* of the calling process must participate in the collective operation. 10 The following attributes are optional for host environments that support this operation: PMIX_TIMEOUT "pmix.timeout" (int) 11 12 Time in seconds before the specified operation should time out (zero indicating infinite) and 13 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 14 caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 15 Nonblocking version of the PMIx Fence routine. See the PMIx Fence description for further 16 17 details. **Fence-related attributes** 5.2.1 18 The following attributes are defined specifically to support the fence operation: 19 PMIX_COLLECT_DATA "pmix.collect" (bool) 20 21 Collect all data posted by the participants using **PMIx Put** that has been committed via PMIx Commit, making the collection locally available to each participant at the end of the 22 operation. By default, this will include all job-level information that was locally generated 23 by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO 24 25 attribute. 26 PMIX COLLECT GENERATED JOB INFO "pmix.collect.gen" (bool) 27 Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx servers. Some job-level information (e.g., distance between processes and fabric devices) is 28 29 best determined on a distributed basis as it primarily pertains to local processes. Should 30 remote processes need to access the information, it can either be obtained collectively using the **PMIx** Fence operation with this directive, or can be retrieved one peer at a time using 31 **PMIx_Get** without first having performed the job-wide collection. 32 PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) 33

All *clones* of the calling process must participate in the collective operation.

5.3 PMIx Get

```
2
               Summary
               Retrieve a key/value pair from the client's namespace.
 3
               Format
   PMIx v1.0
 5
               pmix status t
 6
               PMIx Get(const pmix proc t *proc, const pmix key t key,
 7
                            const pmix_info_t info[], size_t ninfo,
 8
                           pmix value t **val);
               IN
 9
                    proc
10
                    Process identifier - a NULL value may be used in place of the caller's ID (handle)
               IN
11
                    Key to retrieve (pmix_key_t)
12
                    info
13
               IN
                    Array of info structures (array of handles)
14
15
               IN
                    ninfo
                    Number of elements in the info array (integer)
16
17
               OUT val
                    value (handle)
18
               Returns one of the following:
19
               • PMIX_SUCCESS The requested data has been returned in the manner requested (i.e., in a
20
                  provided static memory location )
21
               • PMIX ERR BAD PARAM A bad parameter was passed to the function call - e.g., the request
22
                  included the PMIX_GET_STATIC_VALUES directive, but the provided storage location was
23
                 NULL
24
25
               • PMIX ERR EXISTS OUTSIDE SCOPE The requested key exists, but was posted in a scope
                  (see Section 7.1.1.1) that does not include the requester.
26
27
               • PMIX ERR NOT FOUND The requested data was not available.
28

    a non-zero PMIx error constant indicating a reason for the request's failure.

                                                 Required Attributes
29
               The following attributes are required to be supported by all PMIx libraries:
30
               PMIX_OPTIONAL "pmix.optional" (bool)
                     Look only in the client's local data store for the requested value - do not request data from
31
32
                     the PMIx server if not found.
33
               PMIX IMMEDIATE "pmix.immediate" (bool)
```

Specified operation should immediately return an error from the PMIx server if the requested 1 2 data cannot be found - do not request it from the host RM. 3 PMIX DATA SCOPE "pmix.scope" (pmix scope t) Scope of the data to be searched in a **PMIx_Get** call. 4 PMIX_SESSION_INFO "pmix.ssn.info" (bool) 5 Return information regarding the session realm of the target process. 6 7 PMIX JOB INFO "pmix.job.info" (bool) Return information regarding the job realm corresponding to the namespace in the target 8 process' identifier. 9 PMIX_APP_INFO "pmix.app.info" (bool) 10 Return information regarding the application realm to which the target process belongs - the 11 namespace of the target process serves to identify the job containing the target application. If 12 information about an application other than the one containing the target process is desired, 13 then the attribute array must contain a **PMIX APPNUM** attribute identifying the desired 14 target application. This is useful in cases where there are multiple applications and the 15 16 mapping of processes to applications is unclear. 17 PMIX NODE INFO "pmix.node.info" (bool) Return information from the node realm regarding the node upon which the specified 18 process is executing. If information about a node other than the one containing the specified 19 20 process is desired, then the attribute array must also contain either the PMIX NODEID or **PMIX HOSTNAME** attribute identifying the desired target. This is useful for requesting 21 information about a specific node even if the identity of processes running on that node are 22 23 not known.. PMIX GET_STATIC_VALUES "pmix.get.static" (bool) 24 Request that the data be returned in the provided storage location. The caller is responsible 25 for destructing the pmix value t using the PMIX VALUE DESTRUCT macro when 26 done. 27 28 PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool) Request that any pointers in the returned value point directly to values in the key-value store. 29 The user *must not* release any returned data pointers. 30 31 PMIX GET_REFRESH_CACHE "pmix.get.refresh" (bool) 32 When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. 33 Local process information is assumed to be automatically updated upon posting by the 34 process. A NULL key will cause all values associated with the process to be refreshed -35 36 otherwise, only the indicated key will be updated. A process rank of **PMIX RANK_WILDCARD** can be used to update job-related information in dynamic 37 environments. The user is responsible for subsequently updating refreshed values they may 38 have cached in their own local memory. 39

 Optional Attributes

The following attributes are optional for host environments:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

1

3

4

5

6 7

8

9

10 11

12

13

14 15

16

17

18 19

21

22

Retrieve information for the specified *key* associated with the process identified in the given **pmix_proc_t**. See Chapters 6 and 7 for details on rules governing retrieval of information. Information will be returned according to provided directives:

- In the absence of any directive, the returned **pmix_value_t** shall be an allocated memory object. The caller is responsible for releasing the object when done.
- If **PMIX_GET_POINTER_VALUES** is given, then the function shall return a pointer to a **pmix_value_t** in the PMIx library's memory that contains the requested information.
- If **PMIX_GET_STATIC_VALUES** is given, then the function shall return the information in the provided **pmix_value_t** pointer. In this case, the caller must provide storage for the structure and pass the pointer to that storage in the *val* parameter. If the implementation cannot return a static value, then the call to **PMIX_Get** must return the **PMIX_ERR_NOT_SUPPORTED** status.

This is a blocking operation - the caller will block until the retrieval rules of Chapters 6 or 7 are met.

The *info* array is used to pass user directives regarding the get operation.

o 5.3.1 PMIx Get nb

Summary

Nonblocking **PMIx** Get operation.

1	D141 10	Foi	rmat		
	PMIx v1.0	pmix_status_t			
2					
3		PMI	<pre>[x_Get_nb(const pmix_proc_t *proc, const char key[],</pre>		
4			<pre>const pmix_info_t info[], size_t ninfo,</pre>		
5			<pre>pmix_value_cbfunc_t cbfunc, void *cbdata);</pre>		
			C		
6		IN	proc		
7			Process identifier - a NULL value may be used in place of the caller's ID (handle)		
8		IN	key		
9			Key to retrieve (string)		
0		IN	info		
11			Array of info structures (array of handles)		
12		IN	ninfo		
13			Number of elements in the <i>info</i> array (integer)		
14		IN	cbfunc		
15			Callback function (function reference)		
16		IN	cbdata		
17			Data to be passed to the callback function (memory reference)		
18		Retu	urns one of the following:		
19		• P	MIX_SUCCESS, indicating that the request is being processed by the host environment - result		
20			vill be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback		
21			unction prior to returning from the API.		
22		• a	PMIx error constant indicating either an error in the input or that the request was immediately		
23			rocessed and failed - the <i>cbfunc</i> will <i>not</i> be called.		
24		If ex	xecuted, the status returned in the provided callback function will be one of the following		
25			stants:		
26		• P	MIX_SUCCESS The requested data has been returned.		
27			MIX_ERR_EXISTS_OUTSIDE_SCOPE The requested key exists, but was posted in a scope		
28		(5	see Section 7.1.1.1) that does not include the requester.		
29		• P	MIX_ERR_NOT_FOUND The requested data was not available.		
30		• a	non-zero PMIx error constant indicating a reason for the request's failure.		
		•	Required Attributes		
31		The	following attributes are required to be supported by all PMIx libraries:		
32		PMI	IX_OPTIONAL "pmix.optional" (bool)		
33			Look only in the client's local data store for the requested value - do not request data from		
34		the PMIx server if not found.			

1 PMIX_IMMEDIATE "pmix.immediate" (bool) 2 Specified operation should immediately return an error from the PMIx server if the requested data cannot be found - do not request it from the host RM. 3 PMIX_DATA_SCOPE "pmix.scope" (pmix_scope_t) 4 Scope of the data to be searched in a **PMIx_Get** call. 5 6 PMIX SESSION INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process. 7 PMIX_JOB_INFO "pmix.job.info" (bool) 8 Return information regarding the job realm corresponding to the namespace in the target 9 10 process' identifier. PMIX_APP_INFO "pmix.app.info" (bool) 11 12 Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If 13 information about an application other than the one containing the target process is desired, 14 then the attribute array must contain a PMIX_APPNUM attribute identifying the desired 15 target application. This is useful in cases where there are multiple applications and the 16 17 mapping of processes to applications is unclear. PMIX NODE INFO "pmix.node.info" (bool) 18 19 Return information from the node realm regarding the node upon which the specified 20 process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX NODEID or 21 22 **PMIX HOSTNAME** attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are 23 24 not known.. PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool) 25 Request that any pointers in the returned value point directly to values in the key-value store. 26 The user *must not* release any returned data pointers. 27 28 PMIX GET REFRESH CACHE "pmix.get.refresh" (bool) When retrieving data for a remote process, refresh the existing local data cache for the 29 process in case new values have been put and committed by the process since the last refresh. 30 Local process information is assumed to be automatically updated upon posting by the 31 32 process. A **NULL** key will cause all values associated with the process to be refreshed otherwise, only the indicated key will be updated. A process rank of 33 34 PMIX RANK WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may 35 have cached in their own local memory. 36 37

The following attributes are required for host environments that support this operation:

```
1
                PMIX_WAIT "pmix.wait" (int)
 2
                      Caller requests that the PMIx server wait until at least the specified number of values are
                      found (a value of zero indicates all and is the default).
 3
                                                  Optional Attributes
                The following attributes are optional for host environments that support this operation:
 4
 5
                PMIX_TIMEOUT "pmix.timeout" (int)
                      Time in seconds before the specified operation should time out (zero indicating infinite) and
 6
                      return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
 7
 8
                      caused by multiple layers (client, server, and host) simultaneously timing the operation.
                Description
 9
                The callback function will be executed once the retrieval rules of Chapters 6 or 7 are met. See
10
                PMIx Get for a full description. Note that the non-blocking form of this function cannot support
11
12
                the PMIX GET STATIC VALUES attribute as the user cannot pass in the required pointer to
                storage for the result.
13
              Retrieval attributes
    5.3.2
                The following attributes are defined for use by retrieval APIs:
15
                PMIX OPTIONAL "pmix.optional" (bool)
16
17
                      Look only in the client's local data store for the requested value - do not request data from
                      the PMIx server if not found.
18
                PMIX_IMMEDIATE "pmix.immediate" (bool)
19
20
                      Specified operation should immediately return an error from the PMIx server if the requested
                      data cannot be found - do not request it from the host RM.
21
                PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool)
22
                      Request that any pointers in the returned value point directly to values in the key-value store.
23
                      The user must not release any returned data pointers.
24
25
                PMIX GET STATIC VALUES "pmix.get.static" (bool)
                      Request that the data be returned in the provided storage location. The caller is responsible
26
                      for destructing the pmix_value_t using the PMIX_VALUE_DESTRUCT macro when
27
28
                      done.
29
                PMIX GET REFRESH CACHE "pmix.get.refresh" (bool)
```

When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh. Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of PMIX_RANK_WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.

PMIX_DATA_SCOPE "pmix.scope" (pmix_scope_t)

Scope of the data to be searched in a PMIx Get call.

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

PMIX_WAIT "pmix.wait" (int)

Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates *all* and is the default).

5.4 Query

As the level of interaction between applications and the host SMS grows, so too does the need for the application to query the SMS regarding its capabilities and state information. PMIx provides a generalized query interface for this purpose, along with a set of standardized attribute keys to support a range of requests. This includes requests to determine the status of scheduling queues and active allocations, the scope of API and attribute support offered by the SMS, namespaces of active jobs, location and information about a job's processes, and information regarding available resources.

An example use-case for the <code>PMIx_Query_info_nb</code> API is to ensure clean job completion. Time-shared systems frequently impose maximum run times when assigning jobs to resource allocations. To shut down gracefully (e.g., to write a checkpoint before termination) it is necessary for an application to periodically query the resource manager for the time remaining in its allocation. This is especially true on systems for which allocation times may be shortened or lengthened from the original time limit. Many resource managers provide APIs to dynamically obtain this information, but each API is specific to the resource manager.

PMIx supports this use-case by defining an attribute key (PMIX_TIME_REMAINING) that can be used with the PMIx_Query_info_nb interface to obtain the number of seconds remaining in the current job allocation. Note that one could alternatively use the PMIx_Register_event_handler API to register for an event indicating incipient job termination, and then use the PMIx_Job_control_nb API to request that the host SMS generate an event a specified amount of time prior to reaching the maximum run time. PMIx provides such alternate methods as a means of maximizing the probability of a host system supporting at least one method by which the application can obtain the desired service.

The following APIs support query of various session and environment values.

5.4.1 PMIx_Resolve_peers

Summary

1

4

10

11

12 13

14

15 16

17

18

19

20

21 22

23

24

26 27 Obtain the array of processes within the specified namespace that are executing on a given node.

Format PMIx v1.0 pmix_status_t PMIx_Resolve_peers(const char *nodename, const pmix_nspace_t nspace, pmix_proc_t **procs, size_t *nprocs);

IN nodename

Name of the node to query - **NULL** can be used to denote the current local node (string)

IN nspace

namespace (string)

OUT procs

Array of process structures (array of handles)

OUT nprocs

Number of elements in the *procs* array (integer)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Given a *nodename*, return the array of processes within the specified *nspace* that are executing on that node. If the *nspace* is **NULL**, then all processes on the node will be returned. If the specified node does not currently host any processes, then the returned array will be **NULL**, and *nprocs* will be zero. The caller is responsible for releasing the *procs* array when done with it. The **PMIX_PROC_FREE** macro is provided for this purpose.

5.4.2 PMIx Resolve nodes

Summary

Return a list of nodes hosting processes within the given namespace.

```
Format
1
   PMIx v1.0
2
               pmix status t
               PMIx_Resolve_nodes(const char *nspace, char **nodelist);
 3
4
               IN
                    nspace
 5
                    Namespace (string)
6
               OUT nodelist
 7
                    Comma-delimited list of nodenames (string)
8
               Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
               Description
9
10
               Given a nspace, return the list of nodes hosting processes within that namespace. The returned
11
               string will contain a comma-delimited list of nodenames. The caller is responsible for releasing the
12
               string when done with it.
    5.4.3
             PMIx Query info
               Summary
14
               Query information about the system in general.
15
16
               Format
   PMIx v4.0
17
               pmix status t
               PMIx Query info(pmix query t queries[], size t nqueries,
18
                                    pmix_info_t *info[], size_t *ninfo);
19
20
               IN
                    queries
21
                    Array of query structures (array of handles)
22
               IN
                    nqueries
                   Number of elements in the queries array (integer)
23
               INOUT info
24
                    Address where a pointer to an array of pmix_info_t containing the results of the query can
25
                   be returned (memory reference)
26
27
               INOUT ninfo
                    Address where the number of elements in info can be returned (handle)
28
               Returns one of the following:
29
30
               • PMIX SUCCESS All data was found and has been returned.
31
               • PMIX ERR NOT FOUND None of the requested data was available. The info array will be
32
                 NULL and ninfo zero.
```

1 2	• PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. The <i>info</i> array shall contain an element for each query key that returned a value.
3 4	• PMIX_ERR_NOT_SUPPORTED The host RM does not support this function. The <i>info</i> array will be NULL and <i>ninfo</i> zero.
5 6	• a non-zero PMIx error constant indicating a reason for the request's failure. The <i>info</i> array will be NULL and <i>ninfo</i> zero.
	Required Attributes
7 8	PMIx libraries and host environments that support this API are required to support the following attributes:
9 10	PMIX_QUERY_REFRESH_CACHE "pmix.qry.rfsh" (bool) Retrieve updated information from server. NO QUALIFIERS.
11 12	PMIX_SESSION_INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process.
13 14 15	<pre>PMIX_JOB_INFO "pmix.job.info" (bool) Return information regarding the job realm corresponding to the namespace in the target process' identifier.</pre>
16 17 18 19 20 21 22	PMIX_APP_INFO "pmix.app.info" (bool) Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.
23 24 25 26 27 28 29	PMIX_NODE_INFO "pmix.node.info" (bool) Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX_NODEID or PMIX_HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.
30 31 32 33	PMIX_PROC_INFO "pmix.proc.info" (bool) Return information regarding the target process. This attribute is technically not required as the PMIx_Get API specifically identifies the target process in its parameters. However, it is included here for completeness.
34	<pre>PMIX_PROCID "pmix.procid" (pmix_proc_t)</pre>

 Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix_proc_info_t** of a specified process. Only required when the request is for information on a specific process.

PMIX_NSPACE "pmix.nspace" (char*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX_RANK attribute. Only required when the request is for information on a specific process.

PMIX_RANK "pmix.rank" (pmix_rank_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX_NSPACE** attribute. Only required when the request is for information on a specific process.

PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.

PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)

Request attributes supported by the PMIx client library.

PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)

Request attributes supported by the PMIx server library.

PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)

Request attributes supported by the host environment.

PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)

Request attributes supported by the PMIx tool library functions.

Note that inclusion of both the PMIX_PROCID directive and either the PMIX_NSPACE or the PMIX_RANK attribute will return a PMIX_ERR_BAD_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix_query_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix_query_t structures, each referencing one process.

PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.

	→ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2	PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.
4 5 6	PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.
7 8	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
9 10 11 12	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.
13 14 15 16	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
17 18 19 20 21 22 23	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
24 25	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
26 27	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.
28 29 30 31	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (boo1) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
32 33	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
34 35	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
36	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)</pre>

1 String identifier of the allocation whose status is being requested. NO QUALIFIERS. 2 PMIX TIME REMAINING "pmix.time.remaining" (char*) Ouery number of seconds (uint32 t) remaining in allocation for the specified namespace. 3 OPTIONAL QUALIFIERS: PMIX NSPACE of the namespace whose info is being 4 requested (defaults to allocation containing the caller). 5 PMIX SERVER URI "pmix.srvr.uri" (char*) 6 7 URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's 8 PMIx connection. Defaults to requesting the information for the local PMIx server. 9 PMIX CLIENT AVG MEMORY "pmix.cl.mem.avg" (float) 10 Average Megabytes of memory used by client processes on node. OPTIONAL QUALIFERS: PMIX HOSTNAME or PMIX NODEID (defaults to caller's node). 11 PMIX DAEMON MEMORY "pmix.dmn.mem" (float) 12 Megabytes of memory currently used by the RM daemon on the node. OPTIONAL 13 QUALIFERS: PMIX HOSTNAME or PMIX NODEID (defaults to caller's node). 14 15 PMIX QUERY AUTHORIZATIONS "pmix.qry.auths" (bool) Return operations the PMIx tool is authorized to perform. NO QUALIFIERS. 16 17 PMIX PROC PID "pmix.ppid" (pid t) Operating system PID of specified process. 18 19 PMIX PROC STATE STATUS "pmix.proc.state" (pmix proc state t) State of the specified process as of the last report - may not be the actual current state based 20 21 on update rate.

Description

Query information about the system in general. This can include a list of active namespaces, fabric topology, etc. Also can be used to query node-specific info such as the list of peers executing on a given node. The host environment is responsible for exercising appropriate access control on the information.

The returned *status* indicates if requested data was found or not. The returned *info* array will contain a **PMIX_QUERY_RESULTS** element for each query of the *queries* array. If qualifiers were included in the query, then the first element of each results array shall contain the **PMIX_QUERY_QUALIFIERS** key with a **pmix_data_array_t** containing the qualifiers. The remaining **pmix_info_t** shall contain the results of the query, one entry for each key that was found. Note that duplicate keys in the *queries* array shall result in duplicate responses within the constraints of the accompanying qualifiers. The caller is responsible for releasing the returned array.

22

23

24

25

26

27

28 29

30 31

32

Advice to PMIx library implementers -

Information returned from PMIx_Query_info shall be locally cached so that retrieval by subsequent calls to PMIx_Get, PMIx_Query_info, or PMIx_Query_info_nb can succeed with minimal overhead. The local cache shall be checked prior to querying the PMIx server and/or the host environment. Queries that include the PMIX_QUERY_REFRESH_CACHE attribute shall bypass the local cache and retrieve a new value for the query, refreshing the values in the cache upon return.

5.4.4 PMIx_Query_info_nb

Summary

Query information about the system in general.

Format

PMIx v2.0

1

2

4

5

6

8

9

10

11

12 13

14

15

16

17 18

19

20

21 22

23

24

25

26

27 28

29 30 C

IN queries

Array of query structures (array of handles)

IN nqueries

Number of elements in the *queries* array (integer)

IN cbfunc

Callback function pmix_info_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed.

If executed, the status returned in the provided callback function will be one of the following constants:

• PMIX SUCCESS All data was found and has been returned.

1 2	 PMIX_ERR_NOT_FOUND None of the requested data was available. The info array will be NULL and ninfo zero.
3 4	• PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. The <i>info</i> array shall contain an element for each query key that returned a value.
5 6	• PMIX_ERR_NOT_SUPPORTED The host RM does not support this function. The <i>info</i> array will be NULL and <i>ninfo</i> zero.
7 8	• a non-zero PMIx error constant indicating a reason for the request's failure. The <i>info</i> array will be NULL and <i>ninfo</i> zero.
	▼ Required Attributes
9 10	PMIx libraries and host environments that support this API are required to support the following attributes:
11 12	PMIX_QUERY_REFRESH_CACHE "pmix.qry.rfsh" (bool) Retrieve updated information from server. NO QUALIFIERS.
13 14	PMIX_SESSION_INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process.
15 16 17	<pre>PMIX_JOB_INFO "pmix.job.info" (bool) Return information regarding the job realm corresponding to the namespace in the target process' identifier.</pre>
18 19 20 21 22 23 24	PMIX_APP_INFO "pmix.app.info" (bool) Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.
25 26 27 28 29 30 31	PMIX_NODE_INFO "pmix.node.info" (bool) Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the PMIX_NODEID or PMIX_HOSTNAME attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known
32 33 34	PMIX_PROC_INFO "pmix.proc.info" (bool) Return information regarding the target process. This attribute is technically not required as the PMIx_Get API specifically identifies the target process in its parameters. However, it is

PMIX_PROCID "pmix.procid" (pmix_proc_t)

included here for completeness.

35

 Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance. In this context, specifies the process ID whose information is being requested - e.g., a query asking for the **pmix_proc_info_t** of a specified process. Only required when the request is for information on a specific process.

PMIX_NSPACE "pmix.nspace" (char*)

Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Specifies the namespace of the process whose information is being requested. Must be accompanied by the PMIX_RANK attribute. Only required when the request is for information on a specific process.

PMIX_RANK "pmix.rank" (pmix_rank_t)

Process rank within the job, starting from zero. Specifies the rank of the process whose information is being requested. Must be accompanied by the **PMIX_NSPACE** attribute. Only required when the request is for information on a specific process.

PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)

Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.

PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)

Request attributes supported by the PMIx client library.

PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)

Request attributes supported by the PMIx server library.

PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)

Request attributes supported by the host environment.

PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)

Request attributes supported by the PMIx tool library functions.

Note that inclusion of both the PMIX_PROCID directive and either the PMIX_NSPACE or the PMIX_RANK attribute will return a PMIX_ERR_BAD_PARAM result, and that the inclusion of a process identifier must apply to all keys in that pmix_query_t. Queries for information on multiple specific processes therefore requires submitting multiple pmix_query_t structures, each referencing one process.

PMIx libraries are not required to directly support any other attributes for this function. However, all provided attributes must be passed to the host SMS daemon for processing. The PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making the request.

	▼ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2	PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.
4 5 6	PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.
7 8	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
9 10 11 12	<pre>PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.</pre>
13 14 15 16	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
17 18 19 20 21 22 23	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
24 25	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
26 27	<pre>PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.</pre>
28 29 30 31	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
32 33	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
34 35	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.

PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)

1	String identifier of the allocation whose status is being requested. NO QUALIFIERS.
2 3 4 5	PMIX_TIME_REMAINING "pmix.time.remaining" (char*) Query number of seconds (uint32_t) remaining in allocation for the specified namespace. OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).
6 7 8	PMIX_SERVER_URI "pmix.srvr.uri" (char*) URI of the PMIx server to be contacted. Requests the URI of the specified PMIx server's PMIx connection. Defaults to requesting the information for the local PMIx server.
9 0 1	PMIX_CLIENT_AVG_MEMORY "pmix.cl.mem.avg" (float) Average Megabytes of memory used by client processes on node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
2 3 4	PMIX_DAEMON_MEMORY "pmix.dmn.mem" (float) Megabytes of memory currently used by the RM daemon on the node. OPTIONAL QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
5 6	PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool) Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.
7 8	PMIX_PROC_PID "pmix.ppid" (pid_t) Operating system PID of specified process.
9 20 21	PMIX_PROC_STATE_STATUS "pmix.proc.state" (pmix_proc_state_t) State of the specified process as of the last report - may not be the actual current state based on update rate.
22	Description Non-blocking form of the PMIx_Query_info API.
5.4.5	Query-specific constants
25 26	PMIX_QUERY_PARTIAL_SUCCESS Some, but not all, of the requested information was returned.

1 5.4.6 Query attributes

2	Attributes used to direct behavior of the PMIx_Query_info APIs.
3	<pre>PMIX_QUERY_RESULTS "pmix.qry.res" (pmix_data_array_t)</pre>
4	Contains an array of query results for a given pmix_query_t passed to the
5	PMIx_Query_info APIs. If qualifiers were included in the query, then the first element
6	of the array shall be the PMIX_QUERY_QUALIFIERS attribute containing those qualifiers.
7	Each of the remaining elements of the array is a pmix_info_t containing the query key
8	and the corresponding value returned by the query. This attribute is solely for reporting
9	purposes and cannot be used in PMIx_Get or other query operations.
10	<pre>PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t)</pre>
11	Contains an array of qualifiers that were included in the query that produced the provided
12	results. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or
13	other query operations.
14	<pre>PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*)</pre>
15	Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.
16	<pre>PMIX_QUERY_SUPPORTED_QUALIFIERS "pmix.qry.quals" (char*)</pre>
17	Return comma-delimited list of qualifiers supported by a query on the provided key, instead
18	of actually performing the query on the key. NO QUALIFIERS.
19	PMIX_QUERY_REFRESH_CACHE "pmix.qry.rfsh" (bool)
20	Retrieve updated information from server. NO QUALIFIERS.
21	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*)</pre>
22	Request a comma-delimited list of active namespaces. NO QUALIFIERS.
23	<pre>PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*)</pre>
24	Return an array of active namespace information - each element will itself contain an array
25	including the namespace plus the command line of the application executing within it.
26	OPTIONAL QUALIFIERS: PMIX_NSPACE of specific namespace whose info is being
27	requested.
28	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t)</pre>
29	Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE
30	indicating the namespace whose status is being queried.
31	PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*)
32	Request a comma-delimited list of scheduler queues. NO QUALIFIERS.
33	PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*)
34	Returns status of a specified scheduler queue, expressed as a string. OPTIONAL
35	QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being
36	requested.
37	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)
38	Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each
39	process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER:
40	PMIX_NSPACE indicating the namespace whose process table is being queried.
/1	DMIY OHERY LOCAL DROC MARIE "pmix gry lotable" (chart)

1	Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each
2	process in the specified namespace executing on the same node as the requester, ordered by
3	process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace
4	whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME
5	indicating the host whose local process table is being queried. By default, the query assumes
6	that the host upon which the request was made is to be used.
7	PMIX_QUERY_AUTHORIZATIONS "pmix.qry.auths" (bool)
8	Return operations the PMIx tool is authorized to perform. NO QUALIFIERS.
9	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)
10	Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
11	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool)
12	Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.
13	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool)
14	Return information on memory usage for the processes indicated in the qualifiers.
15	OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of
16	specific process(es) whose memory usage is being requested.
17	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool)
18	Constrain the query to local information only. NO QUALIFIERS.
19	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool)
20	Report only average values for sampled information. NO QUALIFIERS.
21	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool)
22	Report minimum and maximum values. NO QUALIFIERS.
23	PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*)
24	String identifier of the allocation whose status is being requested. NO QUALIFIERS.
25	PMIX_TIME_REMAINING "pmix.time.remaining" (char*)
26	Query number of seconds (uint32_t) remaining in allocation for the specified namespace.
27	OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being
28	requested (defaults to allocation containing the caller).
29	PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool)
30	Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or
31	more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS,
32	PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.
33	<pre>PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t)</pre>
34	Return the number of process sets defined in the specified range (defaults to
35	PMIX_RANGE_SESSION).
36	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*)</pre>
37	Return a pmix_data_array_t containing an array of strings of the process set names
38	defined in the specified range (defaults to PMIX_RANGE_SESSION).
39	<pre>PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*)</pre>
40	Return an array of pmix_proc_t containing the members of the specified process set.
41	<pre>PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*)</pre>

```
Return an array of pmix_info_t, each element itself containing a
 1
2
                    PMIX SERVER INFO ARRAY entry holding all available data for a server on this node to
                    which the caller might be able to connect.
 3
 4
               PMIX_SERVER_INFO_ARRAY "pmix.srv.arr" (pmix_data_array_t)
                    Array of pmix_info_t about a given server, starting with its PMIX_NSPACE and
 5
                    including at least one of the rendezvous-required pieces of information.
 6
7
               These attributes are used to query memory available and used in the system.
               PMIX_AVAIL_PHYS_MEMORY "pmix.pmem" (uint64_t)
8
                    Total available physical memory on a node. OPTIONAL QUALIFERS: PMIX HOSTNAME
9
10
                    or PMIX NODEID (defaults to caller's node).
               PMIX DAEMON_MEMORY "pmix.dmn.mem" (float)
11
12
                    Megabytes of memory currently used by the RM daemon on the node. OPTIONAL
                    QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
13
               PMIX CLIENT AVG MEMORY "pmix.cl.mem.avg" (float)
14
                    Average Megabytes of memory used by client processes on node. OPTIONAL
15
                    QUALIFERS: PMIX_HOSTNAME or PMIX_NODEID (defaults to caller's node).
16
17
               The following attributes are used as qualifiers in queries regarding attribute support within the
18
               PMIx implementation and/or the host environment:
               PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool)
19
                    Request a list of functions supported by the PMIx client library.
20
               PMIX CLIENT ATTRIBUTES "pmix.client.attrs" (bool)
21
                    Request attributes supported by the PMIx client library.
22
               PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool)
23
                    Request a list of functions supported by the PMIx server library.
24
               PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)
25
                    Request attributes supported by the PMIx server library.
26
27
               PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)
28
                    Request a list of functions supported by the host environment.
29
               PMIX HOST ATTRIBUTES "pmix.host.attrs" (bool)
                    Request attributes supported by the host environment.
30
               PMIX TOOL FUNCTIONS "pmix.tool.fns" (bool)
31
                    Request a list of functions supported by the PMIx tool library.
32
               PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)
33
                    Request attributes supported by the PMIx tool library functions.
34
             Query Structure
    5.4.7
36
               The pmix query t structure is used by the PMIx Query info APIs to describe a single
```

The **pmix_query_t** structure is used by the **PMIx_Query_info** APIs to describe a single query operation.

PMIx v2.0

```
1
               typedef struct pmix_query {
 2
                    char **keys;
 3
                    pmix_info_t *qualifiers;
                    size_t nqual;
 4
 5
               } pmix_query_t;
               where:
6
 7
               • keys is a NULL-terminated argv-style array of strings
               • qualifiers is an array of pmix_info_t describing constraints on the query
8
9
               • ngual is the number of elements in the qualifiers array
    5.4.7.1
              Query structure support macros
               The following macros are provided to support the pmix_query_t structure.
11
               Initialize the query structure
12
               Initialize the pmix_query_t fields
13
   PMIx v2.0
14
               PMIX_QUERY_CONSTRUCT (m)
               IN
15
                    m
                   Pointer to the structure to be initialized (pointer to pmix_query_t
16
               Destruct the query structure
17
               Destruct the pmix_query_t fields
18
   PMIx v2.0
19
               PMIX_QUERY_DESTRUCT (m)
20
               IN
21
                   Pointer to the structure to be destructed (pointer to pmix_query_t
```

1 2	Create a query array Allocate and initialize an array of pmix_query_t structures		
PMIx v2.0			
3	PMIX_QUERY_CREATE (m, n)		
	C		
4 5 6 7	INOUT m Address where the pointer to the array of pmix_query_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)		
8	Free a query structure		
9 <i>PMIx v4.</i> 0	Release a pmix_query_t structure C		
10	PMIX_QUERY_RELEASE (m)		
11 12	IN m Pointer to a pmix_query_t structure (handle)		
13 14	Free a query array Release an array of pmix_query_t structures		
<i>PMIx v2.</i> 0	PMIX_QUERY_FREE (m, n)		
16 17 18 19	 IN m Pointer to the array of pmix_query_t structures (handle) IN n Number of structures in the array (size_t) 		
20 21 22	Create the info array of query qualifiers Create an array of pmix_info_t structures for passing query qualifiers, updating the nqual field of the pmix_query_t structure.		
PMIx v2.2	C		
23	PMIX_QUERY_QUALIFIERS_CREATE (m, n)		
	C		
24 25	IN m Pointer to the pmix_query_t structure (handle)		
26 27	IN n		
<u>~ 1</u>	Number of qualifiers to be allocated (size_t)		

5.5 Using Get vs Query

Both **PMIx_Get** and **PMIx_Query_info** can be used to retrieve information about the system. In general, the *get* operation should be used to retrieve:

- information provided by the host environment at time of job start. This includes information on the number of processes in the job, their location, and possibly their communication endpoints.
- information posted by processes via the **PMIx_Put** function.

This information is largely considered to be *static*, although this will not necessarily be true for environments supporting dynamic programming models or fault tolerance. Note that the **PMIx_Get** function only accesses information about execution environments - i.e., its scope is limited to values pertaining to a specific *session*, *job*, *application*, *process*, or *node*. It cannot be used to obtain information about areas such as the status of queues in the WLM.

In contrast, the *query* option should be used to access:

- system-level information (such as the available WLM queues) that would generally not be included in job-level information provided at job start.
- dynamic information such as application and queue status, and resource utilization statistics.
 Note that the PMIX_QUERY_REFRESH_CACHE attribute must be provided on each query to ensure current data is returned.
- information created post job start, such as process tables.
- information requiring more complex search criteria than supported by the simpler PMIx_Get API.
- queries focused on retrieving multi-attribute blocks of data with a single request, thus bypassing the single-key limitation of the **PMIx_Get** API.

In theory, all information can be accessed via PMIx_Query_info as the local cache is typically the same datastore searched by PMIx_Get. However, in practice, the overhead associated with the query operation may (depending upon implementation) be higher than the simpler get operation due to the need to construct and process the more complex pmix_query_t structure. Thus, requests for a single key value are likely to be accomplished faster with PMIx_Get versus the query operation.

5.6 Accessing attribute support information

Information as to which attributes are supported by either the PMIx implementation or its host environment can be obtained via the PMIx_Query_info APIs. The PMIX_QUERY_ATTRIBUTE_SUPPORT attribute must be listed as the first entry in the *keys* field of the pmix_query_t structure, followed by the name of the function whose attribute support is being requested - support for multiple functions can be requested simultaneously by simply adding

the function names to the array of *keys*. Function names *must* be given as user-level API names - e.g., "PMIx_Get", "PMIx_server_setup_application", or "PMIx_tool_attach_to_server".

The desired levels of attribute support are provided as qualifiers. Multiple levels can be requested simultaneously by simply adding elements to the *qualifiers* array. Each qualifier should contain the desired level attribute with the boolean value set to indicate whether or not that level is to be included in the returned information. Failure to provide any levels is equivalent to a request for all levels. Supported levels include:

- PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool)

 Request a list of functions supported by the PMIx client library.
- PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool)

 Request attributes supported by the PMIx client library.
- PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool)

 Request a list of functions supported by the PMIx server library.
- PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool)
 Request attributes supported by the PMIx server library.
- PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool)

 Request a list of functions supported by the host environment.
- PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool)

 Request attributes supported by the host environment.
- PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool)

 Request a list of functions supported by the PMIx tool library.
- PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool)

 Request attributes supported by the PMIx tool library functions.

Unlike other queries, queries for attribute support can result in the number of returned <code>pmix_info_t</code> structures being different from the number of queries. Each element in the returned array will correspond to a pair of specified attribute level and function in the query, where the <code>key</code> is the function and the <code>value</code> contains a <code>pmix_data_array_t</code> of <code>pmix_info_t</code>. Each element of the array is marked by a <code>key</code> indicating the requested attribute <code>level</code> with a <code>value</code> composed of a <code>pmix_data_array_t</code> of <code>pmix_regattr_t</code>, each describing a supported attribute for that function, as illustrated in Fig. 5.1 below where the requestor asked for supported attributes of <code>PMIx_Get</code> at the <code>client</code> and <code>server</code> levels, plus attributes of <code>PMIx_Allocation_request</code> at all levels.

The array of returned structures, and their child arrays, are subject to the return rules for the **PMIx_Query_info_nb** API. For example, a request for supported attributes of the **PMIx_Get** function that includes the *host* level will return values for the *client* and *server* levels, plus an array element with a *key* of **PMIX_HOST_ATTRIBUTES** and a value type of **PMIX_UNDEF** indicating that no attributes are supported at that level.




Figure 5.1.: Returned information hierarchy for attribute support request

CHAPTER 6

Reserved Keys

Reserved keys are keys whose string representation begin with a prefix of "pmix". By definition, reserved keys are provided by the host environment and the PMIx server, and are required to be available at client start of execution. PMIx clients and tools are therefore prohibited from posting reserved keys using the PMIx_Put API.

PMIx implementations may choose to define their own custom-prefixed keys which may adhere to either the *reserved* or the *non-reserved* retrieval rules at the discretion of the implementation. Implementations may choose to provide such custom keys at client start of execution, but this is not required.

Host environments may also opt to define their own custom keys. However, PMIx implementations are unlikely to recognize such host-defined keys and will therefore treat them according to the *non-reserved* rules described in Chapter 7. Users are advised to check both the local PMIx implementation and host environment documentation for a list of any custom prefixes they must avoid, and to learn of any non-standard keys that may require special handling.

4 6.1 Data realms

PMIx information spans a wide range of sources. In some cases, there are multiple overlapping sources for the same type of data - e.g., the session, job, and application can each provide information on the number of nodes involved in their respective area. In order to resolve the ambiguity, a *data realm* is used to identify the scope to which the referenced data applies. Thus, a reference to an attribute that isn't specific to a realm (e.g., the PMIX_NUM_NODES attribute) must be accompanied by a corresponding attribute identifying the realm to which the request pertains if it differs from the default.

PMIx defines five *data realms* to resolve the ambiguities, as captured in the following attributes used in **PMIx Get** for retrieving information from each of the realms:

PMIX_SESSION_INFO "pmix.ssn.info" (bool)

Return information regarding the session realm of the target process.

PMIX_JOB_INFO "pmix.job.info" (bool)

Return information regarding the job realm corresponding to the namespace in the target process' identifier.

PMIX_APP_INFO "pmix.app.info" (bool)

Return information regarding the application realm to which the target process belongs - the namespace of the target process serves to identify the job containing the target application. If information about an application other than the one containing the target process is desired, then the attribute array must contain a PMIX_APPNUM attribute identifying the desired target application. This is useful in cases where there are multiple applications and the mapping of processes to applications is unclear.

PMIX PROC INFO "pmix.proc.info" (bool)

Return information regarding the target process. This attribute is technically not required as the **PMIx_Get** API specifically identifies the target process in its parameters. However, it is included here for completeness.

PMIX NODE INFO "pmix.node.info" (bool)

Return information from the node realm regarding the node upon which the specified process is executing. If information about a node other than the one containing the specified process is desired, then the attribute array must also contain either the **PMIX_NODEID** or **PMIX_HOSTNAME** attribute identifying the desired target. This is useful for requesting information about a specific node even if the identity of processes running on that node are not known.

Advice to users

If information about a session other than the one containing the requesting process is desired, then the attribute array must contain a **PMIX_SESSION_ID** attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

The PMIx server has corresponding attributes the host can use to specify the realm of information that it provides during namespace registration (see Section 16.2.3.2).

4 6.1.1 Session realm attributes

 If information about a session other than the one containing the requesting process is desired, then the *info* array passed to **PMIx_Get** must contain a **PMIX_SESSION_ID** attribute identifying the desired target session. This is required as many environments only guarantee unique namespaces within a session, and not across sessions.

Note that the *proc* argument of **PMIx_Get** is ignored when referencing session-related information.

Session-level information includes the following attributes:

```
PMIX_SESSION_ID "pmix.session.id" (uint32_t)
Session identifier assigned by the scheduler.

PMIX_CLUSTER_ID "pmix.clid" (char*)
A string name for the cluster this allocation is on.

PMIX_UNIV_SIZE "pmix.univ.size" (uint32 t)
```

1 2 3 4 5 6 7 8	Maximum number of process that can be simultaneously executing in a session. Note that this attribute is equivalent to the PMIX_MAX_PROCS attribute for the session realm - it is included in the PMIx Standard for historical reasons. PMIX_TMPDIR "pmix.tmpdir" (char*) Full path to the top-level temporary directory assigned to the session. PMIX_TDIR_RMCLEAN "pmix.tdir.rmclean" (bool) Resource Manager will cleanup assigned temporary directory trees. PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) Fully Qualified Domain Names (FQDNs) are being retained by the PMIx library.
10	The following attributes are used to describe the RM - these are values assigned by the host
11	environment to the session:
12	PMIX_RM_NAME "pmix.rm.name" (char*)
13	String name of the RM.
14	PMIX_RM_VERSION "pmix.rm.version" (char*)
15	RM version string.
16	The remaining session-related information can only be retrieved by including the
17	PMIX_SESSION_INFO attribute in the <i>info</i> array passed to PMIx_Get:
18	PMIX_ALLOCATED_NODELIST "pmix.alist" (char*)
19	Comma-delimited list or regular expression of all nodes in the specified realm regardless of
20	whether or not they currently host processes. Defaults to the <i>job</i> realm.
21	<pre>PMIX_NUM_ALLOCATED_NODES "pmix.num.anodes" (uint32_t)</pre>
22	Number of nodes in the specified realm regardless of whether or not they currently host
23	processes. Defaults to the <i>job</i> realm.
24	<pre>PMIX_MAX_PROCS "pmix.max.size" (uint32_t)</pre>
25	Maximum number of processes that can be executed in the specified realm. Typically, this is
26	a constraint imposed by a scheduler or by user settings in a hostfile or other resource
27	description. Defaults to the <i>job</i> realm.
28	<pre>PMIX_NODE_LIST "pmix.nlist" (char*)</pre>
29	Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults
30	to the <i>job</i> realm.
31	<pre>PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)</pre>
32	Maximum number of processes that can simultaneously be executing in the specified realm.
33	Note that this attribute is the equivalent to PMIX_MAX_PROCS - it is included in the PMIx
34	Standard for historical reasons. Defaults to the <i>job</i> realm.
35	<pre>PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)</pre>
36	Number of nodes currently hosting processes in the specified realm. Defaults to the <i>job</i>
37	realm.
38	PMIX_NODE_MAP "pmix.nmap" (char*)
39	Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2
40	for an explanation of its generation. Defaults to the <i>job</i> realm.

1 PMIX_NODE_MAP_RAW "pmix.nmap.raw" (char*) 2 Comma-delimited list of nodes containing procs within the specified realm. Defaults to the 3 *job* realm. 4 PMIX_PROC_MAP "pmix.pmap" (char*) Regular expression describing processes on each node in the specified realm - see 16.2.3.2 5 for an explanation of its generation. Defaults to the *job* realm. 6 7 PMIX PROC MAP RAW "pmix.pmap.raw" (char*) Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks 8 9 on the corresponding node within the specified realm. Defaults to the *job* realm. PMIX ANL MAP "pmix.anlmap" (char*) 10 11 Process map equivalent to PMIX PROC MAP expressed in Argonne National Laboratory's 12 PMI-1/PMI-2 notation. Defaults to the *job* realm. 6.1.2 Job realm attributes 13 Job-related information is retrieved by including the namespace of the target job and a rank of 14 **PMIX RANK WILDCARD** in the *proc* argument passed to **PMIx_Get**. If desired for code clarity, 15 16 the caller can also include the **PMIX JOB INFO** attribute in the *info* array, though this is not 17 required. If information is requested about a namespace in a session other than the one containing the requesting process, then the *info* array must contain a **PMIX_SESSION_ID** attribute 18 identifying the desired target session. This is required as many environments only guarantee unique 19 20 namespaces within a session, and not across sessions. Job-level information includes the following attributes: 21 22 PMIX NSPACE "pmix.nspace" (char*) 23 Namespace of the job - may be a numerical value expressed as a string, but is often an 24 alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. 25 26 PMIX JOBID "pmix.jobid" (char*) Job identifier assigned by the scheduler to the specified job - may be identical to the 27 28 namespace, but is often a numerical value expressed as a string (e.g., "12345.3"). PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t) 29 Starting global rank of the specified job. 30 PMIX MAX PROCS "pmix.max.size" (uint32_t) 31 Maximum number of processes that can be executed in the specified realm. Typically, this is 32 a constraint imposed by a scheduler or by user settings in a hostfile or other resource 33 description. Defaults to the job realm. In this context, this is the maximum number of 34 processes that can be simultaneously executed in the specified job, which may be a subset of 35

PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)

the number allocated to the overall session.

36 37

38

39

40

Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to **PMIX_MAX_PROCS** - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the

maximum number of process that can be simultaneously executing within the specified job, which may be a subset of the number allocated to the overall session. Jobs may reserve a subset of their assigned maximum processes for dynamic operations such as **PMIx_Spawn**.

PMIX NUM NODES "pmix.num.nodes" (uint32 t)

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the number of nodes currently hosting processes in the specified job, which may be a subset of the nodes allocated to the overall session. Jobs may reserve a subset of their assigned nodes for dynamic operations such as **PMIx_Spawn** - i.e., not all nodes may have executing processes from this job at a given point in time.

PMIX NODE MAP "pmix.nmap" (char*)

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression of nodes currently hosting processes in the specified job.

PMIX_NODE_LIST "pmix.nlist" (char*)

Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the comma-delimited list of nodes currently hosting processes in the specified job.

PMIX_PROC_MAP "pmix.pmap" (char*)

Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression describing processes on each node in the specified job.

PMIX_ANL_MAP "pmix.anlmap" (char*)

Process map equivalent to PMIX_PROC_MAP expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the *job* realm. In this context, this is the process mapping in Argonne National Laboratory's PMI-1/PMI-2 notation of the processes in the specified job.

PMIX_CMD_LINE "pmix.cmd.line" (char*)

Command line used to execute the specified job (e.g., "mpirun -n 2 -map-by foo ./myapp : -n 4 ./myapp2").

PMIX_NSDIR "pmix.nsdir" (char*)

Full path to the temporary directory assigned to the specified job, under PMIX_TMPDIR.

PMIX JOB SIZE "pmix.job.size" (uint32 t)

Total number of processes in the specified job across all contained applications. Note that this value can be different from **PMIX_MAX_PROCS**. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic programming models may support adding and removing processes from a running *job* on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.

PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t)

Number of applications in the specified job.

6.1.3 Application realm attributes

Application-related information can only be retrieved by including the PMIX_APP_INFO attribute in the *info* array passed to PMIx_Get. If the PMIX_APPNUM qualifier is given, then the query shall return the corresponding value for the given application within the namespace specified in the *proc* argument of the query (a NULL value for the *proc* argument equates to the namespace of the caller). If the PMIX_APPNUM qualifier is not included, then the retrieval shall default to the application containing the specified process. If the rank of the specified process is PMIX_RANK_WILDCARD, then the application number shall default to that of the calling process if the namespace is its own job, or a value of zero if the namespace is that of a different job.

Application-level information includes the following attributes:

PMIX_APPNUM "pmix.appnum" (uint32_t)

The application number within the job in which the specified process is a member.

PMIX_NUM_NODES "pmix.num.nodes" (uint32_t)

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm. In this context, this is the number of nodes currently hosting processes in the specified application, which may be a subset of the nodes allocated to the overall session.

PMIX_APPLDR "pmix.aldr" (pmix_rank_t)

Lowest rank in the specified application.

PMIX_APP_SIZE "pmix.app.size" (uint32_t)

Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.

PMIX_APP_ARGV "pmix.app.argv" (char*)

Consolidated argy passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3").

PMIX_MAX_PROCS "pmix.max.size" (uint32_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. In this context, this is the maximum number of processes that can be executed in the specified application, which may be a subset of the number allocated to the overall session and job.

PMIX_NUM_SLOTS "pmix.num.slots" (uint32_t)

Maximum number of processes that can simultaneously be executing in the specified realm. Note that this attribute is the equivalent to **PMIX_MAX_PROCS** - it is included in the PMIx Standard for historical reasons. Defaults to the *job* realm. In this context, this is the number of slots assigned to the specified application, which may be a subset of the slots allocated to the overall session and job.

PMIX NODE MAP "pmix.nmap" (char*)

Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm. In this context, this is the regular expression of nodes currently hosting processes in the specified application.

1 PMIX_NODE_LIST "pmix.nlist" (char*) 2 Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the job realm. In this context, this is the comma-delimited list of nodes currently hosting 3 processes in the specified application. 4 5 PMIX PROC MAP "pmix.pmap" (char*) 6 Regular expression describing processes on each node in the specified realm - see 16.2.3.2 7 for an explanation of its generation. Defaults to the job realm. In this context, this is the 8 regular expression describing processes on each node in the specified application. 9 PMIX_APP_MAP_TYPE "pmix.apmap.type" (char*) Type of mapping used to layout the application (e.g., cyclic). 10 PMIX_APP_MAP_REGEX "pmix.apmap.regex" (char*) 11 Regular expression describing the result of the process mapping. 12 6.1.4 Process realm attributes 13 14 Process-related information is retrieved by referencing the namespace and rank of the target process 15 in the call to PMIx Get. If information is requested about a process in a session other than the one containing the requesting process, then an attribute identifying the target session must be provided. 16 17 This is required as many environments only guarantee unique namespaces within a session, and not across sessions. 18 19 Process-level information includes the following attributes: 20 PMIX_APPNUM "pmix.appnum" (uint32_t) The application number within the job in which the specified process is a member. 21 22 PMIX RANK "pmix.rank" (pmix rank t) 23 Process rank within the job, starting from zero. PMIX GLOBAL RANK "pmix.grank" (pmix rank t) 24 25 Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and 26 27 end at random times, this is defined as a continually growing number - i.e., it is not 28 dynamically adjusted as individual jobs and processes are started or terminated. 29 PMIX_APP_RANK "pmix.apprank" (pmix_rank_t) 30 Rank of the specified process within its application. PMIX_PARENT_ID "pmix.parent" (pmix_proc_t) 31 Process identifier of the parent process of the specified process - typically used to identify 32 the application process that caused the job containing the specified process to be spawned 33 (e.g., the process that called **PMIx** Spawn). 34 35 PMIX_EXIT_CODE "pmix.exit.code" (int)

PMIX PROCID "pmix.procid" (pmix proc t)

Exit code returned when the specified process terminated.

Process identifier. Used as a key in **PMIx_Get** to retrieve the caller's own process identifier in a portion of the program that doesn't have access to the memory location in which it was originally stored (e.g., due to a call to **PMIx_Init**). The process identifier in the **PMIx_Get** call is ignored in this instance.

PMIX_LOCAL_RANK "pmix.lrank" (uint16_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

PMIX NODE RANK "pmix.nrank" (uint16 t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t)

Rank of the specified process on the *package* where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to Processing Units (PUs) within a single specific package cannot have a package rank.

PMIX_PROC_PID "pmix.ppid" (pid_t)

Operating system PID of specified process.

PMIX_PROCDIR "pmix.pdir" (char*)

Full path to the subdirectory under **PMIX NSDIR** assigned to the specified process.

PMIX CPUSET "pmix.cpuset" (char*)

A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.

PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*)

Bitmap applied to the process upon launch.

PMIX_CREDENTIAL "pmix.cred" (char*)

Security credential assigned to the process.

PMIX SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to **PMIx_Spawn**. Lack of inclusion (i.e., a return status of **PMIX_ERR_NOT_FOUND**) corresponds to a value of **false** for this attribute.

PMIX_REINCARNATION "pmix.reinc" (uint32_t)

Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5

In addition, process-level information includes functional attributes directly associated with a process - for example, the process-related fabric attributes included in Section 14.3 or the distance attributes of Section 11.4.11.

6.1.5 Node realm keys

2

3

4 5

6

7

8

9

10

11 12

13

14

15 16

17

18

19

20

21

22

23

24 25

26

27

28

29

30 31

32

33

34 35

36

37 38

39 40 Information regarding the local node can be retrieved by directly requesting the node realm key in the call to **PMIx Get** - the keys for node-related information are not shared across other realms. The target process identifier will be ignored for keys that are not dependent upon it. Information about a node other than the local node can be retrieved by specifying the PMIX NODE INFO attribute in the info array along with either the PMIX HOSTNAME or PMIX NODEID qualifiers for the node of interest.

Node-level information includes the following keys:

PMIX_HOSTNAME "pmix.hname" (char*)

Name of the host, as returned by the **gethostname** utility or its equivalent.

PMIX HOSTNAME ALIASES "pmix.alias" (char*)

Comma-delimited list of names by which the target node is known.

PMIX_NODEID "pmix.nodeid" (uint32_t)

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the PMIX HOSTNAME of the node - i.e., users can interchangeably reference the same location using either the PMIX HOSTNAME or corresponding PMIX NODEID.

PMIX_NODE_SIZE "pmix.node.size" (uint32_t)

Number of processes across all jobs that are executing upon the node.

PMIX AVAIL PHYS MEMORY "pmix.pmem" (uint64 t)

Total available physical memory on a node.

The following attributes only return information regarding the caller's node - any node-related qualifiers shall be ignored. In addition, these attributes require specification of the namespace in the target process identifier except where noted - the value of the rank is ignored in all cases.

PMIX_LOCAL_PEERS "pmix.lpeers" (char*)

Comma-delimited list of ranks that are executing on the local node within the specified namespace – shortcut for **PMIx_Resolve_peers** for the local node.

PMIX LOCAL PROCS "pmix.lprocs" (pmix proc t array)

Array of pmix proc t of all processes executing on the local node – shortcut for PMIx Resolve peers for the local node and a NULL namespace argument. The process identifier is ignored for this attribute.

PMIX_LOCALLDR "pmix.lldr" (pmix_rank_t)

Lowest rank within the specified job on the node (defaults to current node in absence of PMIX_HOSTNAME or PMIX_NODEID qualifier).

PMIX_LOCAL_CPUSETS "pmix.lcpus" (pmix_data_array_t)

A pmix_data_array_t array of string representations of the PU binding bitmaps applied to each local *peer* on the caller's node upon launch. Each string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by PMIX LOCAL PEERS for that namespace.

PMIX_LOCAL_SIZE "pmix.local.size" (uint32_t)

Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the **PMIX_APP_INFO** and the **PMIX_APPNUM** qualifiers are given.

In addition, node-level information includes functional attributes directly associated with a node-for example, the node-related fabric attributes included in Section 14.3.

6.2 Retrieval rules for reserved keys

 The retrieval rules for reserved keys are relatively simple as the keys are required, by definition, to be available when the client begins execution. Accordingly, **PMIx_Get** for a reserved key first checks the local PMIx Client cache (per the data realm rules of the prior section) for the target key. If the information is not found, then the **PMIX_ERR_NOT_FOUND** error constant is returned unless the target process belongs to a different namespace from that of the requester.

In the case where the target and requester's namespaces differ, then the request is forwarded to the local PMIx server. Upon receiving the request, the server shall check its data storage for the specified namespace. If it already knows about this namespace, then it shall attempt to lookup the specified key, returning the value if it is found or the PMIX_ERR_NOT_FOUND error constant.

If the server does not have a copy of the information for the specified namespace, then the server shall take one of the following actions:

- 1. If the request included the **PMIX_IMMEDIATE** attribute, then the server will respond to the client with the **PMIX_ERR_NOT_FOUND** status.
- 2. If the host has provided the Direct Business Card Exchange (DBCX) module function interface (pmix_server_dmodex_req_fn_t), then the server shall pass the request to its host for servicing. The host is responsible for identifying a source of information on the specified namespace and retrieving it. The host is required to retrieve all of the information regarding the target namespace and return it to the requesting server in anticipation of follow-on requests. If the host cannot retrieve the namespace information, then it must respond with the PMIX_ERR_NOT_FOUND error constant unless the PMIX_TIMEOUT is given and reached (in which case, the host must respond with the PMIX_ERR_TIMEOUT constant).

Once the the PMIx server receives the namespace information, the server shall search it (again adhering to the prior data realm rules) for the requested key, returning the value if it is found or the PMIX_ERR_NOT_FOUND error constant.

3. If the host does not support the DBCX interface, then the server will respond to the client with the PMIX_ERR_NOT_FOUND status

6.2.1 Accessing information: examples

This section provides examples illustrating methods for accessing information from the various realms. The intent of the examples is not to provide comprehensive coding guidance, but rather to further illustrate the use of **PMIx_Get** for obtaining information on a *session*, *job*, *application*, *process*, and *node*.

6.2.1.1 Session-level information

 The **PMIx_Get** API does not include an argument for specifying the *session* associated with the information being requested. Thus, requests for keys that are not specifically for session-level information must be accompanied by the **PMIX_SESSION_INFO** qualifier.

Example requests are shown below:

```
pmix_info_t info;
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc, wildcard;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #slots in our session */
PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
rc = PMIx_Get(&wildcard, PMIX_UNIV_SIZE, NULL, 0, &value);

/* get the #nodes in our session */
PMIX_INFO_LOAD(&info, PMIX_SESSION_INFO, NULL, PMIX_BOOL);
rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
```

Information regarding a different session can be requested by adding the **PMIX_SESSION_ID** attribute identifying the target session. In this case, the *proc* argument to **PMIx_Get** will be ignored:

```
pmix_info_t info[2];
pmix_value_t *value;
pmix_status_t rc;
pmix_proc_t myproc;
uint32_t sid;

/* initialize the client library */
PMIx_Init(&myproc, NULL, 0);

/* get the #nodes in a different session */
sid = 12345;
PMIX_INFO_LOAD(&info[0], PMIX_SESSION_INFO, NULL, PMIX_BOOL);
PMIX_INFO_LOAD(&info[1], PMIX_SESSION_ID, &sid, PMIX_UINT32);
rc = PMIx_Get(NULL, PMIX_NUM_NODES, info, 2, &value);
```

6.2.1.2 Job-level information

2

3

20

21

Information regarding a job can be obtained by the methods detailed in Section 6.1.2. Example requests are shown below:

```
4
            pmix_info_t info;
5
            pmix value t *value;
6
            pmix status t rc;
7
            pmix_proc_t myproc, wildcard;
8
9
            /* initialize the client library */
10
            PMIx Init(&myproc, NULL, 0);
11
12
            /* get the #apps in our job */
            PMIX_PROC_LOAD(&wildcard, myproc.nspace, PMIX_RANK_WILDCARD);
13
            rc = PMIx_Get(&wildcard, PMIX_JOB_NUM_APPS, NULL, 0, &value);
14
15
16
            /* get the #nodes in our job */
17
            PMIX_INFO_LOAD(&info, PMIX_JOB_INFO, NULL, PMIX_BOOL);
18
            rc = PMIx_Get(&wildcard, PMIX_NUM_NODES, &info, 1, &value);
```

6.2.1.3 Application-level information

Information regarding an application can be obtained by the methods described in Section 6.1.3. Example requests are shown below:

```
22
            pmix info t info;
23
            pmix_value_t *value;
            pmix_status_t rc;
24
25
            pmix_proc_t myproc, otherproc;
26
            uint32_t appsize, appnum;
27
28
            /* initialize the client library */
29
            PMIx_Init(&myproc, NULL, 0);
30
            /* get the #processes in our application */
31
32
            rc = PMIx Get(&myproc, PMIX APP SIZE, NULL, 0, &value);
33
            appsize = value->data.uint32;
34
35
            /* get the #nodes in an application containing "otherproc".
```

```
* For this use-case, assume that we are in the first application
1
2
             * and we want the #nodes in the second application - use the
             * rank of the first process in that application, remembering
3
4
             * that ranks start at zero */
5
            PMIX PROC LOAD (&otherproc, myproc.nspace, appsize);
6
7
            /* Since "otherproc" refers to a process in the second application,
8
             * we can simply mark that we want the info for this key from the
9
             * application realm */
            PMIX_INFO_LOAD(&info, PMIX_APP_INFO, NULL, PMIX_BOOL);
10
            rc = PMIx_Get(&otherproc, PMIX_NUM_NODES, &info, 1, &value);
11
12
13
            /* alternatively, we can directly ask for the #nodes in
14
             * the second application in our job, again remembering that
15
             * application numbers start with zero. Since we are asking
             * for application realm information about a specific appnum
16
17
             * within our own namespace, the process identifier can be NULL */
18
            appnum = 1;
19
            PMIX INFO LOAD (&appinfo[0], PMIX APP INFO, NULL, PMIX BOOL);
20
            PMIX_INFO_LOAD (&appinfo[1], PMIX_APPNUM, &appnum, PMIX_UINT32);
            rc = PMIx_Get(NULL, PMIX_NUM_NODES, appinfo, 2, &value);
21
```

2 6.2.1.4 Process-level information

Process-level information is accessed by providing the namespace and rank of the target process. In the absence of any directive as to the level of information being requested, the PMIx library will always return the process-level value. See Section 6.1.4 for details.

26 6.2.1.5 Node-level information

Information regarding a node within the system can be obtained by the methods described in Section 6.1.5. Example requests are shown below:

```
29
            pmix_info_t info[2];
            pmix value t *value;
30
            pmix status t rc;
31
32
            pmix proc t myproc, otherproc;
            uint32_t nodeid;
33
34
35
            /* initialize the client library */
36
            PMIx_Init(&myproc, NULL, 0);
37
            /* get the #procs on our node */
38
```

23 24

25

27

```
1
           rc = PMIx_Get(&myproc, PMIX_NODE_SIZE, NULL, 0, &value);
2
           /* get the #slots on another node */
3
4
           PMIX_INFO_LOAD(&info[0], PMIX_NODE_INFO, NULL, PMIX_BOOL);
5
           PMIX_INFO_LOAD(&info[1], PMIX_HOSTNAME, "remotehost", PMIX_STRING);
6
           rc = PMIx_Get(NULL, PMIX_MAX_PROCS, info, 2, &value);
7
8
           /* get the total #procs on the remote node - note that we don't
9
             * actually need to include the "PMIX_NODE_INFO" attribute here,
10
             * but (a) it does no harm and (b) it allowed us to simply reuse
11
            * the prior info array
12
           rc = PMIx_Get(NULL, PMIX_NODE_SIZE, info, 2, &value);
```

CHAPTER 7

Process-Related Non-Reserved Keys

Non-reserved keys are keys whose string representation begin with a prefix other than "pmix". Such keys are typically defined by an application when information needs to be exchanged between processes (e.g., where connection information is required and the host environment does not support the *instant on* option) or where the host environment does not provide a required piece of data. Beyond the restriction on name prefix, non-reserved keys are required to be unique across conflicting *scopes* as defined in Section 7.1.1.1 - e,g., a non-reserved key cannot be posted by the same process in both the PMIX_LOCAL and PMIX_REMOTE scopes (note that posting the key in the PMIX_GLOBAL scope would have met the desired objective).

PMIx provides support for two methods of exchanging non-reserved keys:

- Global, collective exchange of the information prior to retrieval. This is accomplished by
 executing a barrier operation that includes collection and exchange of the data provided by each
 process such that each process has access to the full set of data from all participants once the
 operation has completed. PMIx provides the PMIx_Fence function (or its non-blocking
 equivalent) for this purpose, accompanied by the PMIX_COLLECT_DATA qualifier.
- Direct, on-demand retrieval of the information. No barrier or global exchange is conducted in
 this case. Instead, information is retrieved from the host where that process is executing upon
 request i.e., a call to PMIx_Get results in a data exchange with the PMIx server on the remote
 host. Various caching strategies may be employed by the host environment and/or PMIx
 implementation to reduce the number of retrievals. Note that this method requires that the host
 environment both know the location of the posting process and support direct information
 retrieval.

Both of the above methods are based on retrieval from a specific process - i.e., the *proc* argument to <code>PMIx_Get</code> must include both the namespace and the rank of the process that posted the information. However, in some cases, non-reserved keys are provided on a globally unique basis and the retrieving process has no knowledge of the identity of the process posting the key. This is typically found in legacy applications (where the originating process identifier is often embedded in the key itself) and in unstructured applications that lack rank-related behavior. In these cases, the key remains associated with the namespace of the process that posted it, but is retrieved by use of the <code>PMIX_RANK_UNDEF</code> rank. In addition, the keys must be globally exchanged prior to retrieval as there is no way for the host to otherwise locate the source for the information.

Note that the retrieval rules for non-reserved keys (detailed in Section 7.2) differ significantly from those used for reserved keys.

7.1 Posting Key/Value Pairs

PMIx clients can post non-reserved key-value pairs associated with themselves by using

PMIx_Put. Alternatively, PMIx clients can cache arbitrary key-value pairs accessible only by the caller via the PMIx Store internal API.

7.1.1 PMIx Put

Summary

Post a key/value pair for distribution.

Format

PMIx v1.0

6 7

10

11 12

13

14

15

16 17

18

19

20

21

22

23 24

25

26

27

28

29

30

31 32

IN scope

Distribution scope of the provided value (handle)

lkov (pprint le

key (pmix_key_t)

IN value

Reference to a pmix value t structure (handle)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. If a reserved key is provided in the *key* argument then **PMIX_Put** will return **PMIX_ERR_BAD_PARAM**.

Description

Post a key-value pair for distribution. Depending upon the PMIx implementation, the posted value may be locally cached in the client's PMIx library until **PMIx_Commit** is called.

The provided *scope* determines the ability of other processes to access the posted data, as defined in Section 7.1.1.1 on page 114. Specific implementations may support different scope values, but all implementations must support at least **PMIX_GLOBAL**.

The **pmix_value_t** structure supports both string and binary values. PMIx implementations are required to support heterogeneous environments by properly converting binary values between host architectures, and will copy the provided *value* into internal memory prior to returning from **PMIx Put**.

Advice to users

Note that keys starting with a string of "pmix" must not be used in calls to PMIx_Put. Thus, applications should never use a defined "PMIX" attribute as the key in a call to PMIx_Put.

7.1.1.1 Scope of Put Data

5

6

7 8

9

10 11

12 13

14

15 16

20

21

22

24

25 26

27 28

29

30

31 32

33

34 35 PMIx v1.0

2 *PMIx v1.0* The **pmix_scope_t** structure is a **uint8_t** type that defines the availability of data passed to **PMIx_Put**. The following constants can be used to set a variable of the type **pmix_scope_t**.

4 All definitions were introduced in version 1 of the standard unless otherwise marked.

Specific implementations may support different scope values, but all implementations must support at least PMIX_GLOBAL. If a specified scope value is not supported, then the PMIX_Put call must return PMIX_ERR_NOT_SUPPORTED.

PMIX_SCOPE_UNDEF Undefined scope.

PMIX_LOCAL The data is intended only for other application processes on the same node. Data marked in this way will not be included in data packages sent to remote requesters - i.e., it is only available to processes on the local node.

PMIX_REMOTE The data is intended solely for applications processes on remote nodes. Data marked in this way will not be shared with other processes on the same node - i.e., it is only available to processes on remote nodes.

PMIX_GLOBAL The data is to be shared with all other requesting processes, regardless of location.

17 *PMIx v2.0* **PMIX_INTERNAL** The data is intended solely for this process and is not shared with other processes.

7.1.2 PMIx Store internal

Summary

Store some data locally for retrieval by other areas of the process.

Format

23 pmix status t

pmix_value_t *val);

U

IN proc

process reference (handle)

IN key

key to retrieve (string)

IN val

Value to store (handle)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. If a reserved key is provided in the *key* argument then **PMIx_Store_internal** will return

PMIX_ERR_BAD_PARAM.

Description

Store some data locally for retrieval by other areas of the process. This is data that has only internal scope - it will never be posted externally. Typically used to cache data obtained by means outside of PMIx so that it can be accessed by various areas of the process.

7.1.3 PMIx Commit

6 Summary

Post all previously **PMIx_Put** values for distribution.

∃ Format

PMIx v1.0

1

3

4

7

9

10

11

12

13 14

15

16

17

18

19

20

C

pmix_status_t PMIx_Commit(void);

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

PMIx implementations may choose to locally cache non-reserved keys prior to submitting them for distribution. Accordingly, PMIx provides a second API specifically to stage all previously posted data for distribution - e.g., by transmitting the entire collection of data posted by the process to a server in one operation. This is an asynchronous operation that will immediately return to the caller while the data is staged in the background.

Advice to users

Users are advised to always include the call to **PMIx_Commit** in case the local implementation requires it. Note that posted data will not be circulated during **PMIx_Commit**. Availability of the data by other processes upon completion of **PMIx_Commit** therefore still relies upon the exchange mechanisms described at the beginning of this chapter.

7.2 Retrieval rules for non-reserved keys

Since non-reserved keys cannot, by definition, have been provided by the host environment, their retrieval follows significantly different rules than those defined for reserved keys (as detailed in Section 6.2). **PMIx_Get** for a non-reserved key will obey the following precedence search:

- 1. If the **PMIX_GET_REFRESH_CACHE** attribute is given, then the request is first forwarded to the local PMIx server which will then update the client's cache. Note that this may not, depending upon implementation details, result in any action.
- 2. Check the local PMIx client cache for the requested key if not found and either the PMIX_OPTIONAL or PMIX_GET_REFRESH_CACHE attribute was given, the search will stop at this point and return the PMIX_ERR_NOT_FOUND status.
- 3. Request the information from the local PMIx server. The server will check its cache for the specified key within the appropriate scope as defined by the process that originally posted the key. If the value exists in a scope that contains the requesting process, then the value shall be returned. If the value exists, but in a scope that excludes the requesting process, then the server shall immediately return the PMIX ERR EXISTS OUTSIDE SCOPE.

If the value still isn't found and the **PMIX_IMMEDIATE** attribute was given, then the library shall return the **PMIX_ERR_NOT_FOUND** error constant to the requester. Otherwise, the PMIx server library will take one of the following actions:

- If the target process has a rank of PMIX_RANK_UNDEF, then this indicates that the key being requested is globally unique and *not* associated with a specific process. In this case, the server shall hold the request until either the data appears at the server or, if given, the PMIX_TIMEOUT is reached. In the latter case, the server will return the PMIX_ERR_TIMEOUT status. Note that the server may, depending on PMIx implementation, never respond if the caller failed to specify a PMIX_TIMEOUT and the requested key fails to arrive at the server.
- If the target process is *local* (i.e., attached to the same PMIx server), then the server will hold the request until either the target process provides the data or, if given, the PMIX_TIMEOUT is reached. In the latter case, the server will return the PMIX_ERR_TIMEOUT status. Note that data which is posted via PMIx_Put but not staged with PMIx_Commit may, depending upon implementation, never appear at the server.
- If the target process is *remote* (i.e., not attached to the same PMIx server), the server will either:
 - If the host has provided the pmix_server_dmodex_req_fn_t module function interface, then the server shall pass the request to its host for servicing. The host is responsible for determining the location of the target process and passing the request to the PMIx server at that location.

When the remote data request is received, the target PMIx server will check its cache for the specified key. If the key is not present, the request shall be held until either the target process provides the data or, if given, the **PMIX_TIMEOUT** is reached. In the latter case,

the server will return the **PMIX_ERR_TIMEOUT** status. The host shall convey the result 1 2 back to the originating PMIx server, which will reply to the requesting client with the result of the request when the host provides it. 3 4 Note that the target server may, depending on PMIx implementation, never respond if the 5 caller failed to specify a PMIX_TIMEOUT and the target process fails to post the requested 6 key. 7 - if the host does not support the **pmix_server_dmodex_req_fn_t** interface, then the server will immediately respond to the client with the PMIX_ERR_NOT_FOUND status 8 Advice to PMIx library implementers – 9 While there is no requirement that all PMIx implementations follow the client-server paradigm 10 used in the above description, implementers are required to provide behaviors consistent with the described search pattern. 11 Advice to users Users are advised to always specify the PMIX_TIMEOUT value when retrieving non-reserved keys 12 to avoid potential deadlocks should the specified key not become available. 13

CHAPTER 8

1

2

4 5

6

7

8

9 10

11 12

13

14

25

Publish/Lookup Operations

Chapter 6 and Chapter 7 discussed how reserved and non-reserved keys dealt with information that either was associated with a specific process (i.e., the retrieving process knew the identifier of the process that posted it) or required a synchronization operation prior to retrieval (e.g., the case of globally unique non-reserved keys). However, another requirement exists for an asynchronous exchange of data where neither the posting nor the retrieving process is known in advance. For example, two separate namespaces may need to rendezvous with each other without knowing in advance the identity of the other namespace or when that namespace might become active.

The APIs defined in this section focus on resolving that specific situation by allowing processes to publish data that can subsequently be retrieved solely by referral to its key. Mechanisms for constraining availability of the information are also provided as a means for better targeting of the eventual recipient(s).

Note that no presumption is made regarding how the published information is to be stored, nor as to the entity (host environment or PMIx implementation) that shall act as the datastore. The descriptions in the remainder of this chapter shall simply refer to that entity as the *datastore*.

5 8.1 PMIx_Publish

Summary 16 Publish data for later access via PMIx_Lookup. 17 **Format** 18 PMIx v1.0 19 pmix status t PMIx Publish(const pmix_info_t info[], size_t ninfo); 20 21 IN info 22 Array of info structures containing both data to be published and directives (array of handles) 23 IN Number of elements in the *info* array (integer) 24

Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.

Required Attributes There are no required attributes for this API. PMIx implementations that do not directly support the operation but are hosted by environments that do support it must pass any attributes that are provided by the client to the host environment for processing. In addition, the PMIx library is required to add the PMIX USERID and the PMIX GRPID attributes of the client process that published the information to the *info* array passed to the host environment. **A**..... Optional Attributes The following attributes are optional for host environments that support this operation: PMIX TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it. PMIX PERSISTENCE "pmix.persist" (pmix persistence t) Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion. PMIX ACCESS PERMISSIONS "pmix.aperms" (pmix data array t) Define access permissions for the published data. The value shall contain an array of pmix info t structs containing the specified permissions. **Description** Publish the data in the *info* array for subsequent lookup. By default, the data will be published into the PMIX RANGE SESSION range and with PMIX PERSIST APP persistence. Changes to those values, and any additional directives, can be included in the pmix_info_t array. Attempts to access the data by processes outside of the provided data range shall be rejected. The PMIX PERSISTENCE attribute instructs the datastore holding the published information as to how long that information is to be retained. The blocking form of this call will block until it has obtained confirmation from the datastore that the data is available for lookup. The *info* array can be released upon return from the blocking function call.

Publishing duplicate keys is permitted provided they are published to different ranges. Duplicate

keys being published on the same data range shall return the PMIX ERR DUPLICATE KEY error.

1

2

4

5

6 7

8

9 10

11 12

13 14

15

16 17

18

19

20 21

22

23

24 25

26

27 28

29 30

1 8.2 PMIx_Publish_nb

2		Summary	
3		Nonblocking PMIx_Publish routine.	
4	PMIx v1.0	Format	
5		pmix_status_t	
6 7		PMIx_Publish_nb(const pmix_info_t info[], size_t ninfo,	
8		IN info	
9		Array of info structures containing both data to be published and directives (array of handles)	
0		IN ninfo	
1		Number of elements in the <i>info</i> array (integer)	
2		IN cbfunc	
3		Callback function pmix_op_cbfunc_t (function reference) IN cbdata	
4 5		Data to be passed to the callback function (memory reference)	
6		Returns one of the following:	
7 8 9		• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.	
20 21		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.	
22		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.	
		▼	
24		There are no required attributes for this API. PMIx implementations that do not directly support the	
25		operation but are hosted by environments that do support it must pass any attributes that are	
26		provided by the client to the host environment for processing. In addition, the PMIx library is	
27		required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that	
28		published the information to the <i>info</i> array passed to the host environment.	

		▼ Optional Attributes
1		The following attributes are optional for host environments that support this operation:
2 3 4 5		PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
6 7 8		<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>
9 10 11		<pre>PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t) Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion.</pre>
12 13 14		<pre>PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) Define access permissions for the published data. The value shall contain an array of pmix_info_t structs containing the specified permissions.</pre>
15 16	8.3	Description Nonblocking PMIx_Publish routine. Dublish_specific constants
17	0.3	Publish-specific constants
18		The following constants are defined for use with the PMIx_Publish APIs:
19 20		PMIX_ERR_DUPLICATE_KEY The provided key has already been published on the same data range.
21	8.4	Publish-specific attributes
22		The following attributes are defined for use with the PMIx_Publish APIs:
23 24 25		PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
26 27 28		PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t) Declare how long the datastore shall retain the provided data. The datastore is to delete the data upon reaching the persistence criterion.
29		<pre>PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) Define access permissions for the published data. The value shall contain an array of</pre>

```
1 PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t)
2 Array of effective User IDs (UIDs) that are allowed to access the published data.
3 PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t)
4 Array of effective Group IDs (GIDs) that are allowed to access the published data.
```

8.5 Publish-Lookup Datatypes

The following data types are defined for use with the **PMIx Publish** APIs.

8.5.1 Range of Published Data

- The pmix_data_range_t structure is a uint8_t type that defines a range for both data

 published via the PMIx_Publish API and generated events. The following constants can be used to set a variable of the type pmix_data_range_t.
 - **PMIX_RANGE_UNDEF** Undefined range.
 - **PMIX_RANGE_RM** Data is intended for the host environment, or lookup is restricted to data published by the host environment.
 - **PMIX_RANGE_LOCAL** Data is only available to processes on the local node, or lookup is restricted to data published by processes on the local node of the requester.
 - **PMIX_RANGE_NAMESPACE** Data is only available to processes in the same namespace, or lookup is restricted to data published by processes in the same namespace as the requester.
 - **PMIX_RANGE_SESSION** Data is only available to all processes in the session, or lookup is restricted to data published by other processes in the same session as the requester.
 - **PMIX_RANGE_GLOBAL** Data is available to all processes, or lookup is open to data published by anyone.
 - **PMIX_RANGE_CUSTOM** Data is available only to processes as specified in the **pmix_info_t** associated with this call, or lookup is restricted to data published by processes as specified in the **pmix_info_t**.
 - **PMIX_RANGE_PROC_LOCAL** Data is only available to this process, or lookup is restricted to data published by this process.
 - **PMIX_RANGE_INVALID** Invalid value typically used to indicate that a range has not yet been set.

29 8.5.2 Data Persistence Structure

- The pmix_persistence_t structure is a uint8_t type that defines the policy for data published by clients via the PMIx_Publish API. The following constants can be used to set a variable of the type pmix_persistence_t.
- 33 **PMIX_PERSIST_INDEF** Retain data until specifically deleted.
- 34 **PMIX_PERSIST_FIRST_READ** Retain data until the first access, then the data is deleted.
- 35 **PMIX_PERSIST_PROC** Retain data until the publishing process terminates.
 - **PMIX PERSIST APP** Retain data until the application terminates.
 - **PMIX PERSIST SESSION** Retain data until the session/allocation terminates.
- 38 **PMIX_PERSIST_INVALID** Invalid value typically used to indicate that a persistence has 39 not yet been set.

11 12

13

14

15

16 17

18

19

20

21

22

23

24 25

26

27

28

1 8.6 PMIx_Lookup

2		Summary				
3 4		Lookup information published by this or another process with PMIx_Publish or PMIx_Publish_nb .				
5		For	rmat			
	<i>PMIx v1.0</i>					
6	6 pmix_status_t					
7		PMI	x_Lookup(pmix_pdata_t data[], size_t ndata,			
8			<pre>const pmix_info_t info[], size_t ninfo);</pre>			
			C			
9		INO	OUT data			
0			Array of publishable data structures (array of pmix_pdata_t)			
1		IN	ndata			
2			Number of elements in the <i>data</i> array (integer)			
3		IN	info			
4		IN	Array of info structures (array of pmix_info_t) ninfo			
5		IIN	Number of elements in the <i>info</i> array (integer)			
7		Retu	urns one of the following:			
8		• P	MIX_SUCCESS All data was found and has been returned.			
9			MIX_ERR_NOT_FOUND None of the requested data could be found within the requester's ange.			
21 22 23 24		bo th	MIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Any key that cannot be found will return with a data type of PMIX_UNDEF in the associated <i>value</i> struct. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.			
25 26			MIX_ERR_NOT_SUPPORTED There is no available datastore (either at the host environment r PMIx implementation level) on this system that supports this function.			
27 28 29		 PMIX_ERR_NO_PERMISSIONS All of the requested data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions. 				
0		• a	non-zero PMIx error constant indicating a reason for the request's failure.			

Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX USERID and the PMIX GRPID attributes of the client process that is requesting the info. Optional Attributes The following attributes are optional for host environments that support this operation: PMIX TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it. PMIX WAIT "pmix.wait" (int) Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates all and is the default). **Description** Lookup information published by this or another process. By default, the search will be constrained to publishers that fall within the PMIX RANGE SESSION range in case duplicate keys exist on different ranges. Changes to the range (e.g., expanding the search to all potential publishers via the PMIX RANGE GLOBAL constant), and any additional directives, can be provided in the pmix info t array. Data is returned per the retrieval rules of Section 8.8. The data parameter consists of an array of pmix_pdata_t structures with the keys specifying the requested information. Data will be returned for each **key** field in the associated **value** field of this structure as per the above description of return values. The proc field in each pmix pdata t structure will contain the namespace/rank of the process that published the data. Advice to users -Although this is a blocking function, it will not wait by default for the requested data to be published. Instead, it will block for the time required by the datastore to lookup its current data and return any found items. Thus, the caller is responsible for either ensuring that data is published prior to executing a lookup, using PMIX WAIT to instruct the datastore to wait for the data to be

1

2

3

5

6

7

8

9

10

11

12 13

14

15

16 17

18

19

20

21 22

23

24

25

26

27 28

29

30

published, or retrying until the requested data is found.

1 8.7 PMIx_Lookup_nb

2	Summary Nonblocking version of PMIx_Lookup.	
4	Format	
	PMIx v1.0	
5	pmix_status_t	
6	PMIx_Lookup_nb(char **keys,	
7	<pre>const pmix_info_t info[], size_t ninfo,</pre>	
8	<pre>pmix_lookup_cbfunc_t cbfunc, void *cbdata);</pre>	
	C	
9	IN keys	
0	NULL-terminated array of keys (array of strings)	
11	IN info	
12	Array of info structures (array of handles)	
13	IN ninfo	
14	Number of elements in the <i>info</i> array (integer)	
15	IN cbfunc	
16 17	Callback function (handle) IN cbdata	
18	Callback data to be provided to the callback function (pointer)	
19	Returns one of the following:	
20	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - res	ult
21	will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback	
22	function prior to returning from the API.	
23	• a PMIx error constant indicating an error in the input - the <i>cbfunc</i> will <i>not</i> be called.	
24	If executed, the status returned in the provided callback function will be one of the following	
25	constants:	
26	• PMIX_SUCCESS All data was found and has been returned.	
27	• PMIX_ERR_NOT_FOUND None of the requested data was available within the requester's ran	ıge.
28	The <i>pdata</i> array in the callback function shall be NULL and the <i>npdata</i> parameter set to zero.	
29	• PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Only found data w	vill
30	be included in the returned <i>pdata</i> array. Note that the specific reason for a particular piece of	
31	missing information (e.g., lack of permissions) cannot be communicated back to the requester	in
32	this situation.	
33	• PMIX_ERR_NOT_SUPPORTED There is no available datastore (either at the host environment	nt
34	or PMIx implementation level) on this system that supports this function.	

1 2 3	 PMIX_ERR_NO_PERMISSIONS All of the requested data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions.
4	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
5 6 7 8	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the info.
	▼ Optional Attributes
9	The following attributes are optional for host environments that support this operation:
10 11 12 13	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
14 15 16	<pre>PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.</pre>
17 18 19	PMIX_WAIT "pmix.wait" (int) Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates <i>all</i> and is the default).
20	Description
21	Non-blocking form of the PMIx_Lookup function.

8.7.1 Lookup Returned Data Structure

2 The pmix_pdata_t structure is used by PMIx_Lookup to describe the data being accessed. PMIx v1.0 3 typedef struct pmix_pdata { 4 pmix_proc_t proc; 5 pmix_key_t key; pmix_value_t value; 6 7 } pmix_pdata_t; where: 8 • proc is the process identifier of the data publisher. 9 • key is the string key of the published data. 10 11 • *value* is the value associated with the *key*. Lookup data structure support macros 8.7.1.1 The following macros are provided to support the pmix_pdata_t structure. 13 Initialize the pdata structure 14 15 Initialize the pmix pdata t fields *PMIx v1.0* 16 PMIX PDATA CONSTRUCT (m) 17 IN m Pointer to the structure to be initialized (pointer to pmix_pdata_t) 18 Destruct the pdata structure 19 20 Destruct the pmix_pdata_t fields PMIx v1.0 21 PMIX_PDATA_DESTRUCT (m) IN 22 23 Pointer to the structure to be destructed (pointer to pmix_pdata_t)

1		Create a pdata array
2		Allocate and initialize an array of pmix_pdata_t structures
	PMIx v1.0	C
3		PMIX_PDATA_CREATE(m, n)
		C
4		INOUT m
5		Address where the pointer to the array of pmix_pdata_t structures shall be stored (handle)
6		IN n
7		Number of structures to be allocated (size_t)
8		Free a pdata structure
9		Release a pmix_pdata_t structure
Ū		C C
	<i>PMIx v4.0</i>	
10		PMIX_PDATA_RELEASE (m)
		C -
11		IN m
12		Pointer to a pmix_pdata_t structure (handle)
13		Free a pdata array
14		Release an array of pmix_pdata_t structures
14		Release all array of philix_pdata_c structures
	<i>PMIx v1.0</i>	
15		PMIX_PDATA_FREE(m, n)
. •		
16		IN m
17		Pointer to the array of <pre>pmix_pdata_t</pre> structures (handle)
18		IN n
19		Number of structures in the array (size_t)
00		Lood a lookup data atrustura
20		Load a lookup data structure
21		This macro simplifies the loading of key, process identifier, and data into a pmix_pdata_t by
22		correctly assigning values to the structure's fields.
	PMIx v1.0	

	V V
1	PMIX_PDATA_LOAD(m, p, k, d, t);
	C
2	IN m
3	Pointer to the pmix_pdata_t structure into which the key and data are to be loaded
4	(pointer to pmix_pdata_t)
5	IN p
6	Pointer to the pmix_proc_t structure containing the identifier of the process being
7	referenced (pointer to pmix_proc_t)
8	IN k
9	String key to be loaded - must be less than or equal to PMIX_MAX_KEYLEN in length
10	(handle)
11	IN d
12	Pointer to the data value to be loaded (handle)
13	IN t
14	Type of the provided data value (pmix_data_type_t)
	Advice to users
. =	
15	Key, process identifier, and data will all be copied into the pmix_pdata_t - thus, the source
16	information can be modified or free'd without affecting the copied data once the macro has
17	completed.
18	Transfer a lookup data structure
19	This macro simplifies the transfer of key, process identifier, and data value between
20	twopmix_pdata_t structures.
PMIx v2.0	C
21	PMIX_PDATA_XFER(d, s);
22	IN d
23	Pointer to the destination <pre>pmix_pdata_t</pre> (pointer to <pre>pmix_pdata_t</pre>)
24	IN s
25	Pointer to the source pmix_pdata_t (pointer to pmix_pdata_t)
	Advice to users —
26	Key, process identifier, and data will all be copied into the destination pmix_pdata_t - thus, the
26 27	source pmix_pdata_t may free'd without affecting the copied data once the macro has
28	completed.
_0	completed.

8.7.2 Lookup Callback Function

Summary 2 3 The pmix_lookup_cbfunc_t is used by PMIx_Lookup_nb to return data. PMIx v1.0 4 typedef void (*pmix lookup cbfunc t) 5 (pmix status t status, 6 pmix pdata t data[], size t ndata, 7 void *cbdata); IN 8 status Status associated with the operation (handle) 9 IN 10 11 Array of data returned (pmix pdata t) 12 IN ndata Number of elements in the *data* array (size t) 13 14 IN cbdata 15 Callback data passed to original API call (memory reference) **Description** 16 17 A callback function for calls to PMIx Lookup nb. The function will be called upon completion of the **PMIx** Lookup nb API with the *status* indicating the success or failure of the request. Any 18 retrieved data will be returned in an array of pmix pdata t structs. The namespace and rank of 19 the process that provided each data element is also returned. 20

Note that the **pmix_pdata_t** structures will be released upon return from the callback function, so the receiver must copy/protect the data prior to returning if it needs to be retained.

8.8 Retrieval rules for published data

The retrieval rules for published data primarily revolve around enforcing data access permissions and range constraints. The datastore shall search its stored information for each specified key according to the following precedence logic:

- 1. If the requester specified the range, then the search shall be constrained to data where the publishing process falls within the specified range.
- 2. If the key of the stored information does not match the specified key, then the search will continue.
- 3. If the requester's identifier does not fall within the range specified by the publisher, then the search will continue.

21

22

24

25

26 27

28

29

30 31

32

- 4. If the publisher specified access permissions, the effective UID and GID of the requester shall be checked against those permissions, with the datastore rejecting the match if the requester fails to meet the requirements.
- 5. If all of the above checks pass, then the value is added to the information that is to be returned.

The status returned by the datastore shall be set to:

- PMIX SUCCESS All data was found and is included in the returned information.
- PMIX ERR NOT FOUND None of the requested data could be found within a requester's range.
- PMIX_ERR_PARTIAL_SUCCESS Some of the requested data was found. Only found data will be included in the returned information. Note that the specific reason for a particular piece of missing information (e.g., lack of permissions) cannot be communicated back to the requester in this situation.
- a non-zero PMIx error constant indicating a reason for the request's failure.

In the case where data was found and range restrictions were met for each specified key, but none of the matching data could be returned due to lack of access permissions, the datastore must return the **PMIX_ERR_NO_PERMISSIONS** error.

Advice to users

Note that duplicate keys are allowed to exist on different ranges, and that ranges do overlap each other. Thus, if duplicate keys are published on overlapping ranges, it is possible for the datastore to successfully find multiple responses for a given key should publisher and requester specify sufficiently broad ranges. In this situation, the choice of resolving the duplication is left to the datastore implementation - e.g., it may return the first value found in its search, or the value corresponding to the most limited range of the found values, or it may choose to simply return an error.

Users are advised to avoid this ambiguity by careful selection of key values and ranges - e.g., by creating range-specific keys where necessary.

8.9 PMIx_Unpublish

Summary

Unpublish data posted by this process using the given keys.

1	Format
<i>PMIx v1.0</i>	pmix_status_t
3	<pre>PMIx_Unpublish(char **keys,</pre>
5 6 7 8 9 0	 IN keys NULL-terminated array of keys (array of strings) IN info Array of info structures (array of handles) IN ninfo Number of elements in the <i>info</i> array (integer)
1	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
	Required Attributes
2 3 4 5	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the operation.
	▼ Optional Attributes
6	The following attributes are optional for host environments that support this operation:
7 8 9	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
21 22 23	PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
24 25 26 27	Description Unpublish data posted by this process using the given <i>keys</i> . The function will block until the data has been removed by the server (i.e., it is safe to publish that key again within the specified range). A value of NULL for the <i>keys</i> parameter instructs the server to remove all data published by this process.
29	By default, the range is assumed to be PMIX_RANGE_SESSION . Changes to the range, and any additional directives, can be provided in the <i>info</i> array.

1 8.10 PMIx_Unpublish_nb

2		Summary Nonblocking version of PMIx_Unpublish.
		Format C
5 6 7 8		<pre>pmix_status_t PMIx_Unpublish_nb(char **keys,</pre>
9 0 1 2 3 4 5 6 7 8		 IN keys NULL-terminated array of keys (array of strings) IN info Array of info structures (array of handles) IN ninfo Number of elements in the info array (integer) IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
9 20 21 22 20 20		Returns one of the following: • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
23 24 25 26		 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called. a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called. Required Attributes
27 28 29 30	4	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host environment for processing, and the PMIx library is required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process that is requesting the operation.

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

PMIX_RANGE "pmix.range" (pmix_data_range_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

Description

1 2

3

5 6

7

8

9

10

11

12

Non-blocking form of the **PMIx_Unpublish** function. The callback function will be executed once the server confirms removal of the specified data. The *info* array must be maintained until the callback is provided.

CHAPTER 9

Event Notification

This chapter defines the PMIx event notification system. These interfaces are designed to support the reporting of events to/from clients and servers, and between library layers within a single process.

9.1 Notification and Management

PMIx event notification provides an asynchronous out-of-band mechanism for communicating events between application processes and/or elements of the SMS. Its uses span a wide range including fault notification, coordination between multiple programming libraries within a single process, and workflow orchestration for non-synchronous programming models. Events can be divided into two distinct classes:

- *Job-specific events* directly relate to a job executing within the session, such as a debugger attachment, process failure within a related job, or events generated by an application process. Events in this category are to be immediately delivered to the PMIx server library for relay to the related local processes.
- Environment events indirectly relate to a job but do not specifically target the job itself. This category includes SMS-generated events such as Error Check and Correction (ECC) errors, temperature excursions, and other non-job conditions that might directly affect a session's resources, but would never include an event generated by an application process. Note that although these do potentially impact the session's jobs, they are not directly tied to those jobs. Thus, events in this category are to be delivered to the PMIx server library only upon request.

Both SMS elements and applications can register for events of either type.

Advice to PMIx library implementers -

Race conditions can cause the registration to come after events of possible interest (e.g., a memory ECC event that occurs after start of execution but prior to registration, or an application process generating an event prior to another process registering to receive it). SMS vendors are *requested* to cache environment events for some time to mitigate this situation, but are not *required* to do so. However, PMIx implementers are *required* to cache all events received by the PMIx server library and to deliver them to registering clients in the same order in which they were received

9

10

3

4

14

29

Applications must be aware that they may not receive environment events that occur prior to registration, depending upon the capabilities of the host SMS.

The generator of an event can specify the target range for delivery of that event. Thus, the generator can choose to limit notification to processes on the local node, processes within the same job as the generator, processes within the same allocation, other threads within the same process, only the SMS (i.e., not to any application processes), all application processes, or to a custom range based on specific process identifiers. Only processes within the given range that register for the provided event code will be notified. In addition, the generator can use attributes to direct that the event not be delivered to any default event handlers, or to any multi-code handler (as defined below).

Event notifications provide the process identifier of the source of the event plus the event code and any additional information provided by the generator. When an event notification is received by a process, the registered handlers are scanned for their event code(s), with matching handlers assembled into an event chain for servicing. Note that users can also specify a source range when registering an event (using the same range designators described above) to further limit when they are to be invoked. When assembled, PMIx event chains are ordered based on both the specificity of the event handler and user directives at time of handler registration. By default, handlers are grouped into three categories based on the number of event codes that can trigger the callback:

- single-code handlers are serviced first as they are the most specific. These are handlers that are registered against one specific event code.
- multi-code handlers are serviced once all single-code handlers have completed. The handler will be included in the chain upon receipt of an event matching any of the provided codes.
- default handlers are serviced once all multi-code handlers have completed. These handlers are always included in the chain unless the generator specifically excludes them.

Users can specify the callback order of a handler within its category at the time of registration. Ordering can be specified either by providing the relevant returned event handler registration ID or using event handler names, if the user specified an event handler name when registering the corresponding event. Thus, users can specify that a given handler be executed before or after another handler should both handlers appear in an event chain (the ordering is ignored if the other handler isn't included). Note that ordering does not imply immediate relationships. For example, multiple handlers registered to be serviced after event handler A will all be executed after A, but are not guaranteed to be executed in any particular order amongst themselves.

In addition, one event handler can be declared as the *first* handler to be executed in the chain. This handler will always be called prior to any other handler, regardless of category, provided the incoming event matches both the specified range and event code. Only one handler can be so designated — attempts to designate additional handlers as first will return an error. Deregistration of the declared *first* handler will re-open the position for subsequent assignment.

Similarly, one event handler can be declared as the *last* handler to be executed in the chain. This handler will *always* be called after all other handlers have executed, regardless of category, provided the incoming event matches both the specified range and event code. Note that this handler will not be called if the chain is terminated by an earlier handler. Only one handler can be designated as *last* — attempts to designate additional handlers as *last* will return an error. Deregistration of the declared *last* handler will re-open the position for subsequent assignment.

Advice to users

Note that the *last* handler is called *after* all registered default handlers that match the specified range of the incoming event unless a handler prior to it terminates the chain. Thus, if the application intends to define a *last* handler, it should ensure that no default handler aborts the process before it.

Upon completing its work and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. PMIx automatically aggregates the status and any results of each handler (as provided in the completion callback) with status from all prior handlers so that each step in the chain has full knowledge of what preceded it. An event handler can terminate all further progress along the chain by passing the PMIX_EVENT_ACTION_COMPLETE status to the completion callback function.

17 9.1.1 Events versus status constants

Return status constants (see Section 3.1.1) represent values that can be returned from or passed into PMIx APIs. These are distinct from PMIx *events* in that they are not values that can be registered against event handlers. In general, the two types of constants are distinguished by inclusion of an "ERR" in the name of error constants versus an "EVENT" in events, though there are exceptions (e.g, the **PMIX_SUCCESS** constant).

3 9.1.2 PMIx_Register_event_handler

24 Summary

Register an event handler.

1 <i>PMIx v2.0</i>	Format C
2	pmix_status_t
3	<pre>PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,</pre>
4	pmix_info_t info[], size_t ninfo,
5	pmix_notification_fn_t evhdlr,
6	pmix_hdlr_reg_cbfunc_t cbfunc,
7	<pre>void *cbdata);</pre>
	C
8	IN codes
9	Array of status codes (array of pmix_status_t)
10	IN ncodes
11	Number of elements in the <i>codes</i> array (size_t)
12	IN info
13	Array of info structures (array of handles)
14	IN ninfo
15	Number of elements in the <i>info</i> array (size_t)
16	IN evhdlr
17	Event handler to be called pmix_notification_fn_t (function reference)
18	IN cbfunc
19	Callback function pmix_hdlr_reg_cbfunc_t (function reference)
20	IN cbdata
21	Data to be passed to the cbfunc callback function (memory reference)
22	If <i>cbfunc</i> is NULL , the function call will be treated as a <i>blocking</i> call. In this case, the returned
23	status will be either (a) the event handler reference identifier if the value is greater than or equal to
24	zero, or (b) a negative error code indicative of the reason for the failure.
25	If the <i>cbfunc</i> is non- NULL , the function call will be treated as a <i>non-blocking</i> call and will return
26	the following:
27	• PMIX_SUCCESS indicating that the request has been accepted for processing and the provided
28	callback function will be executed upon completion of the operation. Note that the library must
29	not invoke the callback function prior to returning from the API. The result of the registration

• PMIX_ERR_EVENT_REGISTRATION indicating that the registration has failed for an undetermined reason.

operation shall be returned in the provided callback function along with the assigned event

• a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed.

handler identifier.

30

31

32

33 34

35

1 2 3	The callback function must not be executed prior to returning from the API, and no events corresponding to this registration may be delivered prior to the completion of the registration callback function (<i>cbfunc</i>).
	Required Attributes
4	The following attributes are required to be supported by all PMIx libraries:
5 6	PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler.
7 8	PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers.
9 10	PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called.
11 12	<pre>PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category.</pre>
13 14	PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called.
15 16	PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value.
17 18	<pre>PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*) Put this event handler immediately after the one specified in the (char*) value.</pre>
19 20	PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool) Prepend this handler to the precedence list within its category.
21 22	PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool) Append this handler to the precedence list within its category.
23 24	<pre>PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*) Array of pmix_proc_t defining range of event notification.</pre>
25 26 27	PMIX_RANGE "pmix.range" (pmix_data_range_t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
28 29	PMIX_EVENT_RETURN_OBJECT "pmix.evobject" (void *) Object to be returned whenever the registered callback function cbfunc is invoked. The

 Host environments that implement support for PMIx event notification are required to support the following attributes when registering handlers - these attributes are used to direct that the handler should be invoked only when the event affects the indicated process(es):

PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t)
 The single process that was affected.

PMIX_EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*)
Array of pmix_proc_t defining affected processes.

Description

Register an event handler to report events. Note that the codes being registered do *not* need to be PMIx error constants — any integer value can be registered. This allows for registration of non-PMIx events such as those defined by a particular SMS vendor or by an application itself.

Advice to users

In order to avoid potential conflicts, users are advised to only define codes that lie outside the range of the PMIx standard's error codes. Thus, SMS vendors and application developers should constrain their definitions to positive values or negative values beyond the PMIX EXTERNAL ERR BASE boundary.

Advice to users ·

As previously stated, upon completing its work, and prior to returning, each handler *must* call the event handler completion function provided when it was invoked (including a status code plus any information to be passed to later handlers) so that the chain can continue being progressed. An event handler can terminate all further progress along the chain by passing the **PMIX_EVENT_ACTION_COMPLETE** status to the completion callback function. Note that the parameters passed to the event handler (e.g., the *info* and *results* arrays) will cease to be valid once the completion function has been called - thus, any information in the incoming parameters that will be referenced following the call to the completion function must be copied.

9.1.3 Event registration constants

PMIX ERR EVENT REGISTRATION Error in event registration.

1 9.1.4 System events

		•
2		PMIX_EVENT_SYS_BASE Mark the beginning of a dedicated range of constants for system
3		event reporting.
4		PMIX_EVENT_NODE_DOWN A node has gone down - the identifier of the affected node will
5		be included in the notification.
6		PMIX_EVENT_NODE_OFFLINE A node has been marked as offline - the identifier of the
7		affected node will be included in the notification.
8		PMIX_EVENT_SYS_OTHER Mark the end of a dedicated range of constants for system event
9		reporting.
10		Detect system event constant
		Test a given event constant to see if it falls within the dedicated range of constants for system event
11		
12		reporting.
	PMIx v2.2	
13		PMIX_SYSTEM_EVENT(a)
		C
14		IN a
15		Error constant to be checked (pmix_status_t)
16		Returns true if the provided values falls within the dedicated range of events for system event
17		reporting.
10	015	
18	9.1.5 I	Event handler registration and notification attributes
18 19	9.1.5 I	
19	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification.
19 20	9.1.5	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*)
19 20 21	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler.
19 20 21 22	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool)
19 20 21 22 23	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers.
19 20 21 22 23 24	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool)
19 20 21 22 23 24 25	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called.
19 20 21 22 23 24 25 26	9.1.5 I	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool)
19 20 21 22 23 24 25 26 27	9.1.5 I	Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category.
19 20 21 22 23 24 25 26 27 28	9.1.5	Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool)
19 20 21 22 23 24 25 26 27 28 29	9.1.5	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called.
19 20 21 22 23 24 25 26 27 28 29 30	9.1.5	Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*)
19 20 21 22 23 24 25 26 27 28 29 30 31	9.1.5	Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value.
19 20 21 22 23 24 25 26 27 28 29 30 31 32	9.1.5	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value. PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*)
19 20 21 22 23 24 25 26 27 28 29 30 31 32 33	9.1.5	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value. PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*) Put this event handler immediately after the one specified in the (char*) value.
19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34	9.1.5	Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value. PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*) Put this event handler immediately after the one specified in the (char*) value. PMIX_EVENT_HDLR_PREPEND "pmix.evprepend" (bool)
19 20 21 22 23 24 25 26 27 28 29 30 31 32 33	9.1.5	Event handler registration and notification attributes Attributes to support event registration and notification. PMIX_EVENT_HDLR_NAME "pmix.evname" (char*) String name identifying this handler. PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool) Invoke this event handler before any other handlers. PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool) Invoke this event handler after all other handlers have been called. PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool) Invoke this event handler before any other handlers in this category. PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool) Invoke this event handler after all other handlers in this category have been called. PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*) Put this event handler immediately before the one specified in the (char*) value. PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*) Put this event handler immediately after the one specified in the (char*) value.

```
1
                    Append this handler to the precedence list within its category.
2
              PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*)
 3
                    Array of pmix_proc_t defining range of event notification.
              PMIX EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t)
 4
5
                    The single process that was affected.
6
              PMIX EVENT AFFECTED PROCS "pmix.evaffected" (pmix data array t*)
7
                    Array of pmix proc t defining affected processes.
              PMIX EVENT NON DEFAULT "pmix.evnondef" (bool)
8
                    Event is not to be delivered to default event handlers.
9
              PMIX EVENT RETURN OBJECT "pmix.evobject" (void *)
10
                    Object to be returned whenever the registered callback function cbfunc is invoked. The
11
                    object will only be returned to the process that registered it.
12
              PMIX EVENT DO NOT CACHE "pmix.evnocache" (bool)
13
14
                    Instruct the PMIx server not to cache the event.
              PMIX EVENT PROXY "pmix.evproxy" (pmix proc t*)
15
                    PMIx server that sourced the event.
16
17
              PMIX EVENT TEXT MESSAGE "pmix.evtext" (char*)
                    Text message suitable for output by recipient - e.g., describing the cause of the event.
18
              PMIX_EVENT_TIMESTAMP "pmix.evtstamp" (time_t)
19
                    System time when the associated event occurred.
20
    9.1.5.1
              Fault tolerance event attributes
21
22
              The following attributes may be used by the host environment when providing an event notification
              as qualifiers indicating the action it intends to take in response to the event:
23
24
              PMIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool)
25
                    The RM intends to terminate this session.
26
              PMIX EVENT TERMINATE JOB "pmix.evterm.job" (bool)
27
                    The RM intends to terminate this job.
              PMIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool)
28
                    The RM intends to terminate all processes on this node.
29
              PMIX EVENT TERMINATE PROC "pmix.evterm.proc" (bool)
30
                    The RM intends to terminate just this process.
31
              PMIX_EVENT_ACTION_TIMEOUT "pmix.evtimeout" (int)
32
                    The time in seconds before the RM will execute the indicated operation.
33
              Hybrid programming event attributes
    9.1.5.2
34
35
              The following attributes may be used by programming models to coordinate their use of common
              resources within a process in conjunction with the PMIX OPENMP PARALLEL ENTERED event:
36
              PMIX MODEL PHASE NAME "pmix.mdl.phase" (char*)
37
                    User-assigned name for a phase in the application execution (e.g., "cfd reduction").
38
39
              PMIX MODEL PHASE TYPE "pmix.mdl.ptype" (char*)
40
                    Type of phase being executed (e.g., "matrix multiply").
```

9.1.6 Notification Function

Summary 2 The **pmix_notification_fn_t** is called by PMIx to deliver notification of an event. 3 Advice to users The PMIx ad hoc v1.0 Standard defined an error notification function with an identical name, but 4 different signature than the v2.0 Standard described below. The ad hoc v1.0 version was removed 5 6 from the v2.0 Standard is not included in this document to avoid confusion. PMIx v2.0 7 typedef void (*pmix_notification_fn_t) (size_t evhdlr_registration_id, 8 pmix_status_t status, 9 10 const pmix_proc_t *source, pmix_info_t info[], size_t ninfo, 11 pmix_info_t results[], size_t nresults, 12 pmix_event_notification_cbfunc_fn_t cbfunc, 13 14 void *cbdata); 15 IN evhdlr_registration_id Registration number of the handler being called (size_t) 16 IN 17 status Status associated with the operation (pmix_status_t) 18 19 IN source 20 Identifier of the process that generated the event (pmix_proc_t). If the source is the SMS, then the nspace will be empty and the rank will be PMIX_RANK_UNDEF 21 IN 22 info Information describing the event (pmix_info_t). This argument will be NULL if no 23 24 additional information was provided by the event generator. IN ninfo 25 Number of elements in the info array (size_t) 26 IN 27 28 Aggregated results from prior event handlers servicing this event (pmix_info_t). This 29 argument will be **NULL** if this is the first handler servicing the event, or if no prior handlers provided results. 30 IN nresults 31 32 Number of elements in the results array (size_t) 33 IN cbfunc pmix_event_notification_cbfunc_fn_t callback function to be executed upon 34 completion of the handler's operation and prior to handler return (function reference). 35

IN cbdata

1

3

4

5

7

8

9

10

11 12

13

14

15

16

17 18

19

20

21

22

23

25

26

Callback data to be passed to cbfunc (memory reference)

Description

Note that different RMs may provide differing levels of support for event notification to application processes. Thus, the *info* array may be **NULL** or may contain detailed information of the event. It is the responsibility of the application to parse any provided info array for defined key-values if it so desires.

Advice to users

Possible uses of the info array include:

- for the host RM to alert the process as to planned actions, such as aborting the session, in response to the reported event
- provide a timeout for alternative action to occur, such as for the application to request an alternate response to the event

For example, the RM might alert the application to the failure of a node that resulted in termination of several processes, and indicate that the overall session will be aborted unless the application requests an alternative behavior in the next 5 seconds. The application then has time to respond with a checkpoint request, or a request to recover from the failure by obtaining replacement nodes and restarting from some earlier checkpoint.

Support for these options is left to the discretion of the host RM. Info keys are included in the common definitions above but may be augmented by environment vendors.

Advice to PMIx server hosts -

On the server side, the notification function is used to inform the PMIx server library's host of a detected event in the PMIx server library. Events generated by PMIx clients are communicated to the PMIx server library, but will be relayed to the host via the pmix_server_notify_event_fn_t function pointer, if provided.

9.1.7 PMIx_Deregister_event_handler

Summary

Deregister an event handler.

ı	DMI2 ()	C
2	PMIx v2.0	pmix_status_t
3		PMIx_Deregister_event_handler(size_t evhdlr_ref,
4		pmix_op_cbfunc_t cbfunc,
5		<pre>void *cbdata);</pre>
6		IN evhdlr_ref
7 8		Event handler ID returned by registration (size_t) IN cbfunc
9		Callback function to be executed upon completion of operation pmix_op_cbfunc_t
10		(function reference)
11		IN cbdata
12		Data to be passed to the cbfunc callback function (memory reference)
13		If <i>cbfunc</i> is NULL , the function will be treated as a <i>blocking</i> call and the result of the operation
14		returned in the status code.
15		If <i>cbfunc</i> is non-NULL, the function will be treated as a <i>non-blocking</i> call and return one of the
16		following:
17		• PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the
18 19		provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
20 21		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
22		• a PMIx error constant indicating either an error in the input or that the request was immediately
23		processed and failed - the <i>cbfunc</i> will <i>not</i> be called
24		The returned status code will be one of the following:
25		• PMIX_SUCCESS The event handler was successfully deregistered.
26		• PMIX_ERR_BAD_PARAM The provided evhdlr_ref was unrecognized.
27		• PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support event notification.
28		Description
29		Deregister an event handler. Note that no events corresponding to the referenced registration may
30		be delivered following completion of the deregistration operation (either return from the API with
31		PMIX_OPERATION_SUCCEEDED or execution of the <i>cbfunc</i>).
32	9.1.8	PMIx_Notify_event

Report an event for notification via any registered event handler.

Summary

33

34

1		Foi	rmat
	PMIx v2.0		
2		pmi	x_status_t
3		PMI	<pre>Ix_Notify_event(pmix_status_t status,</pre>
4			<pre>const pmix_proc_t *source,</pre>
5			<pre>pmix_data_range_t range,</pre>
6			<pre>pmix_info_t info[], size_t ninfo,</pre>
7			<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
			C
8		IN	status
9			Status code of the event (pmix_status_t)
10		IN	source
11			Pointer to a pmix_proc_t identifying the original reporter of the event (handle)
12		IN	range
13			Range across which this notification shall be delivered (pmix_data_range_t)
14		IN	info
15			Array of pmix_info_t structures containing any further info provided by the originator of
16			the event (array of handles)
17		IN	ninfo
18			Number of elements in the <i>info</i> array (size_t)
19		IN	cbfunc
20			Callback function to be executed upon completion of operation pmix_op_cbfunc_t
21			(function reference)
22		IN	cbdata
23			Data to be passed to the cbfunc callback function (memory reference)
24		If ci	bfunc is NULL , the function will be treated as a blocking call and the result of the operation
25			rned in the status code.
26		If a	bfunc is non- NULL , the function will be treated as a non-blocking call and return one of the
27			owing:
21			
28			MIX_SUCCESS The notification request is valid and is being processed. The callback function
29			vill be called when the process-local operation is complete and will provide the resulting status
30			f that operation. Note that this does <i>not</i> reflect the success or failure of delivering the event to
31		aı	ny recipients. The callback function must not be executed prior to returning from the API.
32		• P	MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
33			eturned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called

• PMIX_ERR_BAD_PARAM The request contains at least one incorrect entry that prevents it from being processed. The callback function will *not* be called.

34 35

1 2 3 4	 PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support event notification, or in the case of a PMIx server calling the API, the range extended beyond the local node and the host SMS environment does not support event notification. The callback function will <i>not</i> be called.
•	Required Attributes
5	The following attributes are required to be supported by all PMIx libraries:
6 7	PMIX_EVENT_NON_DEFAULT "pmix.evnondef" (bool) Event is not to be delivered to default event handlers.
8 9	<pre>PMIX_EVENT_CUSTOM_RANGE "pmix.evrange" (pmix_data_array_t*) Array of pmix_proc_t defining range of event notification.</pre>
10 11	PMIX_EVENT_DO_NOT_CACHE "pmix.evnocache" (bool) Instruct the PMIx server not to cache the event.
12 13	<pre>PMIX_EVENT_PROXY "pmix.evproxy" (pmix_proc_t*) PMIx server that sourced the event.</pre>
14 15	<pre>PMIX_EVENT_TEXT_MESSAGE "pmix.evtext" (char*) Text message suitable for output by recipient - e.g., describing the cause of the event.</pre>
16	
17 18	Host environments that implement support for PMIx event notification are required to provide the following attributes for all events generated by the environment:
19 20	<pre>PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t) The single process that was affected.</pre>
21 22	<pre>PMIX_EVENT_AFFECTED_PROCS "pmix.evaffected" (pmix_data_array_t*)</pre>
	▼ Optional Attributes
23 24 25	Host environments that support PMIx event notification may offer notifications for environmental events impacting the job and for SMS events relating to the job. The following attributes may optionally be included to indicate the host environment's intended response to the event:
26 27	<pre>PMIX_EVENT_TERMINATE_SESSION "pmix.evterm.sess" (bool) The RM intends to terminate this session.</pre>
28 29	<pre>PMIX_EVENT_TERMINATE_JOB "pmix.evterm.job" (bool) The RM intends to terminate this job.</pre>
30 31	<pre>PMIX_EVENT_TERMINATE_NODE "pmix.evterm.node" (bool) The RM intends to terminate all processes on this node.</pre>
32	<pre>PMIX_EVENT_TERMINATE_PROC "pmix.evterm.proc" (bool)</pre>

The RM intends to terminate just this process.

PMIX EVENT ACTION TIMEOUT "pmix.evtimeout" (int)

The time in seconds before the RM will execute the indicated operation.

Description

Report an event for notification via any registered event handler. This function can be called by any PMIx process, including application processes, PMIx servers, and SMS elements. The PMIx server calls this API to report events it detected itself so that the host SMS daemon distribute and handle them, and to pass events given to it by its host down to any attached client processes for processing. Examples might include notification of the failure of another process, detection of an impending node failure due to rising temperatures, or an intent to preempt the application. Events may be locally generated or come from anywhere in the system.

Host SMS daemons call the API to pass events down to its embedded PMIx server both for transmittal to local client processes and for the host's own internal processing where the host has registered its own event handlers. The PMIx server library is not allowed to echo any event given to it by its host via this API back to the host through the <code>pmix_server_notify_event_fn_t</code> server module function. The host is required to deliver the event to all PMIx servers where the targeted processes either are currently running, or (if they haven't started yet) might be running at some point in the future as the events are required to be cached by the PMIx server library.

Client application processes can call this function to notify the SMS and/or other application processes of an event it encountered. Note that processes are not constrained to report status values defined in the official PMIx standard — any integer value can be used. Thus, applications are free to define their own internal events and use the notification system for their own internal purposes.

Advice to users —

The callback function will be called upon completion of the **notify_event** function's actions. At that time, any messages required for executing the operation (e.g., to send the notification to the local PMIx server) will have been queued, but may not yet have been transmitted. The caller is required to maintain the input data until the callback function has been executed — the sole purpose of the callback function is to indicate when the input data is no longer required.

9.1.9 Notification Handler Completion Callback Function

Summary 2 3 The pmix_event_notification_cbfunc_fn_t is called by event handlers to indicate completion of their operations. 4 PMIx v2.0typedef void (*pmix event notification cbfunc fn t) 5 6 (pmix status t status, pmix info t *results, size t nresults, 7 pmix op cbfunc t cbfunc, void *thiscbdata, 8 void *notification cbdata); 9 IN 10 status 11 Status returned by the event handler's operation (pmix status t) 12 IN results Results from this event handler's operation on the event (pmix_info_t) 13 14 IN nresults 15 Number of elements in the results array (size_t) 16 IN cbfunc 17 pmix_op_cbfunc_t function to be executed when PMIx completes processing the callback (function reference) 18 IN thiscbdata 19 Callback data that was passed in to the handler (memory reference) 20 IN 21 cbdata Callback data to be returned when PMIx executes cbfunc (memory reference) 22 23 Description Define a callback by which an event handler can notify the PMIx library that it has completed its 24 response to the notification. The handler is required to execute this callback so the library can 25 determine if additional handlers need to be called. The handler shall return 26 PMIX EVENT ACTION COMPLETE if no further action is required. The return status of each 27 28 event handler and any returned **pmix info** t structures will be added to the results array of pmix info t passed to any subsequent event handlers to help guide their operation. 29 30 If non-NULL, the provided callback function will be called to allow the event handler to release the provided info array and execute any other required cleanup operations. 31 **Completion Callback Function Status Codes** 9.1.9.1 32 33 The following status code may be returned indicating various actions taken by other event handlers. PMIX EVENT NO ACTION TAKEN Event handler: No action taken. 34 PMIX EVENT PARTIAL ACTION TAKEN Event handler: Partial action taken. 35 PMIX EVENT ACTION DEFERRED Event handler: Action deferred. 36

PMIX EVENT ACTION COMPLETE

37

Event handler: Action complete.

CHAPTER 10

2

3

4

5 6

7

9

Data Packing and Unpacking

PMIx intentionally does not include support for internode communications in the standard, instead relying on its host SMS environment to transfer any needed data and/or requests between nodes. These operations frequently involve PMIx-defined public data structures that include binary data. Many HPC clusters are homogeneous, and so transferring the structures can be done rather simply. However, greater effort is required in heterogeneous environments to ensure binary data is correctly transferred. PMIx buffer manipulation functions are provided for this purpose via standardized interfaces to ease adoption.

10.1 Data Buffer Type

The pmix_data_buffer_t structure describes a data buffer used for packing and unpacking.

```
PMIx v2.0
10
            typedef struct pmix_data_buffer {
                /** Start of my memory */
11
                char *base_ptr;
12
                /** Where the next data will be packed to
13
                     (within the allocated memory starting
14
15
                    at base_ptr) */
                char *pack ptr;
16
                /** Where the next data will be unpacked
17
                    from (within the allocated memory
18
19
                    starting as base ptr) */
20
                char *unpack ptr;
                /** Number of bytes allocated (starting
21
                    at base_ptr) */
22
                size_t bytes_allocated;
23
24
                /** Number of bytes used by the buffer
25
                     (i.e., amount of data - including
                    overhead - packed in the buffer) */
26
27
                size_t bytes_used;
            } pmix_data_buffer_t;
28
```

1 10.2 Support Macros

2		PMIx provides a set of convenience macros for creating, initiating, and releasing data buffers.			
3		PMIX_DATA_BUFFER_CREATE			
4		Allocate memory for a pmix_data_buffer_t object and initialize it. This macro uses <i>calloc</i> to			
5					
	PMIx v2.0	C -			
6		PMIX DATA BUFFER CREATE (buffer);			
U		FMIX_DATA_BOFF EX_CREATE (DUTTET) ,			
7		OUT buffer			
8		Variable to be assigned the pointer to the allocated <code>pmix_data_buffer_t</code> (handle)			
9		PMIX_DATA_BUFFER_RELEASE			
0		Free a pmix_data_buffer_t object and the data it contains. Free's the data contained in the			
11		buffer, and then free's the buffer itself			
	PMIx v2.0	C			
	1 W11x V2.0				
12		PMIX_DATA_BUFFER_RELEASE (buffer);			
13		IN buffer			
14		Pointer to the pmix_data_buffer_t to be released (handle)			
		. = = (
15		PMIX_DATA_BUFFER_CONSTRUCT			
16		Initialize a statically declared <pre>pmix_data_buffer_t</pre> object.			
	PMIx v2.0	C			
17		PMIX_DATA_BUFFER_CONSTRUCT(buffer);			
1 /		PMIX_DATA_BOFFER_CONSTRUCT(Duffer),			
18		IN buffer			
9		Pointer to the allocated pmix_data_buffer_t that is to be initialized (handle)			
20		PMIX_DATA_BUFFER_DESTRUCT			
21		Release the data contained in a pmix_data_buffer_t object.			
	PMIx v2.0	C			
22		PMIX_DATA_BUFFER_DESTRUCT(buffer);			
_		C			
23		IN buffer			
24		Pointer to the pmix_data_buffer_t whose data is to be released (handle)			

```
1
               PMIX_DATA_BUFFER_LOAD
 2
               Load a blob into a pmix data buffer t object. Load the given data into the provided
               pmix data buffer t object, usually done in preparation for unpacking the provided data.
 3
 4
               Note that the data is not copied into the buffer - thus, the blob must not be released until after
 5
               operations on the buffer have completed.
   PMIx v2.0
 6
               PMIX DATA BUFFER LOAD (buffer, data, size);
 7
               IN
                     buffer
 8
                    Pointer to a pre-allocated pmix data buffer t (handle)
               IN
 9
10
                    Pointer to a blob (char*)
               IN
                     size
11
12
                    Number of bytes in the blob size t
13
               PMIX_DATA_BUFFER_UNLOAD
14
               Unload the data from a pmix data buffer t object. Extract the data in a buffer, assigning the
               pointer to the data (and the number of bytes in the blob) to the provided variables, usually done to
15
               transmit the blob to a remote process for unpacking. The buffer's internal pointer will be set to
16
               NULL to protect the data upon buffer destruct or release - thus, the user is responsible for releasing
17
18
               the blob when done with it.
   PMIx v2.0
               PMIX DATA BUFFER UNLOAD (buffer, data, size);
19
20
               IN
                     buffer
21
                    Pointer to the pmix_data_buffer_t whose data is to be extracted (handle)
22
               OUT data
                    Variable to be assigned the pointer to the extracted blob (void*)
23
               OUT size
24
                     Variable to be assigned the number of bytes in the blob size_t
25
    10.3
               General Routines
27
                The following routines are provided to support internode transfers in heterogeneous environments.
    10.3.1
                PMIx_Data_pack
29
               Summary
               Pack one or more values of a specified type into a buffer, usually for transmission to another process.
30
```

ı		1 01	C		
	PMIx v2.0		U		
2		pmix_status_t			
3		PMIx_Data_pack(const pmix_proc_t *target,			
4			<pre>pmix_data_buffer_t *buffer,</pre>		
5			<pre>void *src, int32_t num_vals,</pre>		
6			<pre>pmix_data_type_t type);</pre>		
			C		
_		INI			
7		IN	target		
8			Pointer to a pmix_proc_t containing the nspace/rank of the process that will be unpacking		
9			the final buffer. A NULL value may be used to indicate that the target is based on the same		
10		INI	PMIx version as the caller. Note that only the target's nspace is relevant. (handle)		
11		IN	buffer Diving to a grain of the buffer of the standard data in the buffer of the standard (bondle)		
12		INI	Pointer to a pmix_data_buffer_t where the packed data is to be stored (handle)		
13		IN	STC		
14			Pointer to a location where the data resides. Strings are to be passed as (char **) — i.e., the		
15			caller must pass the address of the pointer to the string as the (void*). This allows the caller to		
16		INI	pass multiple strings in a single call. (memory reference)		
17		IN	num_vals		
8			Number of elements pointed to by the <i>src</i> pointer. A string value is counted as a single value		
19			regardless of length. The values must be contiguous in memory. Arrays of pointers (e.g.,		
20			string arrays) should be contiguous, although the data pointed to need not be contiguous		
21		INI	across array entries.(int32_t)		
22		IN	type		
23			The type of the data to be packed (pmix_data_type_t)		
24		Retu	urns one of the following:		
25		PM	IX_SUCCESS The data has been packed as requested		
26			IX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.		
27			IIX_ERR_BAD_PARAM The provided buffer or src is NULL		
28			IX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this		
29			implementation		
30		PM	IIX_ERR_OUT_OF_RESOURCE Not enough memory to support the operation		
31			IX ERROR General error		
32			scription		
33			pack function packs one or more values of a specified type into the specified buffer. The buffer		
34			t have already been initialized via the PMIX_DATA_BUFFER_CREATE or		
35			X_DATA_BUFFER_CONSTRUCT macros — otherwise, PMIx_Data_pack will return an		
36		erro	r. Providing an unsupported type flag will likewise be reported as an error.		
37		Note	e that any data to be packed that is not hard type cast (i.e., not type cast to a specific size) may		
38			precision when unpacked by a non-homogeneous recipient. The PMIx_Data_pack function		

will do its best to deal with heterogeneity issues between the packer and unpacker in such cases. Sending a number larger than can be handled by the recipient will return an error code (generated upon unpacking) — the error cannot be detected during packing.

The namespace of the intended recipient of the packed buffer (i.e., the process that will be unpacking it) is used solely to resolve any data type differences between PMIx versions. The recipient must, therefore, be known to the user prior to calling the pack function so that the PMIx library is aware of the version the recipient is using. Note that all processes in a given namespace are *required* to use the same PMIx version — thus, the caller must only know at least one process from the target's namespace.

10.3.2 PMIx_Data_unpack

Summary

Unpack values from a pmix_data_buffer_t

Format

PMIx v2.0

IN source

Pointer to a pmix_proc_t structure containing the nspace/rank of the process that packed the provided buffer. A NULL value may be used to indicate that the source is based on the same PMIx version as the caller. Note that only the source's nspace is relevant. (handle)

IN buffer

A pointer to the buffer from which the value will be extracted. (handle)

INOUT doct

A pointer to the memory location into which the data is to be stored. Note that these values will be stored contiguously in memory. For strings, this pointer must be to (char**) to provide a means of supporting multiple string operations. The unpack function will allocate memory for each string in the array - the caller must only provide adequate memory for the array of pointers. (void*)

INOUT max num values

The number of values to be unpacked — upon completion, the parameter will be set to the actual number of values unpacked. In most cases, this should match the maximum number provided in the parameters — but in no case will it exceed the value of this parameter. Note that unpacking fewer values than are actually available will leave the buffer in an unpackable state — the function will return an error code to warn of this condition.(int32_t)

IN type

 The type of the data to be unpacked — must be one of the PMIx defined data types (pmix_data_type_t)

Returns one of the following:

PMIX_SUCCESS The data has been unpacked as requested

PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

PMIX_ERR_BAD_PARAM The provided buffer or dest is NULL

PMIX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this implementation

PMIX_ERR_ONE_OF_RECONDER Not enough preparation.

PMIX_ERR_OUT_OF_RESOURCE Not enough memory to support the operation PMIX_ERROR General error

Description

The unpack function unpacks the next value (or values) of a specified type from the given buffer. The buffer must have already been initialized via an PMIX_DATA_BUFFER_CREATE or PMIX_DATA_BUFFER_CONSTRUCT call (and assumedly filled with some data) — otherwise, the unpack_value function will return an error. Providing an unsupported type flag will likewise be reported as an error, as will specifying a data type that *does not* match the type of the next item in the buffer. An attempt to read beyond the end of the stored data held in the buffer will also return an error.

Note that it is possible for the buffer to be corrupted and that PMIx will *think* there is a proper variable type at the beginning of an unpack region — but that the value is bogus (e.g., just a byte field in a string array that so happens to have a value that matches the specified data type flag). Therefore, the data type error check is *not* completely safe.

Unpacking values is a "nondestructive" process — i.e., the values are not removed from the buffer. It is therefore possible for the caller to re-unpack a value from the same buffer by resetting the unpack_ptr.

Warning: The caller is responsible for providing adequate memory storage for the requested data. The user must provide a parameter indicating the maximum number of values that can be unpacked into the allocated memory. If more values exist in the buffer than can fit into the memory storage, then the function will unpack what it can fit into that location and return an error code indicating that the buffer was only partially unpacked.

Note that any data that was not hard type cast (i.e., not type cast to a specific size) when packed may lose precision when unpacked by a non-homogeneous recipient. PMIx will do its best to deal with heterogeneity issues between the packer and unpacker in such cases. Sending a number larger than can be handled by the recipient will return an error code generated upon unpacking — these errors cannot be detected during packing.

The namespace of the process that packed the buffer is used solely to resolve any data type differences between PMIx versions. The packer must, therefore, be known to the user prior to calling the pack function so that the PMIx library is aware of the version the packer is using. Note

that all processes in a given namespace are *required* to use the same PMIx version — thus, the caller must only know at least one process from the packer's namespace.

10.3.3 PMIx_Data_copy

Summary

Copy a data value from one location to another.

Format

PMIx v2.0

1

4 5

6

7

8

9

10

11 12

13

14

15 16

17

18

19 20

21

22 23

24

25 26

27

28

29

31 32 C

IN dest

The address of a pointer into which the address of the resulting data is to be stored. (void**)

IN src

A pointer to the memory location from which the data is to be copied (handle)

IN type

The type of the data to be copied — must be one of the PMIx defined data types.

(pmix_data_type_t)

Returns one of the following:

PMIX_SUCCESS The data has been copied as requested

PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

PMIX ERR BAD PARAM The provided src or dest is NULL

PMIX_ERR_UNKNOWN_DATA_TYPE The specified data type is not known to this implementation

PMIX_ERR_OUT_OF_RESOURCE Not enough memory to support the operation

PMIX_ERROR General error

Description

Since registered data types can be complex structures, the system needs some way to know how to copy the data from one location to another (e.g., for storage in the registry). This function, which can call other copy functions to build up complex data types, defines the method for making a copy of the specified data type.

10.3.4 PMIx Data print

Summary

Pretty-print a data value.

```
Format
 1
   PMIx v2.0
 2
               pmix_status_t
 3
               PMIx_Data_print(char **output, char *prefix,
 4
                                    void *src, pmix data type t type);
               IN
 5
                    output
 6
                    The address of a pointer into which the address of the resulting output is to be stored.
 7
                    (char**)
 8
               IN
                    prefix
 9
                    String to be prepended to the resulting output (char*)
10
               IN
                    A pointer to the memory location of the data value to be printed (handle)
11
               IN
                    type
12
13
                    The type of the data value to be printed — must be one of the PMIx defined data types.
                    (pmix_data_type_t)
14
               Returns one of the following:
15
                PMIX_SUCCESS The data has been printed as requested
16
17
                PMIX ERR BAD PARAM The provided data type is not recognized.
18
                PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.
               Description
19
               Since registered data types can be complex structures, the system needs some way to know how to
20
21
               print them (i.e., convert them to a string representation). Primarily for debug purposes.
    10.3.5
               PMIx_Data_copy_payload
               Summary
23
               Copy a payload from one buffer to another
24
               Format
25
   PMIx v2.0
```

IN dest
 Pointer to the destination pmix_data_buffer_t (handle)
IN src
 Pointer to the source pmix_data_buffer_t (handle)

Returns one of the following:

PMIX_SUCCESS The data has been copied as requested

PMIX_ERR_BAD_PARAM The src and dest pmix_data_buffer_t types do not match

PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function.

Description

This function will append a copy of the payload in one buffer into another buffer. Note that this is *not* a destructive procedure — the source buffer's payload will remain intact, as will any pre-existing payload in the destination's buffer. Only the unpacked portion of the source payload will be copied.

CHAPTER 11

29

Process Management

This chapter defines functionality processes can use to abort processes, spawn processes, and determine the relative locality of local processes. 2 11.1 **Abort** PMIx provides a dedicated API by which an application can request that specified processes be 4 5 aborted by the system. 11.1.1 PMIx Abort 7 Summary Abort the specified processes 8 **Format** PMIx v1.0 10 pmix_status_t 11 PMIx_Abort(int status, const char msg[], 12 pmix_proc_t procs[], size_t nprocs) 13 IN status Error code to return to invoking environment (integer) 14 IN 15 String message to be returned to user (string) 16 17 IN procs Array of pmix_proc_t structures (array of handles) 18 IN 19 Number of elements in the *procs* array (integer) 20 21 Returns one of the following: 22 • PMIX_SUCCESS if the operation was successfully completed. Note that the function shall not return in this situation if the caller's own process was included in the request. 23 24 PMIX ERR PARAM VALUE NOT SUPPORTED if the PMIx implementation and host 25 environment support this API, but the request includes processes that the host environment cannot abort - e.g., if the request is to abort subsets of processes from a namespace, or processes 26 outside of the caller's own namespace, and the host environment does not permit such 27 operations. In this case, none of the specified processes will be terminated. 28

• a PMIx error constant indicating an error in the request.

Description

Request that the host resource manager print the provided message and abort the provided array of procs. A Unix or POSIX environment should handle the provided status as a return error code from the main program that launched the application. A **NULL** for the procs array indicates that all processes in the caller's namespace are to be aborted, including itself - this is the equivalent of passing a **pmix_proc_t** array element containing the caller's namespace and a rank value of **PMIX_RANK_WILDCARD**. While it is permitted for a caller to request abort of processes from namespaces other than its own, not all environments will support such requests. Passing a **NULL** msg parameter is allowed.

The function shall not return until the host environment has carried out the operation on the specified processes. If the caller is included in the array of targets, then the function will not return unless the host is unable to execute the operation.

Advice to users

The response to this request is somewhat dependent on the specific RM and its configuration (e.g., some resource managers will not abort the application if the provided status is zero unless specifically configured to do so, some cannot abort subsets of processes in an application, and some may not permit termination of processes outside of the caller's own namespace), and thus lies outside the control of PMIx itself. However, the PMIx client library shall inform the RM of the request that the specified *procs* be aborted, regardless of the value of the provided status.

Note that race conditions caused by multiple processes calling **PMIx_Abort** are left to the server implementation to resolve with regard to which status is returned and what messages (if any) are printed.

11.2 Process Creation

The **PMIx_Spawn** commands spawn new processes and/or applications in the PMIx universe. This may include requests to extend the existing resource allocation or obtain a new one, depending upon provided and supported attributes.

26 11.2.1 PMIx Spawn

Summary

Spawn a new job.

```
Format
 1
   PMIx v1.0
 2
               pmix status t
               PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo,
 3
                              const pmix app t apps[], size t napps,
 4
 5
                              char nspace[])
               IN
                     job info
 6
 7
                    Array of info structures (array of handles)
                    ninfo
               IN
 8
 9
                    Number of elements in the job info array (integer)
10
               IN
                     apps
                    Array of pmix_app_t structures (array of handles)
11
               IN
                    napps
12
13
                    Number of elements in the apps array (integer)
               OUT nspace
14
                    Namespace of the new job (string)
15
16
               Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
                                                 Required Attributes
17
               PMIx libraries are not required to directly support any attributes for this function. However, any
               provided attributes must be passed to the host environment for processing.
18
19
               Host environments are required to support the following attributes when present in either the
20
               job_info or the info array of an element of the apps array:
               PMIX_WDIR "pmix.wdir" (char*)
21
22
                      Working directory for spawned processes.
23
               PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)
24
                      Set the current working directory to the session working directory assigned by the RM - can
                      be assigned to the entire job (by including attribute in the job_info array) or on a
25
                      per-application basis in the info array for each pmix_app_t.
26
27
               PMIX_PREFIX "pmix.prefix" (char*)
28
                      Prefix to use for starting spawned processes - i.e., the directory where the executables can be
                      found.
29
30
               PMIX_HOST "pmix.host" (char*)
                      Comma-delimited list of hosts to use for spawned processes.
31
32
               PMIX_HOSTFILE "pmix.hostfile" (char*)
                      Hostfile to use for spawned processes.
33
```

	→
1	The following attributes are optional for host environments that support this operation:
2	PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation.
4 5	PMIX_ADD_HOST "pmix.addhost" (char*) Comma-delimited list of hosts to add to the allocation.
6 7	PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) Preload executables onto nodes prior to executing launch procedure.
8 9	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
10 11 12	PMIX_PERSONALITY "pmix.pers" (char*) Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.
13 14	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
15 16	<pre>PMIX_PPR "pmix.ppr" (char*) Number of processes to spawn on each identified resource.</pre>
17 18 19 20	<pre>PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.</pre>
21 22 23 24	<pre>PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.</pre>
25 26 27 28	<pre>PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.</pre>
29 30	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
31 32 33 34	PMIX_TAG_OUTPUT "pmix.tagout" (bool) Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
35	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)

1 2	Timestamp output - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t .
3 4 5 6	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool) Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.
7 8 9 10	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</filename></pre>
11 12	PMIX_INDEX_ARGV "pmix.indxargv" (bool) Mark the argv with the rank of the process.
13 14 15 16	<pre>PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.</pre>
17 18	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.
19 20 21	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
22 23	<pre>PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.</pre>
24 25 26 27	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
28 29	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
30 31	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
32 33 34 35	PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.
36 37	PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) Set the envar to the given value, overwriting any pre-existing one

1 2	<pre>PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.</pre>
3 4	<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*) Add the environment variable, but do not overwrite any pre-existing one</pre>
5 6 7	<pre>PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
8 9 10	PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist
1 2 3	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*) Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist</pre>
14 15 16	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
17 18	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.</pre>
19 20	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
21 22	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
23 24	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
25 26 27	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
28 29	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
30 31 32	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
33 34 35	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
36	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)</pre>

Fabric quality of service level for the job being requested in an allocation request. PMIX ALLOC FABRIC TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request. PMIX ALLOC FABRIC PLANE "pmix.alloc.netplane" (char*) ID string for the *fabric plane* to be used for the requested allocation. PMIX ALLOC FABRIC ENDPTS "pmix.alloc.endpts" (size t) Number of endpoints to allocate per *process* in the job. PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per *node* for the job. PMIX_COSPAWN_APP "pmix.cospawn" (bool) Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., PMIX_RANK within the job) provided to any other application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application. PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool) Indicate that the job being spawned is a tool. PMIX EVENT SILENT TERMINATION "pmix.evsilentterm" (bool) Do not generate an event when this job normally terminates. **Description** Spawn a new job. The assigned namespace of the spawned applications is returned in the *nspace* parameter. A NULL value in that location indicates that the caller doesn't wish to have the namespace returned. The nspace array must be at least of size one more than PMIX MAX NSLEN. By default, the spawned processes will be PMIx "connected" to the parent process upon successful launch (see Section 11.3 for details). This includes that (a) the parent process will be given a copy of the new job's information so it can query job-level info without incurring any communication penalties, (b) newly spawned child processes will receive a copy of the parent processes job-level info, and (c) both the parent process and members of the child job will receive notification of errors from processes in their combined assemblage. Advice to users Behavior of individual resource managers may differ, but it is expected that failure of any application process to start will result in termination/cleanup of all processes in the newly spawned

job and return of an error code to the caller.

1

2

3

4

5 6

7

8

9

10

11

12

13 14

15

16 17

18

19

20 21

22

23 24

25

26

27

28

29

30

- Advice to PMIx library implementers -

Tools may utilize **PMIx_Spawn** to start intermediate launchers as described in Section 17.2.2. For times where the tool is not attached to a PMIx server, internal support for fork/exec of the specified applications would allow the tool to maintain a single code path for both the connected and disconnected cases. Inclusion of such support is recommended, but not required.

11.2.2 PMIx_Spawn_nb

6 Summary

Nonblocking version of the **PMIx_Spawn** routine.

Format

PMIx v1.0

1 2

3

7

8

9

10

11

12

13

14

15

16

17

18 19

20

21 22

23

24

25

26 27 C

IN job_info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *job info* array (integer)

IN apps

Array of pmix_app_t structures (array of handles)

IN cbfunc

Callback function pmix_spawn_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- a PMIx error constant indicating an error in the request the *cbfunc* will *not* be called

Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any 1 provided attributes must be passed to the host SMS daemon for processing. 2 3 Host environments are required to support the following attributes when present in either the *job info* or the *info* array of an element of the *apps* array: 5 PMIX WDIR "pmix.wdir" (char*) Working directory for spawned processes. 6 7 PMIX SET SESSION CWD "pmix.ssncwd" (bool) Set the current working directory to the session working directory assigned by the RM - can 8 be assigned to the entire job (by including attribute in the job info array) or on a 9 per-application basis in the *info* array for each pmix app t. 10 PMIX PREFIX "pmix.prefix" (char*) 11 Prefix to use for starting spawned processes - i.e., the directory where the executables can be 12 found. 13 14 PMIX HOST "pmix.host" (char*) 15 Comma-delimited list of hosts to use for spawned processes. PMIX HOSTFILE "pmix.hostfile" (char*) 16 Hostfile to use for spawned processes. 17 Optional Attributes The following attributes are optional for host environments that support this operation: 18 PMIX ADD HOSTFILE "pmix.addhostfile" (char*) 19 Hostfile containing hosts to add to existing allocation. 20 21 PMIX ADD HOST "pmix.addhost" (char*) Comma-delimited list of hosts to add to the allocation. 22 PMIX PRELOAD BIN "pmix.preloadbin" (bool) 23 Preload executables onto nodes prior to executing launch procedure. 24 PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) 25 26 Comma-delimited list of files to pre-position on nodes prior to executing launch procedure. PMIX_PERSONALITY "pmix.pers" (char*) 27 Name of personality corresponding to programming model used by application - supported 28 values depend upon PMIx implementation. 29 PMIX_DISPLAY_MAP "pmix.dispmap" (bool) 30 Display process mapping upon spawn. 31 32 PMIX_PPR "pmix.ppr" (char*)

1	Number of processes to spawn on each identified resource.
2 3 4 5	PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.
6 7 8 9	PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.
10 11 12 13	PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
14 15	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
16 17 18 19	PMIX_TAG_OUTPUT "pmix.tagout" (bool) Tag stdout/stderr with the identity of the source process - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
20 21 22	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool) Timestamp output - can be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i> array for each pmix_app_t.
23 24 25 26	<pre>PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool) Merge stdout and stderr streams - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</pre>
27 28 29 30	<pre>PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*) Direct output (both stdout and stderr) into files of form "<filename>.rank" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</filename></pre>
31 32	PMIX_INDEX_ARGV "pmix.indxargv" (bool) Mark the argv with the rank of the process.
33 34 35 36	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.
37 38	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.

1 2 3	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
4 5	PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.
6 7 8 9	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
10 11	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
12 13	<pre>PMIX_JOB_CONTINUOUS "pmix.continuous" (bool)</pre>
14 15 16 17	<pre>PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.</pre>
18 19	<pre>PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) Set the envar to the given value, overwriting any pre-existing one</pre>
20 21	<pre>PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) Unset the environment variable specified in the string.</pre>
22 23	<pre>PMIX_ADD_ENVAR "pmix.envar.add" (pmix_envar_t*) Add the environment variable, but do not overwrite any pre-existing one</pre>
24 25 26	<pre>PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) Prepend the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
27 28 29	<pre>PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator character, creating the variable if it doesn't already exist</pre>
30 31 32	<pre>PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*) Ensure the given value appears first in the specified envar using the separator character, creating the envar if it doesn't already exist</pre>
33 34 35	<pre>PMIX_ALLOC_QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being referenced in a query.</pre>
36 37	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.

1 2	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
3 4	PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.
5 6	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.
7 8 9	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
10 11	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
12 13 14	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
15 16 17	<pre>PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.</pre>
18 19	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>
20 21	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*) Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.</pre>
22 23	<pre>PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the fabric plane to be used for the requested allocation.</pre>
24 25	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per process in the job.</pre>
26 27	<pre>PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per node for the job.</pre>
28 29 30 31 32	PMIX_COSPAWN_APP "pmix.cospawn" (bool) Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., PMIX_RANK within the job) provided to any other application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application.
33 34	PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool) Indicate that the job being spawned is a tool.
35 36	<pre>PMIX_EVENT_SILENT_TERMINATION "pmix.evsilentterm" (bool) Do not generate an event when this job normally terminates.</pre>

1	Descri	ption
•		

2

4 5

8

10

11

12

13 14

15 16

17

18

20

21 22

23 24

25 26

27

28

29

30

31 32

33

Nonblocking version of the **PMIx_Spawn** routine. The provided callback function will be executed upon successful start of *all* specified application processes.

Advice to users

Behavior of individual resource managers may differ, but it is expected that failure of any application process to start will result in termination/cleanup of all processes in the newly spawned job and return of an error code to the caller.

11.2.3 Spawn-specific constants

In addition to the generic error constants, the following spawn-specific error constants may be returned by the spawn APIs:

PMIX_ERR_JOB_ALLOC_FAILED The job request could not be executed due to failure to obtain the specified allocation

PMIX_ERR_JOB_APP_NOT_EXECUTABLE The specified application executable either could not be found, or lacks execution privileges.

PMIX_ERR_JOB_NO_EXE_SPECIFIED The job request did not specify an executable.

PMIX_ERR_JOB_FAILED_TO_MAP The launcher was unable to map the processes for the specified job request.

PMIX_ERR_JOB_FAILED_TO_LAUNCH One or more processes in the job request failed to launch

19 11.2.4 Spawn attributes

Attributes used to describe PMIx_Spawn behavior - they are values passed to the PMIx_Spawn API and therefore are not accessed using the PMIx_Get APIs when used in that context. However, some of the attributes defined in this section can be provided by the host environment for other purposes - e.g., the host might provide the PMIX_MAPBY attribute in the job-related information so that an application can use PMIx_Get to discover the mapping used for determining process locations. Multi-use attributes and their respective access reference rank are denoted below.

PMIX PERSONALITY "pmix.pers" (char*)

Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.

PMIX_HOST "pmix.host" (char*)

Comma-delimited list of hosts to use for spawned processes.

 ${\tt PMIX_HOSTFILE} \ "\texttt{pmix.hostfile}" \ (\texttt{char} \star)$

Hostfile to use for spawned processes.

PMIX_ADD_HOST "pmix.addhost" (char*)

1	Comma-delimited list of hosts to add to the allocation.
2	PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*)
3	Hostfile containing hosts to add to existing allocation.
4	PMIX_PREFIX "pmix.prefix" (char*)
5	Prefix to use for starting spawned processes - i.e., the directory where the executables can be
6	found.
7	PMIX_WDIR "pmix.wdir" (char*)
8	Working directory for spawned processes.
9	PMIX_DISPLAY_MAP "pmix.dispmap" (bool)
10	Display process mapping upon spawn.
11	PMIX_PPR "pmix.ppr" (char*)
12	Number of processes to spawn on each identified resource.
13	PMIX_MAPBY "pmix.mapby" (char*)
14	Process mapping policy - when accessed using PMIx_Get, use the
15	PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the
16	provided namespace. Supported values are launcher specific.
17	PMIX_RANKBY "pmix.rankby" (char*)
18	Process ranking policy - when accessed using PMIx_Get , use the
19	PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the
20	provided namespace. Supported values are launcher specific.
21	PMIX_BINDTO "pmix.bindto" (char*)
22	Process binding policy - when accessed using PMIx_Get , use the
23	PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the
24	provided namespace. Supported values are launcher specific.
25	PMIX_PRELOAD_BIN "pmix.preloadbin" (bool)
26	Preload executables onto nodes prior to executing launch procedure.
27	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*)</pre>
28	Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.
29	PMIX_STDIN_TGT "pmix.stdin" (uint32_t)
30	Spawned process rank that is to receive any forwarded stdin .
31	PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool)
32	Set the current working directory to the session working directory assigned by the RM - can
33	be assigned to the entire job (by including attribute in the <i>job_info</i> array) or on a
34	per-application basis in the <i>info</i> array for each pmix_app_t .
35	PMIX_TAG_OUTPUT "pmix.tagout" (bool)
36	Tag stdout/stderr with the identity of the source process - can be assigned to the entire
37	job (by including attribute in the <i>job_info</i> array) or on a per-application basis in the <i>info</i>
38	array for each pmix_app_t.
39	PMIX_TIMESTAMP_OUTPUT "pmix.tsout" (bool)
40	Timestamp output - can be assigned to the entire job (by including attribute in the <i>job_info</i>
41	array) or on a per-application basis in the <i>info</i> array for each pmix_app_t .
42	PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool)

1	Merge stdout and stderr streams - can be assigned to the entire job (by including
2	attribute in the job_info array) or on a per-application basis in the info array for each
3	<pre>pmix_app_t.</pre>
4	PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*)
5	Direct output (both stdout and stderr) into files of form " <filename>.rank" - can be</filename>
6	assigned to the entire job (by including attribute in the job_info array) or on a per-application
7	basis in the <i>info</i> array for each pmix_app_t .
8	PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*)
9	Direct output into files of form " <directory>/<jobid>/rank.<rank>/</rank></jobid></directory>
10	stdout[err]" - can be assigned to the entire job (by including attribute in the <i>job_info</i>
11	array) or on a per-application basis in the <i>info</i> array for each pmix_app_t .
12	PMIX_INDEX_ARGV "pmix.indxargv" (bool)
13	Mark the argv with the rank of the process.
14	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t)
15	Number of PUs to assign to each rank - when accessed using PMIx_Get, use the
16	PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the
17	provided namespace.
18	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool)
19	Do not place processes on the head node.
20	PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool)
21	Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a
22	node.
23	PMIX_REPORT_BINDINGS "pmix.repbind" (bool)
24	Report bindings of the individual processes.
25	PMIX_CPU_LIST "pmix.cpulist" (char*)
26	List of PUs to use for this job - when accessed using PMIx_Get, use the
27	PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided
28	namespace.
29	PMIX_JOB_RECOVERABLE "pmix.recover" (bool)
30	Application supports recoverable operations.
31	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool)
32	Application is continuous, all failed processes should be immediately restarted.
33	PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t)
34	Maximum number of times to restart a process - when accessed using PMIx_Get , use the
35	PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided
36	namespace.
37	PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool)
38	Indicate that the job being spawned is a tool.
39	PMIX_TIMEOUT_STACKTRACES "pmix.tim.stack" (bool)
40	Include process stacktraces in timeout report from a job.
41	PMIX_TIMEOUT_REPORT_STATE "pmix.tim.state" (bool)
42	Report process states in timeout report from a job.
43	PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool)
-	_ · · · <u>-</u> F ()

1	Requests that the launcher generate the PMIX_EVENT_JOB_START,
2	PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to
3	include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP
4	indicating the time the event occurred. Note that the requester must register for these
5	individual events, or capture and process them by registering a default event handler instead
6	of individual handlers and then process the events based on the returned status code.
7	Another common method is to register one event handler for all job-related events, with a
8	separate handler for non-job events - see PMIx_Register_event_handler for details
9	PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)
0	Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or
1	abnormal termination of the spawned job. The event shall include the returned status code
2	(PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID)
3	and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a
4	PMIX_EVENT_TIMESTAMP indicating the time the termination occurred. Note that the
5	requester must register for the event or capture and process it within a default event handler.
6	PMIX_NOTIFY_PROC_TERMINATION "pmix.noteproc" (bool)
7	Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event
8	whenever a process either normally or abnormally terminates.
9	PMIX_NOTIFY_PROC_ABNORMAL_TERMINATION "pmix.noteabproc" (bool)
20	Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event only
21	when a process abnormally terminates.
2	PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool)
23	Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event whenever a
24	process either normally or abnormally terminates.
25	PMIX_LOG_PROC_ABNORMAL_TERMINATION "pmix.logabproc" (bool)
26	Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event only when a
27	process abnormally terminates.
28	PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool)
29	Requests that the launcher log the PMIX_EVENT_JOB_START,
80	PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log,
31	subject to the logging attributes of Section 12.4.3.
2	PMIX_LOG_COMPLETION "pmix.logcomp" (bool)
3	Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal
84	termination of the spawned job using PMIx_Log , subject to the logging attributes of
15	Section 12.4.3. The event shall include the returned status code
86	(PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID)
37	and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a
8	PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.
9	PMIX_EVENT_SILENT_TERMINATION "pmix.evsilentterm" (bool)
0	Do not generate an event when this job normally terminates.

Attributes used to adjust remote environment variables prior to spawning the specified application processes.


41

```
PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*)
1
2
                    Set the envar to the given value, overwriting any pre-existing one
 3
              PMIX_UNSET_ENVAR "pmix.envar.unset" (char*)
                    Unset the environment variable specified in the string.
 4
              PMIX ADD ENVAR "pmix.envar.add" (pmix envar t*)
 5
6
                    Add the environment variable, but do not overwrite any pre-existing one
 7
              PMIX PREPEND ENVAR "pmix.envar.prepnd" (pmix envar t*)
8
                    Prepend the given value to the specified environmental value using the given separator
9
                    character, creating the variable if it doesn't already exist
              PMIX APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*)
10
                    Append the given value to the specified environmental value using the given separator
11
12
                    character, creating the variable if it doesn't already exist
              PMIX_FIRST_ENVAR "pmix.envar.first" (pmix_envar_t*)
13
                    Ensure the given value appears first in the specified envar using the separator character,
14
15
                    creating the envar if it doesn't already exist
    11.2.5 Application Structure
16
              The pmix app t structure describes the application context for the PMIx Spawn and
17
              PMIx Spawn nb operations.
18
   PMIx v1.0
19
              typedef struct pmix app
                   /** Executable */
20
21
                   char *cmd;
22
                   /** Argument set, NULL terminated */
23
                   char **argv;
                   /** Environment set, NULL terminated */
24
25
                   char **env;
26
                   /** Current working directory */
27
                   char *cwd;
28
                   /** Maximum processes with this profile */
29
                   int maxprocs;
                   /** Array of info keys describing this application*/
30
31
                   pmix_info_t *info;
32
                   /** Number of info keys in 'info' array */
33
                   size t ninfo;
34
                pmix_app_t;
```

11.2.5.1 App structure support macros

36

The following macros are provided to support the **pmix_app_t** structure.



```
Free an app array
 1
2
               Release an array of pmix app t structures
   PMIx v1.0
3
               PMIX_APP_FREE(m, n)
               IN
4
                   Pointer to the array of pmix_app_t structures (handle)
 5
 6
               IN
 7
                   Number of structures in the array (size t)
               Create the info array of application directives
8
               Create an array of pmix_info_t structures for passing application-level directives, updating the
9
10
               ninfo field of the pmix_app_t structure.
   PMIx v2.2
11
               PMIX_APP_INFO_CREATE(m, n)
               IN
12
                   m
13
                   Pointer to the pmix app t structure (handle)
14
               IN
                   Number of directives to be allocated (size t)
15
    11.2.5.2
               Spawn Callback Function
16
               Summary
17
18
               The pmix_spawn_cbfunc_t is used on the PMIx client side by PMIx_Spawn_nb and on the
19
               PMIx server side by pmix_server_spawn_fn_t.
   PMIx v1.0
20
               typedef void (*pmix_spawn_cbfunc_t)
21
                    (pmix_status_t status,
22
                     pmix_nspace_t nspace, void *cbdata);
               IN
                    status
23
                   Status associated with the operation (handle)
24
25
               IN
                    nspace
                   Namespace string (pmix_nspace_t)
26
27
               IN
                   cbdata
28
                   Callback data passed to original API call (memory reference)
```

Description

The callback will be executed upon launch of the specified applications in **PMIx_Spawn_nb**, or upon failure to launch any of them.

The *status* of the callback will indicate whether or not the spawn succeeded. The *nspace* of the spawned processes will be returned, along with any provided callback data. Note that the returned *nspace* value will not be protected upon return from the callback function, so the receiver must copy it if it needs to be retained.

11.3 Connecting and Disconnecting Processes

This section defines functions to connect and disconnect processes in two or more separate PMIx namespaces. The PMIx definition of *connected* solely implies that the host environment should treat the failure of any process in the assemblage as a reportable event, taking action on the assemblage as if it were a single application. For example, if the environment defaults (in the absence of any application directives) to terminating an application upon failure of any process in that application, then the environment should terminate all processes in the connected assemblage upon failure of any member.

The host environment may choose to assign a new namespace to the connected assemblage and/or assign new ranks for its members for its own internal tracking purposes. However, it is not required to communicate such assignments to the participants (e.g., in response to an appropriate call to PMIx_Query_info_nb). The host environment is required to generate a PMIX_ERR_PROC_TERM_WO_SYNC event should any process in the assemblage terminate or call PMIx_Finalize without first disconnecting from the assemblage. If the job including the process is terminated as a result of that action, then the host environment is required to also generate the PMIX_ERR_JOB_TERM_WO_SYNC for all jobs that were terminated as a result.

Advice to PMIx server hosts ·

The *connect* operation does not require the exchange of job-level information nor the inclusion of information posted by participating processes via <code>PMIx_Put</code>. Indeed, the callback function utilized in <code>pmix_server_connect_fn_t</code> cannot pass information back into the PMIx server library. However, host environments are advised that collecting such information at the participating daemons represents an optimization opportunity as participating processes are likely to request such information after the connect operation completes.

Advice to users Attempting to *connect* processes solely within the same namespace is essentially a *no-op* operation. 1 While not explicitly prohibited, users are advised that a PMIx implementation or host environment 2 may return an error in such cases. 3 Neither the PMIx implementation nor host environment are required to provide any tracking 4 support for the assemblage. Thus, the application is responsible for maintaining the membership 5 6 list of the assemblage. 11.3.1 PMIx Connect Summary 8 Connect namespaces. 9 **Format** 10 PMIx v1.0 11 pmix status t 12 PMIx_Connect(const pmix_proc_t procs[], size_t nprocs, 13 const pmix_info_t info[], size_t ninfo) IN 14 procs 15 Array of proc structures (array of handles) 16 IN nprocs 17 Number of elements in the *procs* array (integer) 18 IN Array of info structures (array of handles) 19 IN ninfo 20 Number of elements in the *info* array (integer) 21 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. 22

Required Attributes

PMIx libraries are not required to directly support any attributes for this function. However, any

provided attributes must be passed to the host SMS daemon for processing.

23

	→ Optional Attributes
1	The following attributes are optional for PMIx implementations:
2	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All <i>clones</i> of the calling process must participate in the collective operation.
4	The following attributes are optional for host environments that support this operation:
5 6 7 8	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
9 10 11 12 13	Description Record the processes specified by the <i>procs</i> array as <i>connected</i> as per the PMIx definition. The function will return once all processes identified in <i>procs</i> have called either PMIx_Connect or its non-blocking version, <i>and</i> the host environment has completed any supporting operations required to meet the terms of the PMIx definition of <i>connected</i> processes.
14 15 16	A process can only engage in one connect operation involving the identical <i>procs</i> array at a time. However, a process can be simultaneously engaged in multiple connect operations, each involving a different <i>procs</i> array.
17 18	As in the case of the PMIx_Fence operation, the <i>info</i> array can be used to pass user-level directives regarding timeout constraints and other options available from the host RM.
	Advice to users
19 20 21 22	All processes engaged in a given PMIx_Connect operation must provide the identical <i>procs</i> array as ordering of entries in the array and the method by which those processes are identified (e.g., use of PMIX_RANK_WILDCARD versus listing the individual processes) <i>may</i> impact the host environment's algorithm for uniquely identifying an operation.
	Advice to PMIx library implementers —
23 24 25	PMIx_Connect and its non-blocking form are both <i>collective</i> operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.
	Advice to PMIx server hosts
26 27	The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating

nodes, and notify the local PMIx server library upon completion of the global collective.

11.3.2 PMIx_Connect_nb Summary Nonblocking **PMIx_Connect_nb** routine. 3 **Format** PMIx v1.0 5 pmix status t 6 PMIx_Connect_nb(const pmix_proc_t procs[], size_t nprocs, 7 const pmix_info_t info[], size_t ninfo, pmix_op_cbfunc_t cbfunc, void *cbdata) 8 9 IN procs Array of proc structures (array of handles) 10 IN nprocs 11 Number of elements in the *procs* array (integer) 12 IN info 13 Array of info structures (array of handles) 14 15 IN ninfo Number of elements in the *info* array (integer) 16 IN 17 cbfunc Callback function pmix op cbfunc t (function reference) 18 IN cbdata 19 20 Data to be passed to the callback function (memory reference) 21 Returns one of the following: • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 22 will be returned in the provided *cbfunc*. Note that the library must not invoke the callback 23 function prior to returning from the API. 24 • PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and 25 26 returned success - the cbfunc will not be called • a PMIx error constant indicating either an error in the input or that the request was immediately 27 processed and failed - the cbfunc will not be called 28 Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any 29 provided attributes must be passed to the host SMS daemon for processing. 30

```
Optional Attributes
 1
               The following attributes are optional for PMIx implementations:
 2
               PMIX ALL CLONES PARTICIPATE "pmix.clone.part" (bool)
 3
                      All clones of the calling process must participate in the collective operation.
               The following attributes are optional for host environments that support this operation:
 4
 5
               PMIX TIMEOUT "pmix.timeout" (int)
                      Time in seconds before the specified operation should time out (zero indicating infinite) and
 6
                      return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
 7
 8
                      caused by multiple layers (client, server, and host) simultaneously timing the operation.
               Description
 9
               Nonblocking version of PMIx Connect. The callback function is called once all processes
10
11
               identified in procs have called either PMIx_Connect or its non-blocking version, and the host
12
               environment has completed any supporting operations required to meet the terms of the PMIx
               definition of connected processes. See the advice provided in the description for PMIx_Connect
13
               for more information.
14
    11.3.3
                PMIx Disconnect
15
               Summary
16
               Disconnect a previously connected set of processes.
17
               Format
18
   PMIx v1.0
19
               pmix status t
20
               PMIx_Disconnect(const pmix_proc_t procs[], size_t nprocs,
                                      const pmix_info_t info[], size_t ninfo);
21
22
               IN
                     procs
                    Array of proc structures (array of handles)
23
               IN
24
                    Number of elements in the procs array (integer)
25
               IN
26
27
                    Array of info structures (array of handles)
               IN
                     ninfo
28
                    Number of elements in the info array (integer)
29
30
               Returns one of the following:
31
               • PMIX SUCCESS, indicating that the request was successfully executed
```

1 2	 the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of procs was not previously connected via a call to PMIx_Connect or its non-blocking form.
3	• a PMIx error constant indicating either an error in the input or that the request failed
	Required Attributes
4 5	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.
	▼ Optional Attributes
6	The following attributes are optional for PMIx implementations:
7 8	<pre>PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All clones of the calling process must participate in the collective operation.</pre>
9	The following attributes are optional for host environments that support this operation:
0 1 2 3	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
4	Description
5	Disconnect a previously connected set of processes. The function will return once all processes
6	identified in <i>procs</i> have called either PMIx_Disconnect or its non-blocking version, and the
7	host environment has completed any required supporting operations.
8	A process can only engage in one disconnect operation involving the identical <i>procs</i> array at a time.
9	However, a process can be simultaneously engaged in multiple disconnect operations, each
20	involving a different <i>procs</i> array.
21	As in the case of the PMIx_Fence operation, the info array can be used to pass user-level
22	directives regarding the algorithm to be used for any collective operation involved in the operation,
23	timeout constraints, and other options available from the host RM.
	Advice to users
24	All processes engaged in a given PMIx_Disconnect operation must provide the identical <i>procs</i>
25	array as ordering of entries in the array and the method by which those processes are identified
26	(e.g., use of PMIX_RANK_WILDCARD versus listing the individual processes) <i>may</i> impact the host
27	environment's algorithm for uniquely identifying an operation.

Advice to PMIx library implementers –

PMIx_Disconnect and its non-blocking form are both *collective* operations. Accordingly, the PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

Advice to PMIx server hosts

The host will receive a single call for each collective operation. The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

11.3.4 PMIx Disconnect nb

Summary

Nonblocking **PMIx_Disconnect** routine.

Format

PMIx v1.0

1

2

3

4 5

6

7

9

10

11

12

13

14 15

16

17

18

19

20 21

22

23

24 25

26

27

28

C

IN procs

Array of proc structures (array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function **pmix_op_cbfunc_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

1 2 3	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.			
4 5	 PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 			
• a PMIx error constant indicating either an error in the input or that the request war processed and failed - the <i>cbfunc</i> will <i>not</i> be called				
	▼ Required Attributes			
8 9	PMIx libraries are not required to directly support any attributes for this function. However, any provided attributes must be passed to the host SMS daemon for processing.			
	▼ Optional Attributes			
10	The following attributes are optional for PMIx implementations:			
11 12	PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool) All <i>clones</i> of the calling process must participate in the collective operation.			
13	The following attributes are optional for host environments that support this operation:			
14 15 16 17	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.			
18 19	Description Nonblocking PMIx_Disconnect routine. The callback function is called either:			
20 21	 to return the PMIX_ERR_INVALID_OPERATION error indicating that the specified set of procs was not previously connected via a call to PMIx_Connect or its non-blocking form; 			
22	• to return a PMIx error constant indicating that the operation failed; or			
23 24	 once all processes identified in <i>procs</i> have called either PMIx_Disconnect_nb or its blocking version, and the host environment has completed any required supporting operations. 			
25	See the advice provided in the description for PMIx_Disconnect for more information.			

11.4 Process Locality

The relative locality of processes is often used to optimize their interactions with the hardware and other processes. PMIx provides a means by which the host environment can communicate the locality of a given process using the <code>PMIx_server_generate_locality_string</code> to generate an abstracted representation of that value. This provides a human-readable format and allows the client to parse the locality string with a method of its choice that may differ from the one used by the server that generated it.

There are times, however, when relative locality and other PMIx-provided information doesn't include some element required by the application. In these instances, the application may need access to the full description of the local hardware topology. PMIx does not itself generate such descriptions - there are multiple third-party libraries that fulfill that role. Instead, PMIx offers an abstraction method by which users can obtain a pointer to the description. This transparently enables support for different methods of sharing the topology between the host environment (which may well have already generated it prior to local start of application processes) and the clients - e.g., through passing of a shared memory region.

16 11.4.1 PMIx_Load_topology

Summary

Load the local hardware topology description

Format

PMIx v4.0

pmix_status_t
PMIx_Load_topology(pmix_topology_t *topo);

INOUT topo

Address of a **pmix_topology_t** structure where the topology information is to be loaded (handle)

Returns **PMIX_SUCCESS**, indicating that the *topo* was successfully loaded, or an appropriate PMIx error constant.

Description

Obtain a pointer to the topology description of the local node. If the *source* field of the provided <code>pmix_topology_t</code> is set, then the PMIx library must return a description from the specified implementation or else indicate that the implementation is not available by returning the <code>PMIX_ERR_NOT_SUPPORTED</code> error constant.

The returned pointer may point to a shared memory region or an actual instance of the topology description. In either case, the description shall be treated as a "read-only" object - attempts to modify the object are likely to fail and return an error. The PMIx library is responsible for performing any required cleanup when the client library finalizes.

- Advice to users

It is the responsibility of the user to ensure that the *topo* argument is properly initialized prior to calling this API, and to check the returned *source* to verify that the returned topology description is compatible with the user's code.

11.4.2 PMIx Get_relative_locality

Summary

Get the relative locality of two local processes given their locality strings.

Format

PMIx v4.0

1

2

3

5

8

9

10 11

12

13

14

15 16

17

18

19

20

21

22

23

24

25

26 27

IN locality1

String returned by the PMIx server generate locality string API (handle)

IN locality2

String returned by the **PMIx_server_generate_locality_string** API (handle)

INOUT locality

Location where the relative locality bitmask is to be constructed (memory reference)

Returns **PMIX_SUCCESS**, indicating that the *locality* was successfully loaded, or an appropriate PMIx error constant.

Description

Parse the locality strings of two processes (as returned by **PMIx_Get** using the **PMIX_LOCALITY_STRING** key) and set the appropriate **pmix_locality_t** locality bits in the provided memory location.

11.4.2.1 Topology description

The **pmix_topology_t** structure contains a (case-insensitive) string identifying the source of the topology (e.g., "hwloc") and a pointer to the corresponding implementation-specific topology description.

```
PMIx v4.0

28 typedef struct pmix_topology {
29 char *source;
30 void *topology;
31 } pmix_topoology_t;
```

C

11.4.2.2 Topology support macros 2 The following macros support the pmix_topology_t structure. Initialize the topology structure 3 Initialize the pmix_topology_t fields to NULL PMIx v4.05 PMIX TOPOLOGY CONSTRUCT (m) 6 IN Pointer to the structure to be initialized (pointer to pmix_topology_t 7 Destruct the topology structure 8 Destruct the pmix_topology_t fields 9 PMIx v4.0 10 PMIX TOPOLOGY DESTRUCT (m) 11 IN m Pointer to the structure to be destructed (pointer to pmix_topology_t) 12 Create a topology array 13 Allocate and initialize a **pmix_topology_t** array. 14 PMIx v4.0 PMIX TOPOLOGY CREATE (m, n) 15 16 INOUT m Address where the pointer to the array of pmix_topology_t structures shall be stored 17 (handle) 18 IN 19 20 Number of structures to be allocated (size t) Release a topology array 21 22 Release a pmix topology t array. PMIx v4.0 23 PMIX_TOPOLOGY_FREE(m, n) 24 INOUT m 25 Address of the array of **pmix_topology_t** structures to be released (handle) 26 IN 27 Number of structures in the array (size t)

11.4.2.3 Relative locality of two processes

2 *PMIx v4.0* The pmix_locality_t datatype is a uint16_t bitmask that defines the relative locality of 3 two processes on a node. The following constants represent specific bits in the mask and can be used to test a locality value using standard bit-test methods. 4 5 PMIX_LOCALITY_UNKNOWN All bits are set to zero, indicating that the relative locality of the 6 two processes is unknown 7 The two processes do not share any common locations PMIX_LOCALITY_NONLOCAL 8 PMIX LOCALITY SHARE HWTHREAD The two processes share at least one hardware thread 9 PMIX LOCALITY SHARE CORE The two processes share at least one core 10 PMIX LOCALITY SHARE L1CACHE The two processes share at least an L1 cache The two processes share at least an L2 cache 11 PMIX_LOCALITY_SHARE_L2CACHE 12 PMIX LOCALITY SHARE L3CACHE The two processes share at least an L3 cache 13 PMIX_LOCALITY_SHARE_PACKAGE The two processes share at least a package PMIX_LOCALITY_SHARE NUMA The two processes share at least one Non-Uniform 14 15 Memory Access (NUMA) region PMIX LOCALITY SHARE NODE 16 The two processes are executing on the same node 17 Implementers and vendors may choose to extend these definitions as needed to describe a particular

19 **11.4.2.4 Locality keys**

system.

18

20

21

22

23

24 25

26

27

28

29

30

31

PMIX_LOCALITY_STRING "pmix.locstr" (char*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to PMIx_Get_relative_locality for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to PMIx_Get for the locality string of a process that returns PMIX_ERR_NOT_FOUND indicates that the process is not executing on the same node.

11.4.3 PMIx_Parse_cpuset_string

Summary

Format

Parse the PU binding bitmap from its string representation.

```
PMIx v4.0

22 pmix_status_t
23 PMIx_Parse_cpuset_string(const char *cpuset_string,
24 pmix_cpuset_t *cpuset);
```

IN cpuset_string 1 2 String returned by the PMIx_server_generate_cpuset_string API (handle) 3 **INOUT** cpuset Address of an object where the bitmap is to be stored (memory reference) 4 Returns PMIX_SUCCESS, indicating that the cpuset was successfully loaded, or an appropriate 5 PMIx error constant. 6 Description 7 Parse the string representation of the binding bitmap (as returned by PMIx_Get using the 8 9 PMIX CPUSET key) and set the appropriate PU binding location information in the provided 10 memory location. 11.4.4 PMIx Get cpuset 11 Summary 12 13 Get the PU binding bitmap of the current process. Format 14 PMIx v4.0 15 pmix status t PMIx_Get_cpuset(pmix_cpuset_t *cpuset, pmix_bind_envelope_t ref); 16 17 **INOUT** cpuset Address of an object where the bitmap is to be stored (memory reference) 18 IN 19 20 The binding envelope to be considered when formulating the bitmap (pmix_bind_envelope_t) 21 22 Returns **PMIX** SUCCESS, indicating that the *cpuset* was successfully loaded, or an appropriate PMIx error constant. 23 24 Description Obtain and set the appropriate PU binding location information in the provided memory location 25 based on the specified binding envelope. 26 11.4.4.1 Binding envelope 27 The pmix bind envelope t data type defines the envelope of threads within a possibly 28 PMIx v4.029 multi-threaded process that are to be considered when getting the cpuset associated with the 30 process. Valid values include: 31 PMIX CPUBIND PROCESS Use the location of all threads in the possibly multi-threaded

Use only the location of the thread calling the API.

process.

PMIX CPUBIND THREAD

32

11.4.5 PMIx_Compute_distances

2 Summary

3

11

12

13

14

15

16

17

18

19

20

21

22

23

24 25

26 27

28

29

30

31

32 33 Compute distances from specified process location to local devices.

Format

IN topo

Pointer to the topology description of the node where the process is located (**NULL** indicates the local node) (**pmix_topology_t**)

IN cpuset

Pointer to the location of the process (pmix_cpuset_t)

IN info

Array of **pmix_info_t** describing the devices whose distance is to be computed (handle)

IN ninfo

Number of elements in *info* (integer)

INOUT distances

Pointer to an address where the array of **pmix_device_distance_t** structures containing the distances from the caller to the specified devices is to be returned (handle)

INOUT ndist

Pointer to an address where the number of elements in the *distances* array is to be returned (handle)

Returns one of the following:

- **PMIX_SUCCESS** indicating that the distances were returned.
- a non-zero PMIx error constant indicating the reason the request failed.

Description

Both the minimum and maximum distance fields in the elements of the array shall be filled with the respective distances between the current process location and the types of devices or specific device identified in the *info* directives. In the absence of directives, distances to all supported device types shall be returned.

$\Delta \cap$	MICE	tΩ	users

A process whose threads are not all bound to the same location may return inconsistent results from calls to this API by different threads if the **PMIX_CPUBIND_THREAD** binding envelope was used when generating the *cpuset*.

11.4.6 PMIx_Compute_distances_nb

Summary

Compute distances from specified process location to local devices.

Format

PMIx v4.0

1

2

3

5

8

9

10

11 12

13

14

15

16

17

18 19

20

21

22

23 24

25

26

27 28

29

30 31

32

C

IN topo

Pointer to the topology description of the node where the process is located (**NULL** indicates the local node) (**pmix_topology_t**)

IN cpuset

Pointer to the location of the process (pmix_cpuset_t)

IN info

Array of pmix info t describing the devices whose distance is to be computed (handle)

IN ninfo

Number of elements in *info* (integer)

IN cbfunc

Callback function **pmix** info **cbfunc** t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed

Description 1 2 Non-blocking form of the PMIx Compute distances API. 11.4.7 **Device Distance Callback Function** Summary 4 The pmix_device_dist_cbfunc_t is used to return an array of device distances. 5 PMIx v4.0 6 typedef void (*pmix_device_dist_cbfunc_t) 7 (pmix status t status, 8 pmix device distance t *dist, 9 size t ndist, 10 void *cbdata, pmix_release_cbfunc_t release_fn, 11 void *release_cbdata); 12 IN 13 status Status associated with the operation (pmix status t) 14 15 IN Array of **pmix_device_distance_t** returned by the operation (pointer) 16 17 IN ndist Number of elements in the *dist* array (**size** t) 18 IN cbdata 19 Callback data passed to original API call (memory reference) 20 21 IN release_fn 22 Function to be called when done with the *dist* data (function pointer) IN 23 release cbdata Callback data to be passed to *release_fn* (memory reference) 24 25 Description The status indicates if requested data was found or not. The array of 26 27 **pmix_device_distance_t** will contain the distance information. 11.4.8 Device type 29 The pmix_device_type_t is a uint64_t bitmask for identifying the type(s) whose distances are being requested, or the type of a specific device being referenced (e.g., in a 30 31 pmix device distance t object). PMIx v1.0

typedef uint16 t pmix device type t;

The following constants can be used to set a variable of the type **pmix_device_type_t**. 1 The device is of an unknown type - will not be included in 2 PMIX DEVTYPE UNKNOWN 3 returned device distances. Operating system block device, or non-volatile memory device 4 PMIX DEVTYPE BLOCK (e.g., "sda" or "dax2.0" on Linux). 5 Operating system Graphics Processing Unit (GPU) device (e.g., 6 PMIX_DEVTYPE_GPU "card0" for a Linux Direct Rendering Manager (DRM) device). 7 8 PMIX DEVTYPE NETWORK Operating system network device (e.g., the "eth0" interface on 9 Linux). Operating system OpenFabrics device (e.g., an "mlx4_0" PMIX DEVTYPE OPENFABRICS 10 InfiniBand Host Channel Adapter (HCA), or "hfi1_0" Omni-Path interface on Linux). 11 Operating system Direct Memory Access (DMA) engine device (e.g., 12 PMIX DEVTYPE DMA 13 the "dma0chan0" DMA channel on Linux). Operating system co-processor device (e.g., "mic0" for a Xeon Phi PMIX DEVTYPE COPROC 14 on Linux, "opencl0d0" for a OpenCL device, or "cuda0" for a Compute Unified Device 15 16 Architecture (CUDA) device).

11.4.9 Device Distance Structure

The **pmix_device_distance_t** structure contains the minimum and maximum relative distance from the caller to a given device.

```
PMIx v4.0
```

```
typedef struct pmix_device_distance {
    char *uuid;
    char *osname;
    pmix_device_type_t type;
    uint16_t mindist;
    uint16_t maxdist;
} pmix device_distance_t;
```

27 28

29

18 19

20

21

22

23

24 25

26

The *unid* is a string identifier guaranteed to be unique within the cluster and is typically assembled from discovered device attributes (e.g., the Internet Protocol (IP) address of the device). The *osname* is the local operating system name of the device and is only unique to that node.

The two distance fields provide the minimum and maximum relative distance to the device from the specified location of the process, expressed as a 16-bit integer value where a smaller number indicates that this device is closer to the process than a device with a larger distance value. Note that relative distance values are not necessarily correlated to a physical property - e.g., a device at twice the distance from another device does not necessarily have twice the latency for communication with it.

Relative distances only apply to similar devices and cannot be used to compare devices of different 1 2 types. Both minimum and maximum distances are provided to support cases where the process may be bound to more than one location, and the locations are at different distances from the device. 3 A relative distance value of **UINT16 MAX** indicates that the distance from the process to the 1 5 device could not be provided. This may be due to lack of available information (e.g., the PMIx 6 library not having access to device locations) or other factors. **Device distance support macros** 11.4.10 The following macros are provided to support the **pmix_device_distance_t** structure. 8 Initialize the device distance structure 9 10 Initialize the pmix device distance t fields. PMIx v4.0 11 PMIX DEVICE DIST CONSTRUCT (m) IN 12 Pointer to the structure to be initialized (pointer to pmix_device_distance_t) 13 Destruct the device distance structure 14 Destruct the pmix_device_distance_t fields. 15 PMIx v4.0 16 PMIX DEVICE DIST DESTRUCT (m) IN 17 18 Pointer to the structure to be destructed (pointer to pmix_device_distance_t) Create an device distance array 19 Allocate and initialize a pmix_device_distance_t array. 20 PMIx v4.0 21 PMIX_DEVICE_DIST_CREATE(m, n) INOUT m 22 Address where the pointer to the array of **pmix_device_distance_t** structures shall be 23 24 stored (handle)

Number of structures to be allocated (size t)

25

26

IN

Release an device distance array 1 Release an array of **pmix device distance** t structures. 2 PMIx v4.0 3 PMIX DEVICE DIST FREE (m, n) 4 IN Pointer to the array of pmix_device_distance_t structures (handle) 5 IN 6 7 Number of structures in the array (size t) **Device distance attributes** 11.4.11 9 The following attributes can be used to retrieve device distances from the PMIx data store. Note that distances stored by the host environment are based on the process location at the time of start 10 of execution and may not reflect changes to location imposed by the process itself. 11 12 PMIX_DEVICE_DISTANCES "pmix.dev.dist" (pmix_data_array_t) Return an array of pmix_device_distance_t containing the minimum and maximum

PMIX DEVICE TYPE "pmix.dev.type" (pmix device type t)

as a directive/qualifier.

name of a particular device.

PMIX_DEVICE_ID "pmix.dev.id" (string)

distances of the given process location to all devices of the specified type on the local node.

Bitmask specifying the type(s) of device(s) whose information is being requested. Only used

System-wide Universally Unique IDentifier (UUID) or node-local Operating System (OS)

13 14

15 16

17 18

CHAPTER 12

Job Management and Reporting

1 2		The job management APIs provide an application with the ability to orchestrate its operation in partnership with the SMS. Members of this category include the
3 4		PMIx_Allocation_request, PMIx_Job_control, and PMIx_Process_monitor APIs.
5	12.1	Allocation Requests
6 7		This section defines functionality to request new allocations from the RM, and request modifications to existing allocations. These are primarily used in the following scenarios:
8		• Evolving applications that dynamically request and return resources as they execute.
9		• <i>Malleable</i> environments where the scheduler redirects resources away from executing applications for higher priority jobs or load balancing.
1		• Resilient applications that need to request replacement resources in the face of failures.
2		• <i>Rigid</i> jobs where the user has requested a static allocation of resources for a fixed period of time but realizes that they underestimated their required time while executing.
4		PMIx attempts to address this range of use-cases with a flexible API.
5	12.1.1	PMIx_Allocation_request
6		Summary
7		Request an allocation operation from the host resource manager.
8	PMIx v3.0	Format C
9		pmix status_t
20		PMIx_Allocation_request(pmix_alloc_directive_t directive,
1		nmiv info t info[] size t ninfo

pmix_info_t *results[], size_t *nresults);

	IN directive
2	Allocation directive (pmix_alloc_directive_t)
3	IN info
4	Array of pmix_info_t structures (array of handles)
5	IN ninfo
6	Number of elements in the <i>info</i> array (integer)
7	INOUT results
8	Address where a pointer to an array of pmix_info_t containing the results of the request
9	can be returned (memory reference)
10	INOUT nresults
11	Address where the number of elements in <i>results</i> can be returned (handle)
12	Returns one of the following:
13	 PMIX_SUCCESS, indicating that the request was processed and returned success
14	• a PMIx error constant indicating either an error in the input or that the request was refused
	Required Attributes
15	PMIx libraries are not required to directly support any attributes for this function. However, any
16	provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is
17	required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making
18	the request.
19	Host environments that implement support for this operation are required to support the following
20	attributes:
21	<pre>PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)</pre>
22	User-provided string identifier for this allocation request which can later be used to query
23	status of the request.
24	PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t)
25	The number of nodes being requested in an allocation request.
26	PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t)
27	Number of PUs being requested in an allocation request.
28	<pre>PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)</pre>
29	Total session time (in seconds) being requested in an allocation request.

The fo	ollowing attributes are optional for host environments that support this operation:
PMIX	Regular expression of the specific nodes being requested in an allocation request.
PMIX	**Regular expression of the number of PUs for each node being requested in an allocation request.
PMIX	Regular expression of the specific PUs being requested in an allocation request.
PMIX	Number of Megabytes[base2] of memory (per process) being requested in an allocation request.
PMIX	ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
РМІХ	The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of this key and the allocated resource description. The type of the included value depends upon the fabric support. For example, a Transmission Control Protocol (TCP) allocation might consist of a comma-delimited string of socket ranges such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include: PMIX_ALLOC_FABRIC_TYPE - the type of resources provided; PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the requested fabric allocation. NOTE: the array contents may differ from those requested, especially if PMIX_INFO_REQD was not set in the request.
PMIX	Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
PMIX	ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.
PMIX	Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
PMIX	ALLOC FABRIC PLANE "pmix.alloc.netplane" (char*)

Optional Attributes

1	ID string for the <i>fabric plane</i> to be used for the requested allocation.
2 3	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per process in the job.</pre>
4 5	PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per <i>node</i> for the job.
6 7	PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t) Request that the allocation include a fabric security key for the spawned job.

Description

 Request an allocation operation from the host resource manager. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute. This should be accomplished in a non-blocking manner so that the application can continue to progress while waiting for resources to become available. Note that the new allocation will be disjoint from (i.e., not affiliated with) the allocation of the requestor thus the termination of one allocation will not impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities. This includes extending the time limit on current resources, and/or requesting additional resources be allocated to the requesting job. Any additional allocated resources will be considered as part of the current allocation, and thus will be released at the same time.
- Return no-longer-required resources to the scheduler. This includes the "loan" of resources back to the scheduler with a promise to return them upon subsequent request.

If successful, the returned results for a request for additional resources must include the host resource manager's identifier (PMIX_ALLOC_ID) that the requester can use to specify the resources in, for example, a call to PMIx_Spawn.

12.1.2 PMIx_Allocation_request_nb

Summary

Request an allocation operation from the host resource manager.

1	Format
PMIx v2.	
2	pmix_status_t
3	PMIx_Allocation_request_nb(pmix_alloc_directive_t directive,
4	<pre>pmix_info_t info[], size_t ninfo,</pre>
5	<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
6	
7	IN directive
8	Allocation directive (pmix_alloc_directive_t)
9	IN info
10	Array of pmix_info_t structures (array of handles)
11	IN ninfo
12	Number of elements in the <i>info</i> array (integer)
13	IN cbfunc
14	Callback function pmix_info_cbfunc_t (function reference) IN cbdata
15 16	IN cbdata Data to be passed to the callback function (memory reference)
10	
17	Returns one of the following:
18	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
19	will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
20	function prior to returning from the API.
21	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
22	returned success - the cbfunc will not be called
23 24	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called
24	
	Required Attributes
25	PMIx libraries are not required to directly support any attributes for this function. However, any
26	provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is
27	required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making
28	the request.
29	Host environments that implement support for this operation are required to support the following
30	attributes:
31	<pre>PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)</pre>
32	User-provided string identifier for this allocation request which can later be used to query
33	status of the request.
34	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t)</pre>
35	The number of nodes being requested in an allocation request.

1 2	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
3 4	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.
	→ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
8 9 10	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
11 12	PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.
13 14 15	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
16 17 18 19	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
20 21 22 23 24 25 26 27 28 29 30 31 32 33	PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*) The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_data_array_t of pmix_info_t whose first element is composed of this key and the allocated resource description. The type of the included value depends upon the fabric support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include: PMIX_ALLOC_FABRIC_TYPE - the type of resources provided; PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH - the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the requested fabric allocation. NOTE: the array contents may differ from those requested, especially if PMIX_INFO_REQD was not set in the request.
34 35 36	<pre>PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.</pre>

```
PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)
 1
 2
                    Fabric quality of service level for the job being requested in an allocation request.
 3
               PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)
                    Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
 4
               PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*)
5
 6
                    ID string for the fabric plane to be used for the requested allocation.
 7
               PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)
8
                    Number of endpoints to allocate per process in the job.
9
               PMIX ALLOC FABRIC ENDPTS NODE "pmix.alloc.endpts.nd" (size t)
10
                    Number of endpoints to allocate per node for the job.
               PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
11
                    Request that the allocation include a fabric security key for the spawned job.
12
13
               Description
14
               Non-blocking form of the PMIx_Allocation_request API.
    12.1.3 Job Allocation attributes
15
               Attributes used to describe the job allocation - these are values passed to and/or returned by the
16
               PMIx Allocation request_nb and PMIx Allocation_request APIs and are not
17
               accessed using the PMIx_Get API.
18
               PMIX_ALLOC_REQ_ID "pmix.alloc.reqid" (char*)
19
20
                    User-provided string identifier for this allocation request which can later be used to query
                    status of the request.
21
               PMIX_ALLOC_ID "pmix.alloc.id" (char*)
22
                    A string identifier (provided by the host environment) for the resulting allocation which can
23
24
                    later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.
               PMIX ALLOC QUEUE "pmix.alloc.queue" (char*)
25
                    Name of the WLM queue to which the allocation request is to be directed, or the queue being
26
27
                    referenced in a query.
               PMIX ALLOC NUM NODES "pmix.alloc.nnodes" (uint64 t)
28
                    The number of nodes being requested in an allocation request.
29
               PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*)
30
31
                    Regular expression of the specific nodes being requested in an allocation request.
               PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t)
32
                    Number of PUs being requested in an allocation request.
33
               PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*)
34
35
                    Regular expression of the number of PUs for each node being requested in an allocation
36
                    request.
```

1	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*)</pre>
2	Regular expression of the specific PUs being requested in an allocation request.
3	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float)</pre>
4	Number of Megabytes[base2] of memory (per process) being requested in an allocation
5	request.
6	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array)
7	Array of pmix_info_t describing requested fabric resources. This must include at least
8	PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and
9	PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
10	PMIX_ALLOC_FABRIC_ID "pmix.alloc.netid" (char*)
11	The key to be used when accessing this requested fabric allocation. The fabric allocation
12	will be returned/stored as a pmix_data_array_t of pmix_info_t whose first
13	element is composed of this key and the allocated resource description. The type of the
14	included value depends upon the fabric support. For example, a TCP allocation might
15	consist of a comma-delimited string of socket ranges such as "32000-32100,
16	33005, 38123-38146". Additional array entries will consist of any provided resource
17	request directives, along with their assigned values. Examples include:
18	<pre>PMIX_ALLOC_FABRIC_TYPE - the type of resources provided;</pre>
19	PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned
20	from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH -
21	the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the
22	requested fabric allocation. NOTE: the array contents may differ from those requested,
23	especially if PMIX_INFO_REQD was not set in the request.
24	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)
25	Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation
26	request.
27	PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*)
28	Fabric quality of service level for the job being requested in an allocation request.
29	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t)
30	Total session time (in seconds) being requested in an allocation request.
31	PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)
32	Type of desired transport (e.g., "tcp", "udp") being requested in an allocation request.
33	PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*)
34	ID string for the <i>fabric plane</i> to be used for the requested allocation.
35	<pre>PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t)</pre>
36	Number of endpoints to allocate per <i>process</i> in the job.
37	PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)
38	Number of endpoints to allocate per <i>node</i> for the job.
39	PMIX_ALLOC_FABRIC_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
40	Request that the allocation include a fabric security key for the spawned job.

1 12.1.4 Job Allocation Directives

- The pmix_alloc_directive_t structure is a uint8_t type that defines the behavior of allocation requests. The following constants can be used to set a variable of the type pmix_alloc_directive_t. All definitions were introduced in version 2 of the standard unless otherwise marked.
 - **PMIX_ALLOC_NEW** A new allocation is being requested. The resulting allocation will be disjoint (i.e., not connected in a job sense) from the requesting allocation.
 - **PMIX_ALLOC_EXTEND** Extend the existing allocation, either in time or as additional resources.
 - **PMIX_ALLOC_RELEASE** Release part of the existing allocation. Attributes in the accompanying **pmix_info_t** array may be used to specify permanent release of the identified resources, or "lending" of those resources for some period of time.
 - **PMIX_ALLOC_REAQUIRE** Reacquire resources that were previously "lent" back to the scheduler.
 - **PMIX_ALLOC_EXTERNAL** A value boundary above which implementers are free to define their own directive values.

7 12.2 Job Control

This section defines APIs that enable the application and host environment to coordinate the response to failures and other events. This can include requesting termination of the entire job or a subset of processes within a job, but can also be used in combination with other PMIx capabilities (e.g., allocation support and event notification) for more nuanced responses. For example, an application notified of an incipient over-temperature condition on a node could use the PMIx_Allocation_request_nb interface to request replacement nodes while simultaneously using the PMIx_Job_control_nb interface to direct that a checkpoint event be delivered to all processes in the application. If replacement resources are not available, the application might use the PMIx_Job_control_nb interface to request that the job continue at a lower power setting, perhaps sufficient to avoid the over-temperature failure.

The job control APIs can also be used by an application to register itself as available for preemption when operating in an environment such as a cloud or where incentives, financial or otherwise, are provided to jobs willing to be preempted. Registration can include attributes indicating how many resources are being offered for preemption (e.g., all or only some portion), whether the application will require time to prepare for preemption, etc. Jobs that request a warning will receive an event notifying them of an impending preemption (possibly including information as to the resources that will be taken away, how much time the application will be given prior to being preempted, whether the preemption will be a suspension or full termination, etc.) so they have an opportunity to save their work. Once the application is ready, it calls the provided event completion callback function to indicate that the SMS is free to suspend or terminate it, and can include directives regarding any desired restart.

12.2.1 PMIx Job control Summary 2 Request a job control action. 3 Format PMIx v3.0 5 pmix status t 6 PMIx Job control(const pmix proc t targets[], size t ntargets, 7 const pmix info t directives[], size t ndirs, pmix_info_t *results[], size_t *nresults); 8 9 IN targets 10 Array of proc structures (array of handles) IN ntargets 11 Number of elements in the *targets* array (integer) 12 IN directives 13 14 Array of info structures (array of handles) ndirs 15 IN Number of elements in the *directives* array (integer) 16 17 **INOUT** results 18 Address where a pointer to an array of pmix info t containing the results of the request 19 can be returned (memory reference) INOUT nresults 20 Address where the number of elements in *results* can be returned (handle) 21 22 Returns one of the following: • PMIX_SUCCESS, indicating that the request was processed by the host environment and 23 returned success. Details of the result will be returned in the results array 24 25 • a PMIx error constant indicating either an error in the input or that the request was refused Required Attributes PMIx libraries are not required to directly support any attributes for this function. However, any 26 provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is 27 required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making 28 the request. 29 Host environments that implement support for this operation are required to support the following 30 attributes: 31

PMIX JOB CTRL ID "pmix.jctrl.id" (char*)

1 2 3	Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to terminate it. The host, therefore, shall track it with the request for future reference.
4 5	<pre>PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool) Pause the specified processes.</pre>
6 7	PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes.
8 9	PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup.
10 11	PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes.
12 13	<pre>PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool) Politely terminate the specified processes.</pre>
14 15	<pre>PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*) Comma-delimited list of files to be removed upon process termination.</pre>
16 17	<pre>PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.</pre>
18 19	PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool) Recursively cleanup all subdirectories under the specified one(s).
20 21	PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) Only remove empty subdirectories.
22 23	<pre>PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*) Comma-delimited list of filenames that are not to be removed.</pre>
24 25 26	<pre>PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool) When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the cleanup request).</pre>
	◆
27	The following attributes are optional for host environments that support this operation:
28 29 30 31	<pre>PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*) Cancel the specified request - the provided request ID must match the PMIX_JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of NULL implies cancel all requests from this requestor.</pre>
32 33	<pre>PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) Restart the specified processes using the given checkpoint ID.</pre>

```
PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*)
 1
 2
                     Checkpoint the specified processes and assign the given ID to it.
               PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)
 3
 4
                     Use event notification to trigger a process checkpoint.
               PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int)
 5
 6
                     Use the given signal to trigger a process checkpoint.
               PMIX JOB CTRL CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
 7
                     Time in seconds to wait for a checkpoint to complete.
8
9
               PMIX JOB CTRL CHECKPOINT METHOD
10
               "pmix.jctrl.ckmethod" (pmix_data_array_t)
                     Array of pmix_info_t declaring each method and value supported by this application.
11
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
12
13
                     Regular expression identifying nodes that are to be provisioned.
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
14
                     Name of the image that is to be provisioned.
15
16
               PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
17
                     Indicate that the job can be pre-empted.
               Description
18
               Request a job control action. The targets array identifies the processes to which the requested job
19
               control action is to be applied. All clones of an identified process are to have the requested action
20
21
               applied to them. A NULL value can be used to indicate all processes in the caller's namespace. The
22
               use of PMIX RANK WILDCARD can also be used to indicate that all processes in the given
23
               namespace are to be included.
24
               The directives are provided as pmix info t structures in the directives array. The returned
25
               status indicates whether or not the request was granted, and information as to the reason for any
```

12.2.2 PMIx Job control nb

Summary

Request a job control action.

26

28

29

denial of the request shall be returned in the *results* array.

1	Format
<i>PMIx v2.0</i>	▼
2	pmix_status_t
3	<pre>PMIx_Job_control_nb(const pmix_proc_t targets[], size_t ntargets,</pre>
4	<pre>const pmix_info_t directives[], size_t ndirs,</pre>
5	<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
	C
6	IN targets
7	Array of proc structures (array of handles)
8	IN ntargets
9	Number of elements in the <i>targets</i> array (integer)
0	IN directives
1	Array of info structures (array of handles)
2	IN ndirs
3	Number of elements in the <i>directives</i> array (integer)
4	IN cbfunc
5	Callback function <pre>pmix_info_cbfunc_t</pre> (function reference)
6	IN cbdata
7	Data to be passed to the callback function (memory reference)
8	Returns one of the following:
9	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
0	will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
1	function prior to returning from the API.
2	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
3	returned success - the cbfunc will not be called
4	• a PMIx error constant indicating either an error in the input or that the request was immediately
5	processed and failed - the <i>cbfunc</i> will <i>not</i> be called
	Required Attributes
6	PMIx libraries are not required to directly support any attributes for this function. However, any
7	provided attributes must be passed to the host SMS daemon for processing, and the PMIx library is
8	required to add the PMIX_USERID and the PMIX_GRPID attributes of the client process making
9	the request.
0	Host environments that implement support for this operation are required to support the following
1	attributes:
2	PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*)
3	Provide a string identifier for this request. The user can provide an identifier for the
4	requested operation, thus allowing them to later request status of the operation or to
5	terminate it. The host therefore shall track it with the request for future reference

1 2	<pre>PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool) Pause the specified processes.</pre>
3 4	PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes.
5 6	PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup.
7 8	PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) Send given signal to specified processes.
9 10	<pre>PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool) Politely terminate the specified processes.</pre>
1 2	<pre>PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*) Comma-delimited list of files to be removed upon process termination.</pre>
13 14	<pre>PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*) Comma-delimited list of directories to be removed upon process termination.</pre>
15 16	PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool) Recursively cleanup all subdirectories under the specified one(s).
17 18	<pre>PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool) Only remove empty subdirectories.</pre>
19 20	PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*) Comma-delimited list of filenames that are not to be removed.
21 22 23	<pre>PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool) When recursively cleaning subdirectories, do not remove the top-level directory (the one given in the cleanup request).</pre>
	→ Optional Attributes
24	The following attributes are optional for host environments that support this operation:
25 26 27 28	PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*) Cancel the specified request - the provided request ID must match the PMIX_JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of NULL implies cancel all requests from this requestor.
29 30	PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) Restart the specified processes using the given checkpoint ID.
31 32	<pre>PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*) Checkpoint the specified processes and assign the given ID to it.</pre>
33	PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)

```
Use event notification to trigger a process checkpoint.
 1
               PMIX JOB CTRL CHECKPOINT SIGNAL "pmix.jctrl.ckptsig" (int)
 2
                     Use the given signal to trigger a process checkpoint.
 3
               PMIX JOB CTRL CHECKPOINT TIMEOUT "pmix.jctrl.ckptsig" (int)
 4
 5
                     Time in seconds to wait for a checkpoint to complete.
 6
               PMIX JOB CTRL CHECKPOINT METHOD
 7
               "pmix.jctrl.ckmethod" (pmix data array t)
                     Array of pmix info t declaring each method and value supported by this application.
8
9
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
10
                     Regular expression identifying nodes that are to be provisioned.
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
11
                     Name of the image that is to be provisioned.
12
13
               PMIX JOB CTRL PREEMPTIBLE "pmix.jctrl.preempt" (bool)
14
                     Indicate that the job can be pre-empted.
               Description
15
               Non-blocking form of the PMIx_Job_control API. The targets array identifies the processes to
16
17
               which the requested job control action is to be applied. All clones of an identified process are to
               have the requested action applied to them. A NULL value can be used to indicate all processes in
18
               the caller's namespace. The use of PMIX RANK WILDCARD can also be used to indicate that all
19
               processes in the given namespace are to be included.
20
               The directives are provided as pmix info t structures in the directives array. The callback
21
22
               function provides a status to indicate whether or not the request was granted, and to provide some
               information as to the reason for any denial in the pmix_info_cbfunc_t array of
23
               pmix_info_t structures.
24
    12.2.3 Job control constants
25
```

The following constants are specifically defined for return by the job control APIs:

PMIX ERR_CONFLICTING_CLEANUP_DIRECTIVES

job/process cleanup.

26

27

28

Conflicting directives given for

12.2.4 Job control events

5

6

7

8

9

10

11

13

14 15

16 17

18

19 20

21

22

23 24

25

26

27

28 29

30

31 32

33

34

35

36

37

38 39

40

- The following job control events may be available for registration, depending upon implementation and host environment support:
- 4 **PMIX_JCTRL_CHECKPOINT** Monitored by PMIx client to trigger a checkpoint operation.
 - **PMIX_JCTRL_CHECKPOINT_COMPLETE** Sent by a PMIx client and monitored by a PMIx server to notify that requested checkpoint operation has completed.
 - **PMIX_JCTRL_PREEMPT_ALERT** Monitored by a PMIx client to detect that an RM intends to preempt the job.
 - **PMIX ERR PROC RESTART** Error in process restart.
 - **PMIX_ERR_PROC_CHECKPOINT** Error in process checkpoint.
 - **PMIX_ERR_PROC_MIGRATE** Error in process migration.

12.2.5 Job control attributes

Attributes used to request control operations on an executing application - these are values passed to the job control APIs and are not accessed using the **PMIx_Get** API.

```
PMIX_JOB_CTRL_ID "pmix.jctrl.id" (char*)
```

Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to terminate it. The host, therefore, shall track it with the request for future reference.

PMIX_JOB_CTRL_PAUSE "pmix.jctrl.pause" (bool)

Pause the specified processes.

PMIX_JOB_CTRL_RESUME "pmix.jctrl.resume" (bool)

Resume ("un-pause") the specified processes.

PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*)

Cancel the specified request - the provided request ID must match the

PMIX_JOB_CTRL_ID provided to a previous call to **PMIx_Job_control**. An ID of **NULL** implies cancel all requests from this requestor.

PMIX_JOB_CTRL_KILL "pmix.jctrl.kill" (bool)

Forcibly terminate the specified processes and cleanup.

PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*)

Restart the specified processes using the given checkpoint ID.

PMIX_JOB_CTRL_CHECKPOINT "pmix.jctrl.ckpt" (char*)

Checkpoint the specified processes and assign the given ID to it.

PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)

Use event notification to trigger a process checkpoint.

PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int)

Use the given signal to trigger a process checkpoint.

PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)

Time in seconds to wait for a checkpoint to complete.

PMIX JOB CTRL CHECKPOINT METHOD

"pmix.jctrl.ckmethod" (pmix_data_array_t)

1		Array of pmix_info_t declaring each method and value supported by this application.
2		PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int)
3		Send given signal to specified processes.
4		<pre>PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)</pre>
5		Regular expression identifying nodes that are to be provisioned.
6		PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
7		Name of the image that is to be provisioned.
8		PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
9		Indicate that the job can be pre-empted.
10		PMIX_JOB_CTRL_TERMINATE "pmix.jctrl.term" (bool)
11		Politely terminate the specified processes.
12		PMIX_REGISTER_CLEANUP "pmix.reg.cleanup" (char*)
13		Comma-delimited list of files to be removed upon process termination.
14		PMIX_REGISTER_CLEANUP_DIR "pmix.reg.cleanupdir" (char*)
15		Comma-delimited list of directories to be removed upon process termination.
16		PMIX_CLEANUP_RECURSIVE "pmix.clnup.recurse" (bool)
17		Recursively cleanup all subdirectories under the specified one(s).
18		PMIX_CLEANUP_EMPTY "pmix.clnup.empty" (bool)
19		Only remove empty subdirectories.
20		<pre>PMIX_CLEANUP_IGNORE "pmix.clnup.ignore" (char*)</pre>
21		Comma-delimited list of filenames that are not to be removed.
22		PMIX_CLEANUP_LEAVE_TOPDIR "pmix.clnup.lvtop" (bool)
23		When recursively cleaning subdirectories, do not remove the top-level directory (the one
24		given in the cleanup request).
25	12.3	Process and Job Monitoring
20		. 100000 and ook monitoring

In addition to external faults, a common problem encountered in HPC applications is a failure to make progress due to some internal conflict in the computation. These situations can result in a significant waste of resources as the SMS is unaware of the problem, and thus cannot terminate the job. Various watchdog methods have been developed for detecting this situation, including requiring a periodic "heartbeat" from the application and monitoring a specified file for changes in size and/or modification time.

The following APIs allow applications to request monitoring, directing what is to be monitored, the frequency of the associated check, whether or not the application is to be notified (via the event notification subsystem) of stall detection, and other characteristics of the operation.

12.3.1 PMIx Process monitor

Summary

Request that application processes be monitored.

l DM	r an European C
	Ix v3.0
2	pmix_status_t
3	PMIx_Process_monitor(const pmix_info_t *monitor,
4	<pre>pmix_status_t error,</pre>
5	<pre>const pmix_info_t directives[], size_t ndirs,</pre>
6	<pre>pmix_info_t *results[], size_t *nresults);</pre>
	C -
7	IN monitor
8	info (handle)
9	IN error
10	status (integer)
11	IN directives
12	Array of info structures (array of handles)
13	IN ndirs
14	Number of elements in the <i>directives</i> array (integer)
15	INOUT results
16	Address where a pointer to an array of pmix_info_t containing the results of the request
17	can be returned (memory reference)
18	INOUT nresults
19	Address where the number of elements in results can be returned (handle)
20	Returns one of the following:
21 22	 PMIX_SUCCESS, indicating that the request was processed and returned success. Details of the result will be returned in the results array
23	• a PMIx error constant indicating either an error in the input or that the request was refused
	→ Optional Attributes
24	The following attributes may be implemented by a PMIx library or by the host environment. If
25	supported by the PMIx server library, then the library must not pass the supported attributes to the
26	host environment. All attributes not directly supported by the server library must be passed to the
27	host environment if it supports this operation, and the library is required to add the
28	PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
29	<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*)</pre>
30	Provide a string identifier for this request.
31	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*)</pre>
32	Identifier to be canceled (NULL means cancel all monitoring for this process).
33	<pre>PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool)</pre>

1 2 3	The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g. terminating the job).
4 5	PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
6 7	<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>
8 9	PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.
0 1	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
2 3	<pre>PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool) Monitor size of given file is growing to determine if the application is running.</pre>
4 5	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*) Monitor time since last access of given file to determine if the application is running.</pre>
6 7	<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*) Monitor time since last modified of given file to determine if the application is running.</pre>
8 9	<pre>PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.</pre>
20 21	<pre>PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t) Number of file checks that can be missed before generating the event.</pre>
22 23	PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void) Send heartbeat to local PMIx server.
24	Description
25	Request that application processes be monitored via several possible methods. For example, that
26	the server monitor this process for periodic heartbeats as an indication that the process has not
27	become "wedged". When a monitor detects the specified alarm condition, it will generate an event
28 29	notification using the provided error code and passing along any available relevant information. It is up to the caller to register a corresponding event handler.
	is up to the canor to register a corresponding event handler.

The *monitor* argument is an attribute indicating the type of monitor being requested. For example, **PMIX_MONITOR_FILE** to indicate that the requestor is asking that a file be monitored.

30

31

32

33

34

The error argument is the status code to be used when generating an event notification alerting that the monitor has been triggered. The range of the notification defaults to

PMIX_RANGE_NAMESPACE. This can be changed by providing a PMIX_RANGE directive.

The directives argument characterizes the monitoring request (e.g., monitor file size) and frequency 1 2 of checking to be done 3 The returned status indicates whether or not the request was granted, and information as to the 4 reason for any denial of the request shall be returned in the *results* array. 12.3.2 PMIx Process monitor nb Summary 6 Request that application processes be monitored. 7 Format PMIx v2.0 9 pmix status t PMIx Process monitor nb (const pmix info t *monitor, 10 pmix_status_t error, 11 12 const pmix info t directives[], 13 size t ndirs, pmix info cbfunc t cbfunc, void *cbdata); 14 IN monitor 15 16 info (handle) 17 IN error status (integer) 18 19 IN directives Array of info structures (array of handles) 20 21 IN ndirs Number of elements in the *directives* array (integer) 22 IN cbfunc 23 Callback function pmix_info_cbfunc_t (function reference) 24 25 IN cbdata 26 Data to be passed to the callback function (memory reference) Returns one of the following: 27 • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result 28 will be returned in the provided cbfunc. Note that the library must not invoke the callback 29 function prior to returning from the API. 30 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 31 returned success - the cbfunc will not be called. 32 33 • a PMIx error constant indicating either an error in the input or that the request was immediately 34 processed and failed - the *cbfunc* will *not* be called.

	▼ Optional Attributes
	The following attributes may be implemented by a PMIx library or by the host environment. If supported by the PMIx server library, then the library must not pass the supported attributes to the host environment. All attributes not directly supported by the server library must be passed to the host environment if it supports this operation, and the library is <i>required</i> to add the PMIX_USERID and the PMIX_GRPID attributes of the requesting process:
	PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.
	<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>
	PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application is requesting that the host environment not take immediate action in response to the event (e.g terminating the job).
	PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.
	<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>
	PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.
	<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>
	PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool) Monitor size of given file is growing to determine if the application is running.
	<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)</pre>
	<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*)</pre>
<	<pre>PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t) Time in seconds between checking the file.</pre>

PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t)

PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void)

Send heartbeat to local PMIx server.

Number of file checks that can be missed before generating the event.

Description 1 2 Non-blocking form of the **PMIx Process monitor** API. The *cbfunc* function provides a 3 status to indicate whether or not the request was granted, and to provide some information as to the 4 reason for any denial in the pmix info cbfunc t array of pmix info t structures. 12.3.3 PMIx Heartbeat Summary 6 7 Send a heartbeat to the PMIx server library **Format** 8 PMIx v2.0 9 PMIx Heartbeat(); **Description** 10 A simplified macro wrapping PMIx_Process_monitor_nb that sends a heartbeat to the PMIx 11 12 server library. 12.3.4 Monitoring events 14 The following monitoring events may be available for registration, depending upon implementation and host environment support: 15 16 PMIX MONITOR HEARTBEAT ALERT Heartbeat failed to arrive within specified window. 17 The process that triggered this alert will be identified in the event. 18 PMIX MONITOR FILE ALERT File failed its monitoring detection criteria. The file that 19 triggered this alert will be identified in the event. 12.3.5 Monitoring attributes 21 Attributes used to control monitoring of an executing application- these are values passed to the 22 PMIx Process monitor nb API and are not accessed using the PMIx Get API. 23 PMIX MONITOR ID "pmix.monitor.id" (char*) 24 Provide a string identifier for this request. PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) 25 Identifier to be canceled (**NULL** means cancel all monitoring for this process). 26 27 PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application is 28 29 requesting that the host environment not take immediate action in response to the event (e.g., 30 terminating the job). 31 PMIX MONITOR HEARTBEAT "pmix.monitor.mbeat" (void) 32 Register to have the PMIx server monitor the requestor for heartbeats.

```
1
              PMIX_SEND_HEARTBEAT "pmix.monitor.beat" (void)
2
                    Send heartbeat to local PMIx server.
 3
              PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t)
 4
                    Time in seconds before declaring heartbeat missed.
              PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t)
 5
6
                    Number of heartbeats that can be missed before generating the event.
 7
              PMIX MONITOR FILE "pmix.monitor.fmon" (char*)
8
                    Register to monitor file for signs of life.
9
              PMIX MONITOR FILE SIZE "pmix.monitor.fsize" (bool)
10
                    Monitor size of given file is growing to determine if the application is running.
              PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*)
11
12
                    Monitor time since last access of given file to determine if the application is running.
              PMIX MONITOR FILE MODIFY "pmix.monitor.fmod" (char*)
13
                    Monitor time since last modified of given file to determine if the application is running.
14
15
              PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t)
16
                    Time in seconds between checking the file.
17
              PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t)
18
                    Number of file checks that can be missed before generating the event.
    12.4 Logging
20
              The logging interface supports posting information by applications and SMS elements to persistent
              storage. This function is not intended for output of computational results, but rather for reporting
21
              status and saving state information such as inserting computation progress reports into the
22
              application's SMS job log or error reports to the local syslog.
23
    12.4.1
               PMIx_Log
              Summary
25
26
              Log data to a data service.
27
              Format
   PMIx v3.0
28
              pmix status t
29
              PMIx_Log(const pmix_info_t data[], size_t ndata,
30
                          const pmix info t directives[], size t ndirs);
              IN
31
                   data
32
                   Array of info structures (array of handles)
33
              IN
                   ndata
                   Number of elements in the data array (size_t)
34
```

1 2 3 4	 IN directives Array of info structures (array of handles) IN ndirs Number of elements in the directives array (size_t)
5	Return codes are one of the following:
6 7 8 9 10	 PMIX_SUCCESS The logging request was successful. PMIX_ERR_BAD_PARAM The logging request contains at least one incorrect entry. PMIX_ERR_NOT_SUPPORTED The PMIx implementation or host environment does not support this function. other appropriate PMIx error code
	Required Attributes
11 12 13	If the PMIx library does not itself perform this operation, then it is required to pass any attributes provided by the client to the host environment for processing. In addition, it must include the following attributes in the passed <i>info</i> array:
14 15	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
16 17	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
18 19	Host environments or PMIx libraries that implement support for this operation are required to support the following attributes:
20 21	<pre>PMIX_LOG_STDERR "pmix.log.stderr" (char*) Log string to stderr.</pre>
22 23	<pre>PMIX_LOG_STDOUT "pmix.log.stdout" (char*) Log string to stdout.</pre>
24 25 26	<pre>PMIX_LOG_SYSLOG "pmix.log.syslog" (char*) Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available, otherwise to local syslog.</pre>
27 28	PMIX_LOG_LOCAL_SYSLOG "pmix.log.lsys" (char*) Log data to local syslog. Defaults to ERROR priority.
29 30	<pre>PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*) Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.</pre>
31 32	PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int) Syslog priority level.
33 34 35	<pre>PMIX_LOG_ONCE "pmix.log.once" (bool) Only log this once with whichever channel can first support it, taking the channels in priority order.</pre>

	▼Optional Attributes
1 2	The following attributes are optional for host environments or PMIx libraries that support this operation:
3 4	<pre>PMIX_LOG_SOURCE "pmix.log.source" (pmix_proc_t*) ID of source of the log request.</pre>
5 6	<pre>PMIX_LOG_TIMESTAMP "pmix.log.tstmp" (time_t) Timestamp for log report.</pre>
7 8	PMIX_LOG_GENERATE_TIMESTAMP "pmix.log.gtstmp" (bool) Generate timestamp for log.
9 10	PMIX_LOG_TAG_OUTPUT "pmix.log.tag" (bool) Label the output stream with the channel name (e.g., "stdout").
11 12	<pre>PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool) Print timestamp in output string.</pre>
13 14	PMIX_LOG_XML_OUTPUT "pmix.log.xml" (bool) Print the output stream in eXtensible Markup Language (XML) format.
15 16	<pre>PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t) Log via email based on pmix_info_t containing directives.</pre>
17 18	<pre>PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*) Comma-delimited list of email addresses that are to receive the message.</pre>
19 20	<pre>PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*) Return email address of sender.</pre>
21 22	PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*) Hostname (or IP address) of SMTP server.
23 24	<pre>PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int32_t) Port the email server is listening to.</pre>
25 26	<pre>PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*) Subject line for email.</pre>
27 28	<pre>PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*) Message to be included in email.</pre>
29 30	PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool) Log the provided information to the host environment's job record.
31 32	PMIX_LOG_GLOBAL_DATASTORE "pmix.log.gstore" (bool) Store the log data in a global data store (e.g., database).

Description

Log data subject to the services offered by the host environment. The data to be logged is provided in the *data* array. The (optional) *directives* can be used to direct the choice of logging channel.

Advice to users

It is strongly recommended that the **PMIx_Log** API not be used by applications for streaming data as it is not a "performant" transport and can perturb the application since it involves the local PMIx server and host SMS daemon. Note that a return of **PMIX_SUCCESS** only denotes that the data was successfully handed to the appropriate system call (for local channels) or the host environment and does not indicate receipt at the final destination.

12.4.2 PMIx_Log_nb

Summary

Log data to a data service.

Format

PMIx v2.0

1

3

4 5

6 7

8

10 11

12

13

14

15

16

17

18

19

20 21

22

23 24

25

26

27

28

29 30

31 32 pmix status t

pmix_op_cbfunc_t cbfunc, void *cbdata);

IN data

Array of info structures (array of handles)

IN ndata

Number of elements in the *data* array (size_t)

IN directives

Array of info structures (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function **pmix** op **cbfunc t** (function reference)

IN chdata

Data to be passed to the callback function (memory reference)

Return codes are one of the following:

PMIX_SUCCESS The logging request is valid and is being processed. The resulting status from the operation will be provided in the callback function. Note that the library must not invoke the callback function prior to returning from the API.

1 2	PMIX_OPERATION_SUCCEEDED , indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
3	PMIX_ERR_BAD_PARAM The logging request contains at least one incorrect entry that prevents
4	it from being processed. The callback function will not be called.
5	PMIX_ERR_NOT_SUPPORTED The PMIx implementation does not support this function. The
6	callback function will not be called.
7	other appropriate PMIx error code - the callback function will not be called.
	Required Attributes
8	If the PMIx library does not itself perform this operation, then it is required to pass any attributes
9	provided by the client to the host environment for processing. In addition, it must include the
0	following attributes in the passed <i>info</i> array:
1	PMIX_USERID "pmix.euid" (uint32_t)
2	Effective user ID of the connecting process.
3	<pre>PMIX_GRPID "pmix.egid" (uint32_t)</pre>
4	Effective group ID of the connecting process.
5	Host environments or PMIx libraries that implement support for this operation are required to
6	support the following attributes:
7	<pre>PMIX_LOG_STDERR "pmix.log.stderr" (char*)</pre>
8	Log string to stderr.
9	<pre>PMIX_LOG_STDOUT "pmix.log.stdout" (char*)</pre>
20	Log string to stdout .
21	<pre>PMIX_LOG_SYSLOG "pmix.log.syslog" (char*)</pre>
2	Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available,
23	otherwise to local syslog.
24	PMIX_LOG_LOCAL_SYSLOG "pmix.log.lsys" (char*)
25	Log data to local syslog. Defaults to ERROR priority.
26	<pre>PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*)</pre>
27	Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.
28	<pre>PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int)</pre>
9	Syslog priority level.
80	<pre>PMIX_LOG_ONCE "pmix.log.once" (bool)</pre>
50 81	Only log this once with whichever channel can first support it, taking the channels in priority
12	order.
,_	oruci.

Optional Attributes The following attributes are optional for host environments or PMIx libraries that support this 1 2 operation: 3 PMIX LOG SOURCE "pmix.log.source" (pmix proc t*) ID of source of the log request. PMIX LOG TIMESTAMP "pmix.log.tstmp" (time t) 5 6 Timestamp for log report. 7 PMIX LOG GENERATE TIMESTAMP "pmix.log.gtstmp" (bool) Generate timestamp for log. 8 9 PMIX_LOG_TAG_OUTPUT "pmix.log.tag" (bool) Label the output stream with the channel name (e.g., "stdout"). 10 11 PMIX LOG TIMESTAMP OUTPUT "pmix.log.tsout" (bool) Print timestamp in output string. 12 13 PMIX LOG XML OUTPUT "pmix.log.xml" (bool) Print the output stream in XML format. 14 PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t) 15 Log via email based on **pmix_info_t** containing directives. 16 17 PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*) Comma-delimited list of email addresses that are to receive the message. 18 PMIX LOG EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*) 19 Return email address of sender. 20 21 PMIX LOG EMAIL SERVER "pmix.log.esrvr" (char*) 22 Hostname (or IP address) of SMTP server. PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int32_t) 23 24 Port the email server is listening to. 25 PMIX LOG EMAIL SUBJECT "pmix.log.emsub" (char*) Subject line for email. 26 27 PMIX LOG EMAIL MSG "pmix.log.emmsg" (char*) Message to be included in email. 28 29 PMIX LOG JOB RECORD "pmix.log.jrec" (bool) Log the provided information to the host environment's job record. 30 31 PMIX LOG GLOBAL DATASTORE "pmix.log.gstore" (bool)

32

Store the log data in a global data store (e.g., database).

Description

1

3

4

5

6 7

8

9

10

11 12

13

37

Log data subject to the services offered by the host environment. The data to be logged is provided in the *data* array. The (optional) *directives* can be used to direct the choice of logging channel. The callback function will be executed when the log operation has been completed. The *data* and *directives* arrays must be maintained until the callback is provided.

Advice to users

It is strongly recommended that the PMIx_Log_nb API not be used by applications for streaming data as it is not a "performant" transport and can perturb the application since it involves the local PMIx server and host SMS daemon. Note that a return of PMIX_SUCCESS only denotes that the data was successfully handed to the appropriate system call (for local channels) or the host environment and does not indicate receipt at the final destination.

12.4.3 Log attributes

```
Attributes used to describe PMIx_Log behavior - these are values passed to the PMIx_Log API and therefore are not accessed using the PMIx_Get API.
```

```
PMIX LOG SOURCE "pmix.log.source" (pmix proc t*)
14
15
                    ID of source of the log request.
16
              PMIX LOG STDERR "pmix.log.stderr" (char*)
17
                    Log string to stderr.
              PMIX LOG STDOUT "pmix.log.stdout" (char*)
18
19
                    Log string to stdout.
              PMIX_LOG_SYSLOG "pmix.log.syslog" (char*)
20
21
                    Log data to syslog. Defaults to ERROR priority. Will log to global syslog if available,
                    otherwise to local syslog.
22
23
              PMIX LOG LOCAL SYSLOG "pmix.log.lsys" (char*)
                    Log data to local syslog. Defaults to ERROR priority.
24
              PMIX_LOG_GLOBAL_SYSLOG "pmix.log.gsys" (char*)
25
                    Forward data to system "gateway" and log msg to that syslog Defaults to ERROR priority.
26
              PMIX_LOG_SYSLOG_PRI "pmix.log.syspri" (int)
27
28
                    Syslog priority level.
              PMIX LOG TIMESTAMP "pmix.log.tstmp" (time t)
29
                    Timestamp for log report.
30
31
              PMIX LOG GENERATE TIMESTAMP "pmix.log.gtstmp" (bool)
                    Generate timestamp for log.
32
              PMIX LOG TAG_OUTPUT "pmix.log.tag" (bool)
33
                   Label the output stream with the channel name (e.g., "stdout").
34
              PMIX_LOG_TIMESTAMP_OUTPUT "pmix.log.tsout" (bool)
35
36
                    Print timestamp in output string.
```

PMIX LOG XML OUTPUT "pmix.log.xml" (bool)

1	Print the output stream in XML format.
2	PMIX_LOG_ONCE "pmix.log.once" (bool)
3	Only log this once with whichever channel can first support it, taking the channels in priority
4	order.
5	PMIX_LOG_MSG "pmix.log.msg" (pmix_byte_object_t)
6	Message blob to be sent somewhere.
7	PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t)
8	Log via email based on pmix_info_t containing directives.
9	PMIX_LOG_EMAIL_ADDR "pmix.log.emaddr" (char*)
10	Comma-delimited list of email addresses that are to receive the message.
11	PMIX_LOG_EMAIL_SENDER_ADDR "pmix.log.emfaddr" (char*)
12	Return email address of sender.
13	<pre>PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*)</pre>
14	Subject line for email.
15	PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*)
16	Message to be included in email.
17	<pre>PMIX_LOG_EMAIL_SERVER "pmix.log.esrvr" (char*)</pre>
18	Hostname (or IP address) of SMTP server.
19	PMIX_LOG_EMAIL_SRVR_PORT "pmix.log.esrvrprt" (int32_t)
20	Port the email server is listening to.
21	PMIX_LOG_GLOBAL_DATASTORE "pmix.log.gstore" (bool)
22	Store the log data in a global data store (e.g., database).
23	<pre>PMIX_LOG_JOB_RECORD "pmix.log.jrec" (bool)</pre>
24	Log the provided information to the host environment's job record.

CHAPTER 13

Process Sets and Groups

PMIx supports two slightly related, but functionally different concepts known as *process sets* and *process groups*. This chapter defines these two concepts and describes how they are utilized, along with their corresponding APIs.

4 13.1 Process Sets

A PMIx *Process Set* is a user-provided or host environment assigned label associated with a given set of application processes. Processes can belong to multiple process *sets* at a time. Users may define a PMIx process set at time of application execution. For example, if using the command line parallel launcher "prun", one could specify process sets as follows:

\$ prun -n 4 --pset ocean myoceanapp : -n 3 --pset ice myiceapp

In this example, the processes in the first application will be labeled with a PMIX_PSET_NAMES attribute with a value of *ocean* while those in the second application will be labeled with an *ice* value. During the execution, application processes could lookup the process set attribute for any process using PMIx_Get. Alternatively, other executing applications could utilize the PMIx_Query_info APIs to obtain the number of declared process sets in the system, a list of their names, and other information about them. In other words, the *process set* identifier provides a label by which an application can derive information about a process and its application - it does *not*, however, confer any operational function.

Host environments can create or delete process sets at any time through the PMIx_server_define_process_set and PMIx_server_delete_process_set

APIs. PMIx servers shall notify all local clients of process set operations via the

PMIX_PROCESS_SET_DEFINE or PMIX_PROCESS_SET_DELETE events.

Process sets differ from process groups in several key ways:

- Process *sets* have no implied relationship between their members i.e., a process in a process set has no concept of a "pset rank" as it would in a process *group*.
- Process set identifiers are set by the host environment or by the user at time of application submission for execution - there are no PMIx APIs provided by which an application can define a process set or change a process set membership. In contrast, PMIx process groups can only be defined dynamically by the application.

- Process *sets* are immutable members cannot be added or removed once the set has been defined. In contrast, PMIx process *groups* can dynamically change their membership using the appropriate APIs.
- Process groups can be used in calls to PMIx operations. Members of process groups that are involved in an operation are translated by their PMIx server into their native identifier prior to the operation being passed to the host environment. For example, an application can define a process group to consist of ranks 0 and 1 from the host-assigned namespace of 210456, identified by the group id of foo. If the application subsequently calls the PMIx_Fence API with a process identifier of {foo, PMIX_RANK_WILDCARD}, the PMIx server will replace that identifier with an array consisting of {210456, 0} and {210456, 1} the host-assigned identifiers of the participating processes prior to processing the request.
- Process groups can request that the host environment assign a unique size_t Process Group
 Context IDentifier (PGCID) to the group at time of group construction. An Message Passing
 Interface (MPI) library may, for example, use the PGCID as the MPI communicator identifier for
 the group.

The two concepts do, however, overlap in that they both involve collections of processes. Users desiring to create a process group based on a process set could, for example, obtain the membership array of the process set and use that as input to <code>PMIx_Group_construct</code>, perhaps including the process set name as the group identifier for clarity. Note that no linkage between the set and group of the same name is implied nor maintained - e.g., changes in process group membership can not be reflected in the process set using the same identifier.

Advice to PMIx server hosts —

The host environment is responsible for ensuring:

- consistent knowledge of process set membership across all involved PMIx servers; and
- that process set names do not conflict with system-assigned namespaces within the scope of the set.

13.1.1 Process Set Constants

PMIx v4.0 The PMIx server is required to send a notification to all local clients upon creation or deletion of process sets. Client processes wishing to receive such notifications must register for the corresponding event:

PMIX_PROCESS_SET_DEFINE The host environment has defined a new process set - the event will include the process set name (PMIX_PSET_NAME) and the membership (PMIX_PSET_MEMBERS).

PMIX_PROCESS_SET_DELETE The host environment has deleted a process set - the event will include the process set name (**PMIX_PSET_NAME**).

1 13.1.2 Process Set Attributes

Several attributes are provided for querying the system regarding process sets using the 2 PMIx v4.03 PMIx_Query_info APIs. 4 PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t) Return the number of process sets defined in the specified range (defaults to 5 6 PMIX_RANGE_SESSION). 7 PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*) 8 Return a pmix_data_array_t containing an array of strings of the process set names 9 defined in the specified range (defaults to PMIX_RANGE_SESSION). 10 PMIX QUERY PSET MEMBERSHIP "pmix.gry.pmems" (pmix data array t*) Return an array of pmix proc t containing the members of the specified process set. 11 12 The PMIX PROCESS SET DEFINE event shall include the name of the newly defined process set and its members: PMIX PSET NAME "pmix.pset.nm" (char*) 13 The name of the newly defined process set. 14 15 PMIX_PSET_MEMBERS "pmix.pset.mems" (pmix_data_array_t*) An array of **pmix_proc_t** containing the members of the newly defined process set. 16 17 In addition, a process can request (via **PMIx_Get**) the process sets to which a given process 18 (including itself) belongs: PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*) 19 20 Returns an array of char* string names of the process sets in which the given process is a 21 member.

13.2 Process Groups

23 24

25 26

27

28

29

30

31 32

33

34 35 PMIx *Groups* are defined as a collection of processes desiring a common, unique identifier for operational purposes such as passing events or participating in PMIx fence operations. As with processes that assemble via **PMIx_Connect**, each member of the group is provided with both the job-level information of any other namespace represented in the group, and the contact information for all group members.

However, members of PMIx Groups are *loosely coupled* as opposed to *tightly connected* when constructed via **PMIx_Connect**. Thus, *groups* differ from **PMIx_Connect** assemblages in several key areas, as detailed in the following sections.

13.2.1 Relation to the host environment

Calls to PMIx Group APIs are first processed within the local PMIx server. When constructed, the server creates a tracker that associates the specified processes with the user-provided group identifier, and assigns a new *group rank* based on their relative position in the array of processes provided in the call to PMIx_Group_construct. Members of the group can subsequently

utilize the group identifier in PMIx function calls to address the group's members, using either PMIX_RANK_WILDCARD to refer to all of them or the group-level rank of specific members. The PMIx server will translate the specified processes into their RM-assigned identifiers prior to passing the request up to its host. Thus, the host environment has no visibility into the group's existence or membership.

In contrast, calls to PMIx_Connect are relayed to the host environment. This means that the host RM should treat the failure of any process in the specified assemblage as a reportable event and take appropriate action. However, the environment is not required to define a new identifier for the connected assemblage or any of its member processes, nor does it define a new rank for each process within that assemblage. In addition, the PMIx server does not provide any tracking support for the assemblage. Thus, the caller is responsible for addressing members of the connected assemblage using their RM-provided identifiers.

Advice to users

User-provided group identifiers must be distinct from both other group identifiers within the system and namespaces provided by the RM so as to avoid collisions between group identifiers and RM-assigned namespaces. This can usually be accomplished through the use of an application-specific prefix - e.g., "myapp-foo"

13.2.2 Construction procedure

PMIx_Connect calls require that every process call the API before completing – i.e., it is modeled upon the bulk synchronous traditional MPI connect/accept methodology. Thus, a given application thread can only be involved in one connect/accept operation at a time, and is blocked in that operation until all specified processes participate. In addition, there is no provision for replacing processes in the assemblage due to failure to participate, nor a mechanism by which a process might decline participation.

In contrast, PMIx Groups are designed to be more flexible in their construction procedure by relaxing these constraints. While a standard blocking form of constructing groups is provided, the event notification system is utilized to provide a designated *group leader* with the ability to replace participants that fail to participate within a given timeout period. This provides a mechanism by which the application can, if desired, replace members on-the-fly or allow the group to proceed with partial membership. In such cases, the final group membership is returned to all participants upon completion of the operation.

Additionally, PMIx supports dynamic definition of group membership based on an invite/join model. A process can asynchronously initiate construction of a group of any processes via the PMIx_Group_invite function call. Invitations are delivered via a PMIx event (using the PMIX_GROUP_INVITED event) to the invited processes which can then either accept or decline the invitation using the PMIx_Group_join API. The initiating process tracks responses by registering for the events generated by the call to PMIx_Group_join, timeouts, or process

terminations, optionally replacing processes that decline the invitation, fail to respond in time, or terminate without responding. Upon completion of the operation, the final list of participants is communicated to each member of the new group.

13.2.3 Destruct procedure

 Members of a PMIx Group may depart the group at any time via the PMIx_Group_leave API. Other members are notified of the departure via the PMIX_GROUP_LEFT event to distinguish such events from those reporting process termination. This leaves the remaining members free to continue group operations. The PMIx_Group_destruct operation offers a collective method akin to PMIx_Disconnect for deconstructing the entire group.

In contrast, processes that assemble via **PMIx_Connect** must all depart the assemblage together – i.e., no member can depart the assemblage while leaving the remaining members in it. Even the non-blocking form of **PMIx_Disconnect** retains this requirement in that members remain a part of the assemblage until all members have called **PMIx_Disconnect_nb**

Note that applications supporting dynamic group behaviors such as asynchronous departure take responsibility for ensuring global consistency in the group definition prior to executing group collective operations - i.e., it is the application's responsibility to either ensure that knowledge of the current group membership is globally consistent across the participants, or to register for appropriate events to deal with the lack of consistency during the operation.

Advice to users

The reliance on PMIx events in the PMIx Group concept dictates that processes utilizing these APIs must register for the corresponding events. Failure to do so will likely lead to operational failures. Users are recommended to utilize the PMIX_TIMEOUT directive (or retain an internal timer) on calls to PMIx Group APIs (especially the blocking form of those functions) as processes that have not registered for required events will never respond.

4 13.2.4 Process Group Events

PMIx v4.0 Asynchronous process group operations rely heavily on PMIx events. The following events have been defined for that purpose.

PMIX_GROUP_INVITED The process has been invited to join a PMIx Group - the identifier of the group and the ID's of other invited (or already joined) members will be included in the notification.

PMIX_GROUP_LEFT A process has asynchronously left a PMIx Group - the process identifier of the departing process will in included in the notification.

PMIX_GROUP_MEMBER_FAILED A member of a PMIx Group has abnormally terminated (i.e., without formally leaving the group prior to termination) - the process identifier of the failed process will be included in the notification.

PMIX_GROUP_INVITE_ACCEPTED A process has accepted an invitation to join a PMIx 1 2 Group - the identifier of the group being joined will be included in the notification. PMIX GROUP INVITE DECLINED 3 A process has declined an invitation to join a PMIx 4 Group - the identifier of the declined group will be included in the notification. PMIX_GROUP_INVITE_FAILED An invited process failed or terminated prior to responding 5 to the invitation - the identifier of the failed process will be included in the notification. 6 7 PMIX GROUP MEMBERSHIP UPDATE The membership of a PMIx group has changed - the identifiers of the revised membership will be included in the notification. 8 9 PMIX GROUP CONSTRUCT ABORT Any participant in a PMIx group construct operation that returns PMIX_GROUP_CONSTRUCT_ABORT from the leader failed event handler will 10 cause all participants to receive an event notifying them of that status. Similarly, the leader 11 may elect to abort the procedure by either returning this error code from the handler assigned 12 to the PMIX GROUP INVITE ACCEPTED or PMIX GROUP INVITE DECLINED 13 14 codes, or by generating an event for the abort code. Abort events will be sent to all invited or existing members of the group. 15 PMIX GROUP CONSTRUCT COMPLETE The group construct operation has completed - the 16 final membership will be included in the notification. 17 PMIX GROUP LEADER FAILED The current *leader* of a group including this process has 18 abnormally terminated - the group identifier will be included in the notification. 19 PMIX GROUP LEADER SELECTED A new *leader* of a group including this process has been 20 selected - the identifier of the new leader will be included in the notification. 21 PMIX_GROUP_CONTEXT_ID_ASSIGNED A new PGCID has been assigned by the host 22 environment to a group that includes this process - the group identifier will be included in the 23 24 notification.

5 13.2.5 Process Group Attributes

```
Attributes for querying the system regarding process groups include:
26 PMIx v4.0
27
              PMIX_QUERY_NUM_GROUPS "pmix.qry.pgrpnum" (size_t)
                    Return the number of process groups defined in the specified range (defaults to session).
28
                    OPTIONAL QUALIFERS: PMIX RANGE.
29
              PMIX QUERY_GROUP_NAMES "pmix.qry.pgrp" (pmix_data_array_t*)
30
                    Return a pmix data array t containing an array of string names of the process groups
31
32
                    defined in the specified range (defaults to session). OPTIONAL QUALIFERS:
33
                    PMIX RANGE.
              PMIX QUERY GROUP MEMBERSHIP
34
              "pmix.qry.pgrpmems" (pmix_data_array_t*)
35
36
                    Return a pmix data array t of pmix proc t containing the members of the
                    specified process group. REQUIRED QUALIFIERS: PMIX GROUP ID.
37
38
              The following attributes are used as directives in PMIx Group operations:
39
              PMIX GROUP ID "pmix.grp.id" (char*)
```

```
User-provided group identifier - as the group identifier may be used in PMIx operations, the
 1
                      user is required to ensure that the provided ID is unique within the scope of the host
 2
                      environment (e.g., by including some user-specific or application-specific prefix or suffix to
 3
 4
                      the string).
 5
                PMIX_GROUP_LEADER "pmix.grp.ldr" (bool)
                      This process is the leader of the group.
 6
                PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)
 7
                      Participation is optional - do not return an error if any of the specified processes terminate
 8
 9
                      without having joined. The default is false.
                PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool)
10
                      Notify remaining members when another member terminates without first leaving the group.
11
                PMIX GROUP FT COLLECTIVE "pmix.grp.ftcoll" (bool)
12
                      Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective
13
                      operation.
14
15
                PMIX_GROUP_MEMBERSHIP "pmix.grp.mbrs" (pmix_data_array_t*)
                      Array pmix_proc_t identifiers identifying the members of the specified group.
16
                PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)
17
18
                      Requests that the RM assign a new context identifier to the newly created group. The
                      identifier is an unsigned, size_t value that the RM guarantees to be unique across the range
19
                      specified in the request. Thus, the value serves as a means of identifying the group within
20
                      that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
21
                PMIX GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)
22
23
                      Group operation only involves local processes. PMIx implementations are required to
                      automatically scan an array of group members for local vs remote processes - if only local
24
                      processes are detected, the implementation need not execute a global collective for the
25
                      operation unless a context ID has been requested from the host environment. This can result
26
                      in significant time savings. This attribute can be used to optimize the operation by indicating
27
28
                      whether or not only local processes are represented, thus allowing the implementation to
                      bypass the scan.
29
                The following attributes are used to return information at the conclusion of a PMIx Group
30
                operation and/or in event notifications:
31
                PMIX_GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t)
32
                      Context identifier assigned to the group by the host RM.
33
                PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
34
                      Data collected during group construction to ensure communication between group members
35
                      is supported upon completion of the operation.
36
37
                In addition, a process can request (via PMIx Get) the process groups to which a given process
                (including itself) belongs:
38
```

PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*)

1 2 3	13.2.6	Returns an array of char* string names of the process groups in which the given process is a member. PMIx_Group_construct
4		Summary
5		Construct a PMIx process group.
6		Format
	PMIx v4.0	
7		pmix_status_t
8		PMIx_Group_construct(const char grp[],
9		<pre>const pmix_proc_t procs[], size_t nprocs,</pre>
10		<pre>const pmix_info_t directives[],</pre>
11		size_t ndirs,
12		<pre>pmix_info_t **results,</pre>
13		size_t *nresults);
		C
14		IN grp
15		NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
16		identifier (string)
17		IN procs
18		Array of pmix_proc_t structures containing the PMIx identifiers of the member processes
19		(array of handles)
20		IN nprocs
21		Number of elements in the <i>procs</i> array (size_t)
22		IN directives
23		Array of pmix_info_t structures (array of handles)
24		IN ndirs Number of elements in the directines array (zizz t)
25 26		Number of elements in the <i>directives</i> array (size_t) INOUT results
20 27		Pointer to a location where the array of pmix_info_t describing the results of the
28		operation is to be returned (pointer to handle)
29		INOUT nresults
30		Pointer to a size_t location where the number of elements in <i>results</i> is to be returned
31		(memory reference)
32		Returns one of the following:
33		• PMIX_SUCCESS, indicating that the request has been successfully completed
34 35		• PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this operation
36 37		• a PMIx error constant indicating either an error in the input or that the request failed to be completed

	▼ Required Attributes
1 2	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
3 4	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool) This process is the leader of the group.
5 6 7	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
8 9 10 11 12 13 14 15	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool) Group operation only involves local processes. PMIx implementations are required to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
16 17 18	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
19	Host environments that support this operation are required to support the following attributes:
20 21 22 23 24	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
25 26 27	<pre>PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.</pre>
	▼ Optional Attributes
28	The following attributes are optional for host environments that support this operation:
29 30 31 32	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

Construct a new group composed of the specified processes and identified with the provided group identifier. The group identifier is a user-defined, **NULL**-terminated character array of length less than or equal to **PMIX_MAX_NSLEN**. Only characters accepted by standard string comparison functions (e.g., *strncmp*) are supported. Processes may engage in multiple simultaneous group construct operations so long as each is provided with a unique group ID. The *directives* array can be used to pass user-level directives regarding timeout constraints and other options available from the PMIx server.

If the PMIX_GROUP_NOTIFY_TERMINATION attribute is provided and has a value of true, then either the construct leader (if PMIX_GROUP_LEADER is provided) or all participants who register for the PMIX_GROUP_MEMBER_FAILED event will receive events whenever a process fails or terminates prior to calling PMIx_Group_construct – i.e. if a group leader is declared, only that process will receive the event. In the absence of a declared leader, all specified group members will receive the event.

The event will contain the identifier of the process that failed to join plus any other information that the host RM provided. This provides an opportunity for the leader or the collective members to react to the event – e.g., to decide to proceed with a smaller group or to abort the operation. The decision is communicated to the PMIx library in the results array at the end of the event handler. This allows PMIx to properly adjust accounting for procedure completion. When construct is complete, the participating PMIx servers will be alerted to any change in participants and each group member will receive an updated group membership (marked with the PMIX GROUP MEMBERSHIP attribute) as part of the *results* array returned by this API.

Failure of the declared leader at any time will cause a PMIX_GROUP_LEADER_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, thereby declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED event identifying the new leader. If no leader was selected, then the pmix_info_t provided to that event handler will include that information so the participants can take appropriate action.

Any participant that returns PMIX_GROUP_CONSTRUCT_ABORT from either the PMIX_GROUP_MEMBER_FAILED or the PMIX_GROUP_LEADER_FAILED event handler will cause the construct process to abort, returning from the call with a PMIX_GROUP_CONSTRUCT_ABORT status.

If the PMIX_GROUP_NOTIFY_TERMINATION attribute is not provided or has a value of false, then the PMIx_Group_construct operation will simply return an error whenever a proposed group member fails or terminates prior to calling PMIx_Group_construct.

Providing the **PMIX_GROUP_OPTIONAL** attribute with a value of **true** directs the PMIx library to consider participation by any specified group member as non-required - thus, the operation will return **PMIX_SUCCESS** if all members participate, or **PMIX_ERR_PARTIAL_SUCCESS** if some

members fail to participate. The *results* array will contain the final group membership in the latter case. Note that this use-case can cause the operation to hang if the **PMIX_TIMEOUT** attribute is not specified and one or more group members fail to call **PMIx_Group_construct** while continuing to execute. Also, note that no leader or member failed events will be generated during the operation.

Processes in a group under construction are not allowed to leave the group until group construction is complete. Upon completion of the construct procedure, each group member will have access to the job-level information of all namespaces represented in the group plus any information posted via **PMIx_Put** (subject to the usual scoping directives) for every group member.

Advice to PMIx library implementers -

At the conclusion of the construct operation, the PMIx library is *required* to ensure that job-related information from each participating namespace plus any information posted by group members via **PMIx_Put** (subject to scoping directives) is available to each member via calls to **PMIx_Get**.

Advice to PMIx server hosts

The collective nature of this API generally results in use of a fence-like operation by the backend host environment. Host environments that utilize the array of process participants as a *signature* for such operations may experience potential conflicts should both a PMIx_Group_construct and a PMIx_Fence operation involving the same participants be simultaneously executed. As PMIx allows for such use-cases, it is therefore the responsibility of the host environment to resolve any potential conflicts.

13.2.7 PMIx_Group_construct_nb

Summary

Non-blocking form of **PMIx Group construct**.

1		For	rmat C
	PMIx v4.0		
2		-	x_status_t
3		PMI	x_Group_construct_nb(const char grp[],
4			<pre>const pmix_proc_t procs[], size_t nprocs,</pre>
5			<pre>const pmix_info_t directives[],</pre>
6			size_t ndirs,
7			<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
			C
0		IN	
8		IIN	grp
9			NULL -terminated character array of maximum size PMIX_MAX_NSLEN containing the group identifier (string)
11		IN	procs
12			Array of pmix_proc_t structures containing the PMIx identifiers of the member processes
13			(array of handles)
14		IN	nprocs
15			Number of elements in the <i>procs</i> array (size_t)
16		IN	directives
17			Array of pmix_info_t structures (array of handles)
8		IN	ndirs
19			Number of elements in the <i>directives</i> array (size_t)
20		IN	cbfunc
21			Callback function <pre>pmix_info_cbfunc_t</pre> (function reference)
22		IN	cbdata
23			Data to be passed to the callback function (memory reference)
24		Retu	urns one of the following:
25		• P	MIX_SUCCESS indicating that the request has been accepted for processing and the provided
26 27			allback function will be executed upon completion of the operation. Note that the library <i>must</i> ot invoke the callback function prior to returning from the API.
_ /		710	of invoke the canoack function prior to returning from the Art.
28			MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
29		re	eturned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
30		• P	MIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i>
31		w	rill not be called.
32		• a	non-zero PMIx error constant indicating a reason for the request to have been rejected - the
33			bfunc will not be called.
34		Ifev	secuted, the status returned in the provided callback function will be one of the following
35			stants:
,,			
36		• P	MIX_SUCCESS The operation succeeded and all specified members participated.

1 2	 PMIX_ERR_PARTIAL_SUCCESS The operation succeeded but not all specified members participated - the final group membership is included in the callback function.
3 4	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
5	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
6 7	PMIx libraries that choose not to support this operation <i>must</i> return PMIX_ERR_NOT_SUPPORTED when the function is called.
8 9	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
0 1	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool) This process is the leader of the group.
2 3 4	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
5 6 7 8 9 0 1	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool) Group operation only involves local processes. PMIx implementations are <i>required</i> to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
3 4 5	PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
6	Host environments that support this operation are required to provide the following attributes:
7 8 9 0	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
2 3 4	<pre>PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.</pre>

```
Optional Attributes
               The following attributes are optional for host environments that support this operation:
 1
 2
               PMIX TIMEOUT "pmix.timeout" (int)
 3
                     Time in seconds before the specified operation should time out (zero indicating infinite) and
                     return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
 4
                     caused by multiple layers (client, server, and host) simultaneously timing the operation.
 5
               Description
 6
 7
               Non-blocking version of the PMIx Group construct operation. The callback function will be
               called once all group members have called either PMIx_Group construct or
 8
               PMIx_Group_construct_nb.
 9
    13.2.8
                PMIx Group destruct
11
               Summary
               Destruct a PMIx process group.
12
               Format
13
   PMIx v4.0
14
               pmix_status_t
               PMIx_Group_destruct(const char grp[],
15
16
                                          const pmix_info_t directives[],
17
                                          size_t ndirs);
               IN
18
                    grp
19
                    NULL-terminated character array of maximum size PMIX MAX NSLEN containing the
                    identifier of the group to be destructed (string)
20
21
               IN
                    directives
22
                    Array of pmix info t structures (array of handles)
               IN
23
24
                    Number of elements in the directives array (size t)
25
               Returns one of the following:
                • PMIX SUCCESS, indicating that the request has been successfully completed
26
               • PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this
27
28
                  operation
29
               • a PMIx error constant indicating either an error in the input or that the request failed to be
30
                  completed
```

Required Attributes For implementations and host environments that support the operation, there are no identified required attributes for this API. 2 _____ Optional Attributes 3 The following attributes are optional for host environments that support this operation: 4 PMIX TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and 6 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 7 caused by multiple layers (client, server, and host) simultaneously timing the operation. **Description** 8 9 Destruct a group identified by the provided group identifier. Processes may engage in multiple simultaneous group destruct operations so long as each involves a unique group ID. The directives 10 array can be used to pass user-level directives regarding timeout constraints and other options 11 available from the PMIx server. 12 13 The destruct API will return an error if any group process fails or terminates prior to calling PMIx_Group_destruct or its non-blocking version unless the 14 PMIX GROUP NOTIFY TERMINATION attribute was provided (with a value of false) at time 15 16 of group construction. If notification was requested, then the PMIX GROUP MEMBER FAILED event will be delivered for each process that fails to call destruct and the destruct tracker updated to 17 18 account for the lack of participation. The PMIx Group destruct operation will subsequently 19 return **PMIX** SUCCESS when the remaining processes have all called destruct – i.e., the event will 20 serve in place of return of an error. Advice to PMIx server hosts -The collective nature of this API generally results in use of a fence-like operation by the backend 21 host environment. Host environments that utilize the array of process participants as a signature for 22 23 such operations may experience potential conflicts should both a PMIx_Group_destruct and a 24 **PMIx Fence** operation involving the same participants be simultaneously executed. As PMIx

allows for such use-cases, it is therefore the responsibility of the host environment to resolve any

13.2.9 PMIx Group destruct nb

Summary

potential conflicts.

25 26

28 29

Non-blocking form of PMIx Group destruct.

1		Format
	<i>PMIx v4.0</i>	· · · · · · · · · · · · · · · · · · ·
2		pmix_status_t
3		PMIx_Group_destruct_nb(const char grp[],
4		<pre>const pmix_info_t directives[],</pre>
5		size_t ndirs,
6		<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
		U
7		IN grp
8		NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the
9		identifier of the group to be destructed (string)
10		IN directives
11		Array of pmix_info_t structures (array of handles)
12 13		Number of elements in the <i>directives</i> array (size_t)
14		IN cbfunc
15		Callback function pmix_op_cbfunc_t (function reference)
16		IN cbdata
17		Data to be passed to the callback function (memory reference)
18		Returns one of the following:
19 20		• PMIX_SUCCESS , indicating that the request is being processed - result will be returned in the provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning
21		from the API.
22 23		• PMIX_OPERATION_SUCCEEDED , indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called
24 25		• PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i> will <i>not</i> be called.
26 27		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
28 29		If executed, the status returned in the provided callback function will be one of the following constants:
30		• PMIX_SUCCESS The operation was successfully completed.
31		• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM
32		does not.
33		• a non-zero PMIx error constant indicating a reason for the request's failure.

	•	Required Attributes
1 2 3	P	MIx libraries that choose not to support this operation <i>must</i> return MIX_ERR_NOT_SUPPORTED when the function is called. For implementations and host nvironments that support the operation, there are no identified required attributes for this API.
	•	Optional Attributes
4	T	The following attributes are optional for host environments that support this operation:
5 6 7 8	P	Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
9 0 1 2	N ca	Description Non-blocking version of the PMIx_Group_destruct operation. The callback function will be alled once all members of the group have executed either PMIx_Group_destruct or PMIx_Group_destruct_nb.
3	13.2.10	PMIx_Group_invite
4 5		Summary Asynchronously construct a PMIx process group.

1		Format
	PMIx v4.0	· · · · · · · · · · · · · · · · · · ·
2		pmix_status_t
3		<pre>PMIx_Group_invite(const char grp[],</pre>
4		<pre>const pmix_proc_t procs[], size_t nprocs,</pre>
5		<pre>const pmix_info_t directives[], size_t ndirs,</pre>
6		<pre>pmix_info_t **results, size_t *nresult);</pre>
		C
7		IN grp
8		NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
9		identifier (string)
10		IN procs
11		Array of pmix_proc_t structures containing the PMIx identifiers of the processes to be
12		invited (array of handles)
13		IN nprocs
14		Number of elements in the <i>procs</i> array (size_t)
15		IN directives
16		Array of pmix_info_t structures (array of handles)
17		IN ndirs
18		Number of elements in the <i>directives</i> array (size_t)
19		INOUT results
20		Pointer to a location where the array of pmix_info_t describing the results of the
21		operation is to be returned (pointer to handle)
22		INOUT nresults
23		Pointer to a size_t location where the number of elements in results is to be returned
24		(memory reference)
25		Returns one of the following:
26		• PMIX_SUCCESS, indicating that the request has been successfully completed.
27		• PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this
28		operation.
29		• a PMIx error constant indicating either an error in the input or that the request failed to be
30		completed.
		Required Attributes
31		The following attributes are <i>required</i> to be supported by all PMIx libraries that support this
32		operation:
33		PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)
34		Participation is optional - do not return an error if any of the specified processes terminate
34 35		without having joined. The default is false .
J		without having Johneu. The default is raise .

1 PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective 2 3 operation. Host environments that support this operation are *required* to provide the following attributes: 4 5 PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The 6 7 identifier is an unsigned, size t value that the RM guarantees to be unique across the range 8 specified in the request. Thus, the value serves as a means of identifying the group within 9 that range. If no range is specified, then the request defaults to PMIX RANGE SESSION. 10 PMIX GROUP NOTIFY TERMINATION "pmix.grp.notterm" (bool) 11 Notify remaining members when another member terminates without first leaving the group. 12 ----- Optional Attributes The following attributes are optional for host environments that support this operation: 13 14 PMIX TIMEOUT "pmix.timeout" (int) 15 Time in seconds before the specified operation should time out (zero indicating infinite) and 16 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 17 Description 18 Explicitly invite the specified processes to join a group. The process making the 19 20 **PMIx Group invite** call is automatically declared to be the *group leader*. Each invited process will be notified of the invitation via the PMIX GROUP INVITED event - the processes 21 being invited must therefore register for the PMIX GROUP INVITED event in order to be notified 22 of the invitation. Note that the PMIx event notification system caches events - thus, no ordering of 23 24 invite versus event registration is required. 25 The invitation event will include the identity of the inviting process plus the name of the group. 26

The invitation event will include the identity of the inviting process plus the name of the group. When ready to respond, each invited process provides a response using either the blocking or non-blocking form of PMIx_Group_join. This will notify the inviting process that the invitation was either accepted (via the PMIX_GROUP_INVITE_ACCEPTED event) or declined (via the PMIX_GROUP_INVITE_DECLINED event). The PMIX_GROUP_INVITE_ACCEPTED event is captured by the PMIx client library of the inviting process – i.e., the application itself does not need to register for this event. The library will track the number of accepting processes and alert the inviting process (by returning from the blocking form of PMIx_Group_invite or calling the callback function of the non-blocking form) when group construction completes.

27

28 29

30

31

32

33

34

35

The inviting process should, however, register for the **PMIX_GROUP_INVITE_DECLINED** if the application allows invited processes to decline the invitation. This provides an opportunity for the

application to either invite a replacement, declare "abort", or choose to remove the declining process from the final group. The inviting process should also register to receive <code>PMIX_GROUP_INVITE_FAILED</code> events whenever a process fails or terminates prior to responding to the invitation. Actions taken by the inviting process in response to these events must be communicated at the end of the event handler by returning the corresponding result so that the PMIx library can adjust accordingly.

Upon completion of the operation, all members of the new group will receive access to the job-level information of each other's namespaces plus any information posted via **PMIx_Put** by the other members.

The inviting process is automatically considered the leader of the asynchronous group construction procedure and will receive all failure or termination events for invited members prior to completion. The inviting process is required to provide a PMIX_GROUP_CONSTRUCT_COMPLETE event once the group has been fully assembled – this event is used by the PMIx library as a trigger to release participants from their call to PMIx_Group_join and provides information (e.g., the final group membership) to be returned in the *results* array.

Failure of the inviting process at any time will cause a PMIX_GROUP_LEADER_FAILED event to be delivered to all participants so they can optionally declare a new leader. A new leader is identified by providing the PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one process is allowed to return that attribute, declaring itself as the new leader. Results of the leader selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED event identifying the new leader. If no leader was selected, then the status code provided in the event handler will provide an error value so the participants can take appropriate action.

Advice to users

Applications are not allowed to use the group in any operations until group construction is complete. This is required in order to ensure consistent knowledge of group membership across all participants.

13.2.11 PMIx_Group_invite_nb

Summary

Non-blocking form of PMIx_Group_invite.

PMIx v4.	o Format
2 3	pmix_status_t
	PMIx_Group_invite_nb(const char grp[],
4	const pmix_proc_t procs[], size_t nprocs,
5	const pmix_info_t directives[], size_t ndirs,
6	<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
	C
7	IN grp
8	NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
9	identifier (string)
0	IN procs
1	Array of pmix_proc_t structures containing the PMIx identifiers of the processes to be
2	invited (array of handles)
3	IN nprocs
4	Number of elements in the <i>procs</i> array (size_t)
5	IN directives
6	Array of pmix_info_t structures (array of handles)
7	IN ndirs
8	Number of elements in the <i>directives</i> array (size_t)
9	IN cbfunc
	Callback function pmix_info_cbfunc_t (function reference)
20	IN cbdata
21	
22	Data to be passed to the callback function (memory reference)
.3	Returns one of the following:
24	• PMIX_SUCCESS, indicating that the request is being processed - result will be returned in the
25	provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning
26	from the API.
. 	
27	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
28	returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
29	• PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i>
80	will <i>not</i> be called.
э.	a DML array constant indicating aither an array in the input or that the request was immediately
31	• a PMIx error constant indicating either an error in the input or that the request was immediately
12	processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
3	If executed, the status returned in the provided callback function will be one of the following
34	constants:
15	PMIX_SUCCESS The operation succeeded and all specified members participated.
J	• FMIA_30CCE33 THE OPERATION SUCCESSES AND AN SPECIMEN MEMBERS PARTICIPATED.

1 2	 PMIX_ERR_PARTIAL_SUCCESS The operation succeeded but not all specified members participated - the final group membership is included in the callback function.
3 4	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
5	• a non-zero PMIx error constant indicating a reason for the request's failure.
	Required Attributes
6 7	The following attributes are <i>required</i> to be supported by all PMIx libraries that support this operation:
8 9 0	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
1 2 3	<pre>PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.</pre>
4	Host environments that support this operation are required to provide the following attributes:
5 6 7 8 9	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
20 21 22	PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.
	▼ Optional Attributes
:3	The following attributes are optional for host environments that support this operation:
24 25 26 27	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
28	Description
29 30	Non-blocking version of the PMIx_Group_invite operation. The callback function will be called once all invited members of the group (or their substitutes) have executed either
31	PMIx_Group_join or PMIx_Group_join_nb.

13.2.12 PMIx_Group_join Summary 2 3 Accept an invitation to join a PMIx process group. Format PMIx v4.0 5 pmix status t 6 PMIx Group join(const char grp[], 7 const pmix_proc_t *leader, 8 pmix_group_opt_t opt, 9 const pmix info t directives[], size t ndirs, 10 pmix info t **results, size t *nresult); IN 11 grp NULL-terminated character array of maximum size PMIX MAX_NSLEN containing the group 12 identifier (string) 13 IN leader 14 Process that generated the invitation (handle) 15 IN 16 Accept or decline flag (pmix_group_opt_t) 17 directives 18 IN 19 Array of pmix_info_t structures (array of handles) IN ndirs 20 Number of elements in the *directives* array (size_t) 21 **INOUT** results 22 23 Pointer to a location where the array of **pmix_info_t** describing the results of the operation is to be returned (pointer to handle) 24 INOUT presults 25 Pointer to a size_t location where the number of elements in results is to be returned 26 27 (memory reference) 28 Returns one of the following: • PMIX_SUCCESS, indicating that the request has been successfully completed. 29 • PMIX ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this 30 operation. 31 32 • a PMIx error constant indicating either an error in the input or that the request failed to be

There are no identified required attributes for implementers.

completed.

33

34

Required Attributes

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

 Respond to an invitation to join a group that is being asynchronously constructed. The process must have registered for the **PMIX_GROUP_INVITED** event in order to be notified of the invitation. When called, the event information will include the **pmix_proc_t** identifier of the process that generated the invitation along with the identifier of the group being constructed. When ready to respond, the process provides a response using either form of **PMIx_Group_join**.

Advice to users

Since the process is alerted to the invitation in a PMIx event handler, the process *must not* use the blocking form of this call unless it first "thread shifts" out of the handler and into its own thread context. Likewise, while it is safe to call the non-blocking form of the API from the event handler, the process *must not* block in the handler while waiting for the callback function to be called.

Calling this function causes the inviting process (aka the *group leader*) to be notified that the process has either accepted or declined the request. The blocking form of the API will return once the group has been completely constructed or the group's construction has failed (as described below) – likewise, the callback function of the non-blocking form will be executed upon the same conditions.

Failure of the leader during the call to PMIx_Group_join will cause a
PMIX_GROUP_LEADER_FAILED event to be delivered to all invited participants so they can
optionally declare a new leader. A new leader is identified by providing the
PMIX_GROUP_LEADER attribute in the results array in the return of the event handler. Only one
process is allowed to return that attribute, declaring itself as the new leader. Results of the leader
selection will be communicated to all participants via a PMIX_GROUP_LEADER_SELECTED
event identifying the new leader. If no leader was selected, then the status code provided in the
event handler will provide an error value so the participants can take appropriate action.

Any participant that returns PMIX_GROUP_CONSTRUCT_ABORT from the leader failed event handler will cause all participants to receive an event notifying them of that status. Similarly, the leader may elect to abort the procedure by either returning PMIX_GROUP_CONSTRUCT_ABORT from the handler assigned to the PMIX_GROUP_INVITE_ACCEPTED or PMIX_GROUP_INVITE_DECLINED codes, or by generating an event for the abort code. Abort events will be sent to all invited participants.

1 13.2.13 PMIx_Group_join_nb

2			mmary -blocking form of PMIx_Group_join
4 <i>I</i>	PMIx v4.0	For	rmat C
5			.x_status_t
6		PMI	x_Group_join_nb(const char grp[],
7			<pre>const pmix_proc_t *leader,</pre>
8			<pre>pmix_group_opt_t opt,</pre>
9			<pre>const pmix_info_t directives[], size_t ndirs,</pre>
0			<pre>pmix_info_cbfunc_t cbfunc, void *cbdata);</pre>
			C
1		IN	grp
2			NULL -terminated character array of maximum size PMIX_MAX_NSLEN containing the group
3			identifier (string)
4		IN	leader
5			Process that generated the invitation (handle)
6		IN	opt
7			Accept or decline flag (pmix_group_opt_t)
8		IN	directives
9			Array of pmix_info_t structures (array of handles)
0		IN	ndirs
1			Number of elements in the <i>directives</i> array (size_t)
2		IN	cbfunc
3			Callback function <pre>pmix_info_cbfunc_t</pre> (function reference)
4		IN	cbdata
5			Data to be passed to the callback function (memory reference)
6		Retu	urns one of the following:
7		• P	MIX_SUCCESS, indicating that the request is being processed - result will be returned in the
8			rovided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning
9			om the API.
		,	
0			MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
1		re	eturned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
2		• P	MIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i>
3			rill <i>not</i> be called.
J		W	in not be caned.
4		• a	PMIx error constant indicating either an error in the input or that the request was immediately
5		p:	rocessed and failed - the <i>cbfunc</i> will <i>not</i> be called.

1 2	If executed, the status returned in the provided callback function will be one of the following constants:
3 4	 PMIX_SUCCESS The operation succeeded and group membership is in the callback function parameters.
5 6	• PMIX_ERR_NOT_SUPPORTED While the PMIx server supports this operation, the host RM does not.
7	• a non-zero PMIx error constant indicating a reason for the request's failure.
	▼ Required Attributes
8	There are no identified required attributes for implementers.
	▼ Optional Attributes
9	The following attributes are optional for host environments that support this operation:
10 11 12 13	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
14 15 16 17	Description Non-blocking version of the PMIx_Group_join operation. The callback function will be called once all invited members of the group (or their substitutes) have executed either PMIx_Group_join or PMIx_Group_join_nb.
18 13.2.1	3.1 Group accept/decline directives
19 <i>PMIx v4.</i> 20	The <pre>pmix_group_opt_t</pre> type is a <pre>uint8_t</pre> value used with the <pre>PMIx_Group_join</pre> API to indicate accept or decline of the invitation - these are provided for readability of user code:
21 22	PMIX_GROUP_DECLINE Decline the invitation. PMIX_GROUP_ACCEPT Accept the invitation.
23 13.2.	14 PMIx_Group_leave
24 25	Summary Leave a PMIx process group.

DM	Format
PMIx v	
2	pmix_status_t
3	PMIx_Group_leave(const char grp[],
4	<pre>const pmix_info_t directives[],</pre>
5	size_t ndirs);
6	IN grp
7	NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
8	identifier (string)
9	IN directives
10	Array of pmix_info_t structures (array of handles)
11	IN ndirs
12	Number of elements in the <i>directives</i> array (size_t)
13	Returns one of the following:
14	• PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server.
15	• PMIX_ERR_NOT_SUPPORTED The PMIx library and/or the host RM does not support this
16	operation.
17	• a PMIx error constant indicating either an error in the input or that the request is unsupported.
	▼
18	There are no identified required attributes for implementers.
	^^
19	Description
20	Calls to PMIx_Group_leave (or its non-blocking form) will cause a PMIX_GROUP_LEFT
21	event to be generated notifying all members of the group of the caller's departure. The function will
22	return (or the non-blocking function will execute the specified callback function) once the event has
23	been locally generated and is not indicative of remote receipt.
	Advice to users
24	The PMIx_Group_leave API is intended solely for asynchronous departures of individual
25	processes from a group as it is not a scalable operation – i.e., when a process determines it should
26	no longer be a part of a defined group, but the remainder of the group retains a valid reason to
27	continue in existence. Developers are advised to use PMIx_Group_destruct (or its
28	non-blocking form) for all other scenarios as it represents a more scalable operation.

1 13.2.15 PMIx_Group_leave_nb

2	S	ummary
3	N	on-blocking form of PMIx_Group_leave.
4	PMIx v4.0	ormat C
5		mix_status_t
6	P	MIx_Group_leave_nb(const char grp[],
7		<pre>const pmix_info_t directives[],</pre>
8		size_t ndirs,
9		<pre>pmix_op_cbfunc_t cbfunc,</pre>
0		void *cbdata);
		C -
11	11	N grp
12		NULL-terminated character array of maximum size PMIX_MAX_NSLEN containing the group
13		identifier (string)
14	II	directives
15		Array of pmix_info_t structures (array of handles)
16	11	N ndirs
17		Number of elements in the <i>directives</i> array (size_t)
8	11	V cbfunc
19		Callback function <pre>pmix_op_cbfunc_t</pre> (function reference)
20	11	
21		Data to be passed to the callback function (memory reference)
22	R	eturns one of the following:
23	•	PMIX_SUCCESS , indicating that the request is being processed - result will be returned in the
24		provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning
25		from the API.
26	•	PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
27		returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
28		PMIX_ERR_NOT_SUPPORTED The PMIx library does not support this operation - the <i>cbfunc</i>
29		will <i>not</i> be called.
30		a PMIx error constant indicating either an error in the input or that the request was immediately
31		processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
	Τ.(
32		executed, the status returned in the provided callback function will be one of the following
33	Co	onstants:
34	•	PMIX_SUCCESS The operation succeeded - i.e., the PMIX_GROUP_LEFT event was generated.

- PMIX_ERR_NOT_SUPPORTED While the PMIx library supports this operation, the host RM does not.
 - a non-zero PMIx error constant indicating a reason for the request's failure.

----- Required Attributes

There are no identified required attributes for implementers.

Description

1

3

4

5

6 7 Non-blocking version of the **PMIx_Group_leave** operation. The callback function will be called once the event has been locally generated and is not indicative of remote receipt.

CHAPTER 14

Fabric Support Definitions

As the drive for performance continues, interest has grown in scheduling algorithms that take into account network locality of the allocated resources and in optimizing collective communication patterns by structuring them to follow fabric topology. In addition, concerns over the time required to initiate execution of parallel applications and enable communication across them have grown as the size of those applications extends into the hundreds of thousands of individual processes spanning tens of thousands of nodes.

PMIx supports the communication part of these efforts by defining data types and attributes by which fabric endpoints and coordinates for processes and devices can be obtained from the host environment. When used in conjunction with other PMIx methods described in Chapter 16, this results in the ability of a process to obtain the fabric endpoint and coordinate of all other processes without incurring additional overhead associated with a global exchange of that information. This includes:

- Defining several interfaces specifically intended to support WLMs by providing access to information of potential use to scheduling algorithms e.g., information on communication costs between different points on the fabric.
- Supporting hierarchical collective operations by providing the fabric coordinates for all devices on participating nodes as well as a list of the peers sharing each fabric switch. This enables one, for example, to aggregate the contribution from all processes on a node, then again across all nodes on a common switch, and finally across all switches based on detailed knowledge of the fabric location of each participant.
- Enabling the "*instant on*" paradigm to mitigate the scalable launch problem by providing each process with a rich set of information about the environment and the application, including everything required for communication between peers within the application, at time of process start of execution.

Meeting these needs in the case where only a single fabric device exists on each node is relatively straightforward - PMIx and the host environment provide a single endpoint for each process plus a coordinate for the device on each node, and there is no uncertainty regarding the endpoint each process will use. Extending this to the multiple device per node case is more difficult as the choice of endpoint by any given process cannot be known in advance, and questions arise regarding reachability between devices on different nodes. Resolving these ambiguities without requiring a global operation requires that PMIx provide both (a) an endpoint for each application process on each of its local devices; and (b) the fabric coordinates of all remote and local devices on participating nodes. It also requires that each process open all of its assigned endpoints as the endpoint selected for contact by a remote peer cannot be known in advance.

While these steps ensure the ability of a process to connect to a remote peer, it leaves unanswered the question of selecting the *preferred* device for that communication. If multiple devices are present on a node, then the application can benefit from having each process utilize its "closest" fabric device (i.e., the device that minimizes the communication distance between the process' location and that device) for messaging operations. In some cases, messaging libraries prefer to also retain the ability to use non-nearest devices, prioritizing the devices based on distance to support multi-device operations (e.g., for large message transmission in parallel).

PMIx supports this requirement by providing the array of process-to-device distance information for each process and local fabric device at start of execution. Both minimum and maximum distances are provided since a single process can occupy multiple processor locations. In addition, since processes can relocate themselves by changing their processor bindings, PMIx provides an API that allows the process to dynamically request an update to its distance array.

However, while these measures assist a process in selecting its own best endpoint, they do not resolve the uncertainty over the choice of preferred device by a remote peer. There are two methods by which this ambiguity can be resolved:

- a) A process can select a remote endpoint to use based on its own preferred device and reachability of the peer's remote devices. Once the initial connection has been made, the two processes can exchange information and mutually determine their desired communication path going forward.
- b) The application can use knowledge of both the local and remote distance arrays to compute the best communication path and establish that connection. In some instances (e.g., a homogeneous system), a PMIx server may provide distance information for both local and remote devices. Alternatively, when this isn't available, an application can opt to collect the information using the PMIX_COLLECT_GENERATED_JOB_INFO with the PMIX_Fence API, or can obtain it on a one peer-at-a-time basis using the PMIX_Get API on systems where the host environment supports the *Direct Modex* operation.

Information on fabric coordinates, endpoints, and device distances are provided as *reserved keys* as detailed in Chapter 6 - i.e., they are to be available at client start of execution and are subject to the retrieval rules of Section 6.2. Examples for retrieving fabric-related information include retrieval of:

- An array of information on fabric devices for a node by passing PMIX_FABRIC_DEVICES as
 the key to PMIX_Get along with the PMIX_HOSTNAME of the node as a directive
- An array of information on a specific fabric device by passing PMIX_FABRIC_DEVICE as the
 key to PMIx_Get along with the PMIX_DEVICE_ID of the device as a directive
- An array of information on a specific fabric device by passing PMIX_FABRIC_DEVICE as the
 key to PMIX_Get along with both PMIX_FABRIC_DEVICE_NAME of the device and the
 PMIX_HOSTNAME of the node as directives

When requesting data on a device, returned data must include at least the following attributes:

• PMIX HOSTNAME "pmix.hname" (char*)

2	PMIX_NODEID may be returned in its place, or in addition to the hostname.
3 4	• PMIX_DEVICE_ID "pmix.dev.id" (string) System-wide UUID or node-local OS name of a particular device.
5 6 7	• PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.
8 9	• PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.
10 11	• PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string) The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
12 13 14 15 16 17 18 19 20	• PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a Peripheral Component Interconnect (PCI) device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system. This item should be included if the device bus type is PCI - the equivalent should be provided for any other bus type.
21	The returned array may optionally contain one or more of the following in addition to the above list:
22 23	 PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
24 25	• PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string) This is a vendor-provided identifier for the device or product.
26 27	• PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.
28 29	• PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.
30 31 32	• PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a Media Access Control (MAC) address. If multiple addresses are available, only one will be reported.
33 34 35	• PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.

Name of the host, as returned by the **gethostname** utility or its equivalent. The

• PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) 1 2 The maximum transfer unit of link level frames or packets, in bytes. 3 • PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second. 4 5 • PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) 6 The last available physical port state for the specified device. Possible values are 7 PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to 8 indicate if the port state is unknown or not applicable (unknown), inactive (down), or 9 active (up). 10 • PMIX FABRIC DEVICE TYPE "pmix.fabdev.type" (string) 11 Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand. 12 13 The remainder of this chapter details the events, data types, attributes, and APIs associated with 14 fabric-related operations. 14.1 Fabric Support Events 16 The following events are defined for use in fabric-related operations. 17 PMIX FABRIC UPDATE PENDING The PMIx server library has been alerted to a change in the fabric that requires updating of one or more registered **pmix fabric t** objects. 18 19 PMIX FABRIC UPDATED The PMIx server library has completed updating the entries of all 20 affected pmix fabric t objects registered with the library. Access to the entries of those 21 objects may now resume. 22 PMIX FABRIC UPDATE ENDPOINTS Endpoint assignments have been updated, usually in 23 response to migration or restart of a process. Clients should use **PMIx_Get** to update any 24 internally cached connections. 14.2 **Fabric Support Datatypes**

27 14.2.1 Fabric Endpoint Structure

The pmix_endpoint_t structure contains an assigned endpoint for a given fabric device.

Several datatype definitions have been created to support fabric-related operations and information.

PMIx v4.0

```
1
               typedef struct pmix endpoint {
 2
                    char *uuid;
 3
                    char *osname;
                    pmix_byte_object_t endpt;
               } pmix_endpoint_t;
 5
               The uuid field contains the UUID of the fabric device, the osname is the local operating system's
6
               name for the device, and the endpt field contains a fabric vendor-specific object identifying the
 7
               communication endpoint assigned to the process.
 8
    14.2.2
               Fabric endpoint support macros
9
10
               The following macros are provided to support the pmix_endpoint_t structure.
               Initialize the endpoint structure
11
               Initialize the pmix endpoint t fields.
12
   PMIx v4.0
13
               PMIX ENDPOINT CONSTRUCT (m)
               IN
14
                    Pointer to the structure to be initialized (pointer to pmix_endpoint_t)
15
               Destruct the endpoint structure
16
17
               Destruct the pmix endpoint t fields.
   PMIx v4.0
18
               PMIX_ENDPOINT_DESTRUCT (m)
               IN
19
20
                    Pointer to the structure to be destructed (pointer to pmix endpoint t)
21
               Create an endpoint array
22
               Allocate and initialize a pmix_endpoint_t array.
   PMIx v4.0
23
               PMIX_ENDPOINT_CREATE(m, n)
               INOUT m
24
                    Address where the pointer to the array of pmix_endpoint_t structures shall be stored
25
                    (handle)
26
               ĪN
27
                    n
28
                    Number of structures to be allocated (size t)
```

```
Release an endpoint array
 1
 2
                Release an array of pmix endpoint t structures.
   PMIx v4.0
 3
                PMIX ENDPOINT FREE (m, n)
                IN
 4
 5
                     Pointer to the array of pmix_endpoint_t structures (handle)
 6
                IN
 7
                     Number of structures in the array (size t)
    14.2.3 Fabric Coordinate Structure
                The pmix_coord_t structure describes the fabric coordinates of a specified device in a given
 9
10
                view.
   PMIx v4.0
11
                typedef struct pmix_coord {
12
                     pmix_coord_view_t view;
                     uint32_t *coord;
13
14
                      size t dims;
15
                } pmix coord t;
                All coordinate values shall be expressed as unsigned integers due to their units being defined in
16
                fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity
17
                and not relative communication distance.
18

    Advice to PMIx library implementers

                Note that the pmix coord t structure does not imply nor mandate any requirement on how the
19
20
                coordinate data is to be stored within the PMIx library. Implementers are free to store the
21
                coordinate in whatever format they choose.
22
                A fabric coordinate is associated with a given fabric device and must be unique within a given view.
23
                Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates
                are logically grouped within the node realm (as described in Section 6.1) and can be retrieved per
24
25
                the rules detailed in Section 6.1.5.
```

14.2.4 Fabric coordinate support macros

27

The following macros are provided to support the **pmix_coord_t** structure.

1	Initialize the coord structure
2 <i>PMIx v4.0</i>	Initialize the pmix_coord_t fields.
3	PMIX_COORD_CONSTRUCT (m)
4 5	IN m Pointer to the structure to be initialized (pointer to pmix_coord_t)
6 7 <i>PMIx v4.0</i>	Destruct the coord structure Destruct the pmix_coord_t fields.
8 8	PMIX_COORD_DESTRUCT (m)
9 10	IN m Pointer to the structure to be destructed (pointer to pmix_coord_t)
11 12	Create a coord array Allocate and initialize a pmix_coord_t array.
<i>PMIx v4.0</i>	PMIX_COORD_CREATE (m, n)
14 15 16 17	INOUT m Address where the pointer to the array of pmix_coord_t structures shall be stored (handle) IN n Number of structures to be allocated (size_t)
18 19 <i>PMIx v4.0</i>	Release a coord array Release an array of pmix_coord_t structures.
20	PMIX_COORD_FREE (m, n)
21 22 23 24	<pre>IN m Pointer to the array of pmix_coord_t structures (handle) IN n Number of structures in the array (size_t)</pre>

14.2.5 Fabric Geometry Structure

2 The pmix_geometry_t structure describes the fabric coordinates of a specified device. PMIx v4.03 typedef struct pmix geometry { 4 size t fabric; 5 char *uuid; 6 char *osname; 7 pmix_coord_t *coordinates; 8 size t ncoords; 9 } pmix geometry t; All coordinate values shall be expressed as unsigned integers due to their units being defined in 10 fabric devices and not physical distances. The coordinate is therefore an indicator of connectivity 11 12 and not relative communication distance. ——— Advice to PMIx library implementers -Note that the pmix coord t structure does not imply nor mandate any requirement on how the 13 14 coordinate data is to be stored within the PMIx library. Implementers are free to store the 15 coordinate in whatever format they choose. A fabric coordinate is associated with a given fabric device and must be unique within a given view. 16 17 Fabric devices are associated with the operating system which hosts them - thus, fabric coordinates are logically grouped within the *node* realm (as described in Section 6.1) and can be retrieved per 18 the rules detailed in Section 6.1.5. 19 14.2.6 Fabric geometry support macros The following macros are provided to support the **pmix_geometry_t** structure. 21 22 Initialize the geometry structure Initialize the pmix_geometry_t fields. 23 PMIx v4.024 PMIX GEOMETRY CONSTRUCT (m) 25 IN 26 Pointer to the structure to be initialized (pointer to **pmix_geometry_t**)

1		Destruct the geometry structure
2		Destruct the pmix_geometry_t fields.
PM	11x v4.0	C
3		PMIX_GEOMETRY_DESTRUCT (m)
Ü		
4		IN m
5		Pointer to the structure to be destructed (pointer to pmix_geometry_t)
		remore to the situation to each assistance (permore to primary to
6		Create a geometry array
7		Allocate and initialize a pmix_geometry_t array.
אנת	II 10	
PM	IIx v4.0	
8		PMIX_GEOMETRY_CREATE(m, n)
		C
_		
9		INOUT m
0		Address where the pointer to the array of pmix_geometry_t structures shall be stored
1		(handle)
2		IN n
3		Number of structures to be allocated (size_t)
4		Pologo o goometry erroy
4		Release a geometry array
5		Release an array of pmix_geometry_t structures.
PM	11x v4.0	
6		PMIX_GEOMETRY_FREE(m, n)
O .		IMIX_GEOMETRI_IREE (M, II)
7		IN m
8		Pointer to the array of pmix_geometry_t structures (handle)
9		IN n
20		Number of structures in the array (size_t)
		Tumber of Subtraction in the diray (C110_C)

1 14.2.7 Fabric Coordinate Views

PMI:	x v4.0	C
2		<pre>typedef uint8_t pmix_coord_view_t;</pre>
3		#define PMIX_COORD_VIEW_UNDEF 0x00
4		#define PMIX_COORD_LOGICAL_VIEW 0x01
5		#define PMIX_COORD_PHYSICAL_VIEW 0x02
6		Fabric coordinates can be reported based on different <i>views</i> according to user preference at the time
7		of request. The following views have been defined:
8		PMIX_COORD_VIEW_UNDEF The coordinate view has not been defined.
9		PMIX_COORD_LOGICAL_VIEW The coordinates are provided in a <i>logical</i> view, typically
10		given in Cartesian (x,y,z) dimensions, that describes the data flow in the fabric as defined by
11		the arrangement of the hierarchical addressing scheme, fabric segmentation, routing domains,
12		and other similar factors employed by that fabric.
13 14		PMIX_COORD_PHYSICAL_VIEW The coordinates are provided in a <i>physical</i> view based on the actual wiring diagram of the fabric - i.e., values along each axis reflect the relative
15		position of that interface on the specific fabric cabling.
16		If the requester does not specify a view, coordinates shall default to the <i>logical</i> view.
17 14	.2.8	Fabric Link State
18		The pmix_link_state_t is a uint32_t type for fabric link states.
PMI	x v4.0	C
19		<pre>typedef uint8_t pmix_link_state_t;</pre>
.0		C
20		The following constants can be used to set a variable of the type pmix_link_state_t . All
21		definitions were introduced in version 4 of the standard unless otherwise marked. Valid link state
22		values start at zero.
23		PMIX_LINK_STATE_UNKNOWN The port state is unknown or not applicable.
24		PMIX_LINK_DOWN The port is inactive.
25		PMIX_LINK_UP The port is active.
	4	

14.2.9 Fabric Operation Constants

```
The pmix_fabric_operation_t data type is an enumerated type for specifying fabric
  PMIx v4.0
3
              operations used in the PMIx server module's pmix_server_fabric_fn_t API.
              PMIX_FABRIC_REQUEST_INFO
                                                   Request information on a specific fabric - if the fabric isn't
4
5
                   specified as per PMIx_Fabric_register, then return information on the default fabric of
6
                   the overall system. Information to be returned is described in pmix_fabric_t.
7
              PMIX FABRIC UPDATE INFO
                                                 Update information on a specific fabric - the index of the
8
                   fabric (PMIX FABRIC INDEX) to be updated must be provided.
```

14.2.10 Fabric registration structure

The **pmix_fabric_t** structure is used by a WLM to interact with fabric-related PMIx interfaces, and to provide information about the fabric for use in scheduling algorithms or other purposes.

```
PMIx v4.0

typedef struct pmix_fabric_s {
    char *name;
    size_t index;
    pmix_info_t *info;
    size_t ninfo;
    void *module;
    pmix_fabric_t;;
```

Note that in this structure:

- *name* is an optional user-supplied string name identifying the fabric being referenced by this struct. If provided, the field must be a **NULL**-terminated string composed of standard alphanumeric values supported by common utilities such as *strcmp*.;
- *index* is a PMIx-provided number identifying this object;
- *info* is an array of **pmix_info_t** containing information (provided by the PMIx library) about the fabric;
- *ninfo* is the number of elements in the *info* array;
- module points to an opaque object reserved for use by the PMIx server library.

Note that only the *name* field is provided by the user - all other fields are provided by the PMIx library and must not be modified by the user. The *info* array contains a varying amount of information depending upon both the PMIx implementation and information available from the fabric vendor. At a minimum, it must contain (ordering is arbitrary):

10 11

19 20

21

22

23

24

25

26 27

28

29

	▼
1 2	<pre>PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.</pre>
3 4	PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string) An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).
5 6 7	PMIX_FABRIC_NUM_DEVICES "pmix.fab.nverts" (size_t) Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.
8	and may optionally contain one or more of the following:
	→ Optional Attributes
9 10 11	<pre>PMIX_FABRIC_COST_MATRIX "pmix.fab.cm" (pointer) Pointer to a two-dimensional square array of point-to-point relative communication costs expressed as uint16_t values.</pre>
12 13 14 15 16 17	PMIX_FABRIC_GROUPS "pmix.fab.grps" (string) A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes in that group, with the groups delimited by semi-colons (e.g., 0:node000, node002, node004, node006; 1:node001, node003, node005, node007)
18 19 20 21 22	<pre>PMIX_FABRIC_DIMS "pmix.fab.dims" (uint32_t) Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a pmix_data_array_t containing an array of uint32_t values. Default is to provide dimensions in logical view.</pre>
23 24 25 26 27	PMIX_FABRIC_PLANE "pmix.fab.plane" (string) ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.
28 29 30 31	PMIX_FABRIC_SHAPE "pmix.fab.shape" (pmix_data_array_t*) The size of each dimension in the specified fabric plane/view, returned in a pmix_data_array_t containing an array of uint32_t values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one
32	dimension of a physical view of a fabric plane. If no plane is specified, then the shape of
33 34 35	each plane in the overall system will be returned in a pmix_data_array_t array where each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed by that plane's fabric shape. Default is to provide the shape in <i>logical</i> view.

1 2 3 4 5	PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string) Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array where each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed by that plane's fabric shape string. Default is to provide the shape in logical view.
6 7 8 9	While unusual due to scaling issues, implementations may include an array of PMIX_FABRIC_DEVICE elements describing the device information for each device in the overall system. Each element shall contain a pmix_data_array_t of pmix_info_t values describing the device. Each array may contain one or more of the following (ordering is arbitrary):
10 11 12	<pre>PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.</pre>
13 14	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.</pre>
15 16	PMIX_DEVICE_ID "pmix.dev.id" (string) System-wide UUID or node-local OS name of a particular device.
17 18	PMIX_HOSTNAME "pmix.hname" (char*) Name of the host, as returned by the gethostname utility or its equivalent.
19 20	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.</pre>
21 22	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.</pre>
23 24 25	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported.</pre>
26 27	<pre>PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.</pre>
28 29	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.</pre>
30 31 32 33	PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) The last available physical port state for the specified device. Possible values are PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
34 35 36	<pre>PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string) Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.</pre>
37	<pre>PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)</pre>

The type of bus to which the device is attached (e.g., "PCI", "GEN-Z"). 1 2 PMIX FABRIC DEVICE PCI DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a PCI device. Provided only if the device is located on a 3 PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of 4 5 the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in 6 zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The 7 combination of node identifier (PMIX HOSTNAME or PMIX NODEID) and 8 PMIX FABRIC DEVICE PCI DEVID shall be unique within the overall system. 14.2.10.1 Initialize the fabric structure 10 Initialize the **pmix fabric t** fields. PMIx v4.0PMIX FABRIC CONSTRUCT (m) 11 IN 12 13 Pointer to the structure to be initialized (pointer to pmix fabric t) 14.3 **Fabric Support Attributes** The following attribute is used by the PMIx server library supporting the system's WLM to indicate 15 that it wants access to the fabric support functions: 16 17 PMIX SERVER SCHEDULER "pmix.srv.sched" (bool) Server is supporting system scheduler and desires access to appropriate WLM-supporting 18 19 features. Indicates that the library is to be initialized for scheduler support. 20 The following attributes may be returned in response to fabric-specific APIs or queries (e.g., **PMIx_Get** or **PMIx_Query_info**). These attributes are not related to a specific *data realm* (as 21 described in Section 6.1) - the PMIx Get function shall therefore ignore the value in its proc 22 23 process identifier argument when retrieving these values. 24 PMIX FABRIC COST MATRIX "pmix.fab.cm" (pointer) Pointer to a two-dimensional square array of point-to-point relative communication costs 25 expressed as uint16 t values. 26 27 PMIX FABRIC GROUPS "pmix.fab.grps" (string) A string delineating the group membership of nodes in the overall system, where each fabric 28 29 group consists of the group number followed by a colon and a comma-delimited list of nodes in that group, with the groups delimited by semi-colons (e.g., 30 0:node000, node002, node004, node006; 1:node001, node003, 31 32 node005, node007)

PMIX_FABRIC_PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a **pmix_data_array_t** of string identifiers for all fabric planes in the overall system.

PMIX_FABRIC_SWITCH "pmix.fab.switch" (string)

ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a **pmix_data_array_t** of string identifiers for all fabric switches in the overall system.

The following attributes may be returned in response to queries (e.g., PMIx_Get or PMIx_Query_info). A qualifier (e.g., PMIX_FABRIC_INDEX) identifying the fabric whose value is being referenced must be provided for queries on systems supporting more than one fabric when values for the non-default fabric are requested. These attributes are not related to a specific data realm (as described in Section 6.1) - the PMIx_Get function shall therefore ignore the value in its proc process identifier argument when retrieving these values.

PMIX FABRIC VENDOR "pmix.fab.vndr" (string)

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string)

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

PMIX_FABRIC_INDEX "pmix.fab.idx" (size_t)

The index of the fabric as returned in **pmix_fabric_t**.

PMIX_FABRIC_NUM_DEVICES "pmix.fab.nverts" (size_t)

Total number of fabric devices in the overall system - corresponds to the number of rows or columns in the cost matrix.

PMIX FABRIC DIMS "pmix.fab.dims" (uint32 t)

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a **pmix_data_array_t** containing an array of **uint32_t** values. Default is to provide dimensions in *logical* view.

PMIX_FABRIC_SHAPE "pmix.fab.shape" (pmix_data_array_t*)

The size of each dimension in the specified fabric plane/view, returned in a <code>pmix_data_array_t</code> containing an array of <code>uint32_t</code> values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a <code>pmix_data_array_t</code> array where each element is itself a two-element array containing the <code>PMIX_FABRIC_PLANE</code> followed by that plane's fabric shape. Default is to provide the shape in <code>logical</code> view.

PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string)

Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array

1 2	where each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed by that plane's fabric shape string. Default is to provide the shape in <i>logical</i> view.
3	The following attributes are related to the <i>node realm</i> (as described in Section 6.1.5) and are
4	retrieved according to those rules.
5	<pre>PMIX_FABRIC_DEVICES "pmix.fab.devs" (pmix_data_array_t)</pre>
6	Array of pmix_info_t containing information for all devices on the specified node. Each
7	element of the array will contain a PMIX_FABRIC_DEVICE entry, which in turn will
8	contain an array of information on a given device.
9	<pre>PMIX_FABRIC_COORDINATES "pmix.fab.coords" (pmix_data_array_t)</pre>
10	Array of pmix_geometry_t fabric coordinates for devices on the specified node. The
11	array will contain the coordinates of all devices on the node, including values for all
12	supported coordinate views. The information for devices on the local node shall be provided
13	if the node is not specified in the request.
14	<pre>PMIX_FABRIC_DEVICE "pmix.fabdev" (pmix_data_array_t)</pre>
15	An array of pmix_info_t describing a particular fabric device using one or more of the
16	attributes defined below. The first element in the array shall be the PMIX_DEVICE_ID of
17	the device.
18	<pre>PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t)</pre>
19	Index of the device within an associated communication cost matrix.
20	PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string)
21	The operating system name associated with the device. This may be a logical fabric interface
22	name (e.g. "eth0" or "eno1") or an absolute filename.
23	<pre>PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string)</pre>
24	Indicates the name of the vendor that distributes the device.
25	PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string)
26	The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").
27	PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string)
28	This is a vendor-provided identifier for the device or product.
29	PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string)
30	The name of the driver associated with the device.
31	PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string)
32	The device's firmware version.
33	PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string)
34	The primary link-level address associated with the device, such as a MAC address. If
35	multiple addresses are available, only one will be reported.
36	PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The project are a fabric coordinates for the device including values for all
37	The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.
38	supported coordinate views. PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t)
39 40	The maximum transfer unit of link level frames or packets, in bytes.
40 41	PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t)
+1	FMIX_FABRIC_DEVICE_SFEED PMIX.Tabdev.speed (SIZE_C)

1 The active link data rate, given in bits per second. 2 PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) 3 The last available physical port state for the specified device. Possible values are PMIX LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate 4 if the port state is unknown or not applicable (unknown), inactive (down), or active (up). 5 PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string) 6 7 Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand. 8 9 PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string) A node-level unique identifier for a PCI device. Provided only if the device is located on a 10 PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of 11 12 the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in 13 zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The 14 combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and 15 **PMIX_FABRIC_DEVICE_PCI_DEVID** shall be unique within the overall system. The following attributes are related to the process realm (as described in Section 6.1.4) and are 16 retrieved according to those rules. 17 18 PMIX_FABRIC_ENDPT "pmix.fab.endpt" (pmix_data_array_t) 19 Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given 20 process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix data_array t of 21 pmix_endpoint_t elements. 22 23 The following attributes are related to the *job realm* (as described in Section 6.1.2) and are retrieved according to those rules. Note that distances to fabric devices are retrieved using the 24 PMIX_DEVICE_DISTANCES key with the appropriate pmix_device_type_t qualifier. 25 26 PMIX_SWITCH_PEERS "pmix.speers" (pmix_data_array_t) Peer ranks that share the same switch as the process specified in the call to PMIx_Get. 27 Returns a pmix_data_array_t array of pmix_info_t results, each element 28 containing the PMIX SWITCH_PEERS key with a three-element pmix_data_array_t 29 array of pmix info t containing the PMIX_DEVICE_ID of the local fabric device, the 30 31 PMIX FABRIC SWITCH identifying the switch to which it is connected, and a

14.4 Fabric Support Functions

The following APIs allow the WLM to request specific services from the fabric subsystem via the PMIx library.

comma-delimited string of peer ranks sharing the switch to which that device is connected.

32

34

Advice to PMIx server hosts

Due to their high cost in terms of execution, memory consumption, and interactions with other SMS components (e.g., a fabric manager), it is strongly advised that the underlying implementation of these APIs be restricted to a single PMIx server in a system that is supporting the SMS component responsible for the scheduling of allocations (i.e., the system *scheduler*). The **PMIX_SERVER_SCHEDULER** attribute can be used for this purpose to control the execution path. Clients, tools, and other servers utilizing these functions are advised to have their requests forwarded to the server supporting the scheduler using the **pmix_server_fabric_fn_t** server module function, as needed.

14.4.1 PMIx_Fabric_register

Summary

Register for access to fabric-related information.

Format

PMIx v4.0

1

2

4

5

6

7

8

10 11

12

13

14

15

16

17

18

19

20

21

22

23

24

25

pmix_status_t

PMIx_Fabric_register(pmix_fabric_t *fabric,

const pmix_info_t directives[],

size_t ndirs);

INOUT fabric

address of a **pmix_fabric_t** (backed by storage). User may populate the "name" field at will - PMIx does not utilize this field (handle)

IN directives

an optional array of values indicating desired behaviors and/or fabric to be accessed. If **NULL**, then the highest priority available fabric will be used (array of handles)

IN ndirs

Number of elements in the *directives* array (integer)

Returns **PMIX** SUCCESS or a negative value corresponding to a PMIx error constant.

Required Attributes

The following directives are required to be supported by all PMIx libraries to aid users in identifying the fabric whose data is being sought:

PMIX_FABRIC_PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a **pmix_data_array_t** of string identifiers for all fabric planes in the overall system.

PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string)

An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).

PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string)

Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.

Description

Register for access to fabric-related information, including the communication cost matrix. This call must be made prior to requesting information from a fabric. The caller may request access to a particular fabric using the vendor, type, or identifier, or to a specific *fabric plane* via the <code>PMIX_FABRIC_PLANE</code> attribute - otherwise, information for the default fabric will be returned. Upon successful completion of the call, information will have been filled into the fields of the provided *fabric* structure.

For performance reasons, the PMIx library does not provide thread protection for accessing the information in the <code>pmix_fabric_t</code> structure. Instead, the PMIx implementation shall provide two methods for coordinating updates to the provided fabric information:

- Users may periodically poll for updates using the PMIx Fabric update API
- Users may register for PMIX_FABRIC_UPDATE_PENDING events indicating that an update to
 the cost matrix is pending. When received, users are required to terminate or pause any actions
 involving access to the cost matrix before returning from the event. Completion of the
 PMIX_FABRIC_UPDATE_PENDING event handler indicates to the PMIx library that the fabric
 object's entries are available for updating. This may include releasing and re-allocating memory
 as the number of vertices may have changed (e.g., due to addition or removal of one or more
 devices). When the update has been completed, the PMIx library will generate a
 PMIX_FABRIC_UPDATED event indicating that it is safe to begin using the updated fabric
 object(s).

There is no requirement that the caller exclusively use either one of these options. For example, the user may choose to both register for fabric update events, but poll for an update prior to some critical operation.

14.4.2 PMIx_Fabric_register_nb

SummaryRegister for a

Register for access to fabric-related information.

Format

PMIx v4.0

5

6

7

8

10

11

12

13

14

15

16

17 18

19

20

21 22

23

24

25

26 27

28 29

30

31

33

34

INOUT fabric

address of a **pmix_fabric_t** (backed by storage). User may populate the "name" field at will - PMIx does not utilize this field (handle)

IN directives

an optional array of values indicating desired behaviors and/or fabric to be accessed. If **NULL**, then the highest priority available fabric will be used (array of handles)

IN ndirs

Number of elements in the *directives* array (integer)

IN cbfunc

Callback function pmix_op_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed

Description

Non-blocking form of **PMIx_Fabric_register**. The caller is not allowed to access the provided **pmix_fabric_t** until the callback function has been executed, at which time the fabric information will have been loaded into the provided structure.

14.4.3 PMIx Fabric update

Summary

Update fabric-related information.

```
Format
 1
   PMIx v4.0
 2
               pmix status t
               PMIx Fabric update(pmix fabric t *fabric);
 3
 4
               INOUT fabric
                    address of a pmix fabric t (backed by storage) (handle)
 5
 6
               Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
               Description
 7
 8
               Update fabric-related information. This call can be made at any time to request an update of the
 9
               fabric information contained in the provided pmix_fabric_t object. The caller is not allowed to
               access the provided pmix fabric t until the call has returned. Upon successful return, the
10
11
               information fields in the fabric structure will have been updated.
    14.4.4
                PMIx_Fabric_update_nb
13
               Summary
14
               Update fabric-related information.
               Format
15
   PMIx v4.0
16
               pmix status t
17
               PMIx Fabric update nb(pmix fabric t *fabric,
18
                                             pmix op cbfunc t cbfunc, void *cbdata);
               INOUT fabric
19
                    address of a pmix_fabric_t (handle)
20
21
22
                    Callback function pmix op cbfunc t (function reference)
               IN
                     cbdata
23
                    Data to be passed to the callback function (memory reference)
24
25
               Returns one of the following:
26
               • PMIX SUCCESS indicating that the request has been accepted for processing and the provided
27
                  callback function will be executed upon completion of the operation. Note that the library must
                  not invoke the callback function prior to returning from the API.
28
29
                • a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this
30
                  case, the provided callback function will not be executed
```

1	Description
2	Non-blocking form of PMIx_Fabric_update. The caller is not allowed to access the provided
3	<pre>pmix_fabric_t until the callback function has been executed, at which time the fields in the</pre>
4	provided <i>fabric</i> structure will have been updated.
5 14.4	.5 PMIx_Fabric_deregister
6	Summary
7	Deregister a fabric object.
8	Format
PMIx v	d.0 C
9	pmix_status_t
0	PMIx_Fabric_deregister(pmix_fabric_t *fabric);
· ·	TMIX_TABITC_deregister(pmix_tabitc_t *labitc);
1	IN fabric
2	address of a pmix_fabric_t (handle)
3	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
4	Description
5	Deregister a fabric object, providing an opportunity for the PMIx library to cleanup any information
6	(e.g., cost matrix) associated with it. Contents of the provided pmix_fabric_t will be
7	invalidated upon function return.
1	invalidated upon function return.
8 14.4	.6 PMIx_Fabric_deregister_nb
9	Summary
20	Deregister a fabric object.
21	Format
PMIx v	4.0

١

<pre>pmix_status_t</pre>	<pre>PMIx_Fabric_deregister_nb(pmix_fabric_t *fa</pre>	abric,
	pmix_op_cbfunc_t	cbfunc,
	<pre>void *cbdata);</pre>	
	_	

С

IN	fabric
	address of a pmix_fabric_t (handle)
INI	abfuna

Callback function **pmix_op_cbfunc_t** (function reference)

IN cbdata
Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS indicating that the request has been accepted for processing and the provided callback function will be executed upon completion of the operation. Note that the library must not invoke the callback function prior to returning from the API.
- a non-zero PMIx error constant indicating a reason for the request to have been rejected. In this case, the provided callback function will not be executed

Description

Non-blocking form of **PMIx_Fabric_deregister**. Provided *fabric* must not be accessed until after callback function has been executed.

CHAPTER 15

Security

PMIx utilizes a multi-layered approach toward security that differs for client versus tool processes. By definition, *client* processes must be preregistered with the PMIx server library via the PMIx_server_register_client API before they are spawned. This API requires that the host pass the expected effective UID/GID of the client process.

When the client attempts to connect to the PMIx server, the server shall use available standard OS methods to determine the effective UID/GID of the process requesting the connection. PMIx implementations shall not rely on any values reported by the client process itself. The effective UID/GID reported by the OS is compared to the values provided by the host during registration - if the values fail to match, the PMIx server is required to drop the connection request. This ensures that the PMIx server does not allow connection from a client that doesn't at least meet some minimal security requirement.

Once the requesting client passes the initial test, the PMIx server can, at the choice of the implementor, perform additional security checks. This may involve a variety of methods such as exchange of a system-provided key or credential. At the conclusion of that process, the PMIx server reports the client connection request to the host via the

pmix_server_client_connected2_fn_t interface, if provided. The host may perform any additional checks and operations before responding with either **PMIX_SUCCESS** to indicate that the connection is approved, or a PMIx error constant indicating that the connection request is refused. In this latter case, the PMIx server is required to drop the connection.

Tools started by the host environment are classed as a subgroup of client processes and follow the client process procedure. However, tools that are not started by the host environment must be handled differently as registration information is not available prior to the connection request. In these cases, the PMIx server library is required to use available standard OS methods to get the effective UID/GID of the tool and report them upwards as part of invoking the <code>pmix_server_tool_connection_fn_t</code> interface, deferring initial security screening to the host. Host environments willing to accept tool connections must therefore both explicitly enable them via the <code>PMIX_SERVER_TOOL_SUPPORT</code> attribute, thereby confirming acceptance of the authentication and authorization burden, and provide the <code>pmix_server_tool_connection_fn_t</code> server module function pointer.

15.1 Obtaining Credentials

Applications and tools often interact with the host environment in ways that require security beyond just verifying the user's identity - e.g., access to that user's relevant authorizations. This is

1 particularly important when tools connect directly to a system-level PMIx server that may be 2 operating at a privileged level. A variety of system management software packages provide authorization services, but the lack of standardized interfaces makes portability problematic. 3 4 This section defines two PMIx client-side APIs for this purpose. These are most likely to be used by user-space applications/tools, but are not restricted to that realm. 5 15.1.1 PMIx Get credential Summary 8 Request a credential from the PMIx server library or the host environment. Format 9 PMIx v3.010 pmix status t PMIx_Get_credential(const pmix_info_t info[], size_t ninfo, 11 pmix byte object t *credential); 12 IN 13 info 14 Array of pmix info t structures (array of handles) IN 15 Number of elements in the *info* array (size t) 16 17 IN credential Address of a pmix_byte_object_t within which to return credential (handle) 18 19 Returns one of the following: • PMIX SUCCESS, indicating that the credential has been returned in the provided 20 21 pmix byte object t 22 • a PMIx error constant indicating either an error in the input or that the request is unsupported Required Attributes There are no required attributes for this API. Note that implementations may choose to internally 23 execute integration for some security environments (e.g., directly contacting a munge server). 24 Implementations that support the operation but cannot directly process the client's request must 25 pass any attributes that are provided by the client to the host environment for processing. In 26 addition, the following attributes are required to be included in the info array passed from the PMIx 27 library to the host environment: 28 29 PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process. 30 31 PMIX_GRPID "pmix.egid" (uint32_t) 32 Effective group ID of the connecting process.

		A
		▼Optional Attributes
1		The following attributes are optional for host environments that support this operation:
2 3 4 5		PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
6 7 8 9	15 1 0	Description Request a credential from the PMIx server library or the host environment. The credential is returned as a pmix_byte_object_t to support potential binary formats - it is therefore opaque to the caller. No information as to the source of the credential is provided.
10	15.1.2	PMIx_Get_credential_nb
11		Summary
12		Request a credential from the PMIx server library or the host environment.
13	PMIx v3.0	Format
14 15 16 17		<pre>pmix_status_t PMIx_Get_credential_nb(const pmix_info_t info[], size_t ninfo,</pre>
		C
18		IN info
19 20		Array of pmix_info_t structures (array of handles) IN ninfo
21		Number of elements in the <i>info</i> array (size_t)
22		IN cbfunc
23 24		Callback function to return credential (pmix_credential_cbfunc_t function reference)
25		IN cbdata
26		Data to be passed to the callback function (memory reference)
27		Returns one of the following:
28 29		• PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server - result will be returned in the provided <i>cbfunc</i>
30 31		• a PMIx error constant indicating either an error in the input or that the request is unsupported - the <i>cbfunc</i> will <i>not</i> be called

	Required Attributes
1 2	There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a <i>munge</i> server).
3 4 5 6	Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the <i>info</i> array passed from the PMIx library to the host environment:
7 8	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
9	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
	▼Optional Attributes
11	The following attributes are optional for host environments that support this operation:
12 13 14 15	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
16 17 18 19 20	Description Request a credential from the PMIx server library or the host environment. This version of the API is generally preferred in scenarios where the host environment may have to contact a remote credential service. Thus, provision is made for the system to return additional information (e.g., the identity of the issuing agent) outside of the credential itself and visible to the application.
21 15.1.3	Credential Attributes
22	The following attributes are defined to support credential operations:
23 24 25 26 27	PMIX_CRED_TYPE "pmix.sec.ctype" (char*) When passed in PMIx_Get_credential, a prioritized, comma-delimited list of desired credential types for use in environments where multiple authentication mechanisms may be available. When returned in a callback function, a string identifier of the credential type. PMIX_CRYPTO_KEY "pmix.sec.key" (pmix_byte_object_t)

Blob containing crypto key.

1 15.2 Validating Credentials

Given a credential, PMIx provides two methods by which a caller can request that the system validate it, returning any additional information (e.g., authorizations) conveyed within the credential.

5 15.2.1 PMIx_Validate_credential

Summary

Request validation of a credential by the PMIx server library or the host environment.

Format

PMIx v3.0

6 7

8

9

10

11

12

13

14

15 16

17 18

19

20 21

22

23 24

25

26

27

28

29

C

IN cred

Pointer to pmix_byte_object_t containing the credential (handle)

IN info

Array of pmix info t structures (array of handles)

IN ninfo

Number of elements in the *info* array (size t)

INOUT results

Address where a pointer to an array of **pmix_info_t** containing the results of the request can be returned (memory reference)

INOUT nresults

Address where the number of elements in *results* can be returned (handle)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request was processed and returned *success* (i.e., the credential was both valid and any information it contained was successfully processed). Details of the result will be returned in the *results* array
- a PMIx error constant indicating either an error in the parsing of the credential or that the request was refused

	→
1 2	There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a <i>munge</i> server).
3 4 5 6	Implementations that support the operation but cannot directly process the client's request must pass any attributes that are provided by the client to the host environment for processing. In addition, the following attributes are required to be included in the <i>info</i> array passed from the PMIx library to the host environment:
7 8	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
9 10	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
	Outlined Attitle for
	▼ Optional Attributes
11	The following attributes are optional for host environments that support this operation:
12 13 14 15	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
16 17	Description Request validation of a credential by the PMIx server library or the host environment.
18 15.2.2	PMIx_Validate_credential_nb
19 20 21 22	Summary Request validation of a credential by the PMIx server library or the host environment. Provision is made for the system to return additional information regarding possible authorization limitations beyond simple authentication.

1		Format
	<i>PMIx v3.0</i>	<u> </u>
2		pmix_status_t
3		PMIx_Validate_credential_nb(const pmix_byte_object_t *cred,
4		<pre>const pmix_info_t info[], size_t ninfo,</pre>
5		pmix_validation_cbfunc_t cbfunc,
6		<pre>void *cbdata);</pre>
		C
7		IN cred
8		Pointer to pmix_byte_object_t containing the credential (handle)
9		IN info
0		Array of pmix_info_t structures (array of handles)
11		IN ninfo
12		Number of elements in the <i>info</i> array (size_t)
13		IN cbfunc
14		Callback function to return result (pmix_validation_cbfunc_t function reference)
15		IN cbdata
16		Data to be passed to the callback function (memory reference)
17		Returns one of the following:
18 19		• PMIX_SUCCESS, indicating that the request has been communicated to the local PMIx server - result will be returned in the provided <i>cbfunc</i>
20 21		• a PMIx error constant indicating either an error in the input or that the request is unsupported - the <i>cbfunc</i> will <i>not</i> be called
22 23		Upon completion of processing the callback function will be executed. Note that the callback function must not be executed prior to return from the API.
		Required Attributes
24 25		There are no required attributes for this API. Note that implementations may choose to internally execute integration for some security environments (e.g., directly contacting a <i>munge</i> server).
26		Implementations that support the operation but cannot directly process the client's request must
27		pass any attributes that are provided by the client to the host environment for processing. In
28		addition, the following attributes are required to be included in the <i>info</i> array passed from the PMIx
29		library to the host environment:
30		<pre>PMIX_USERID "pmix.euid" (uint32_t)</pre>
31		Effective user ID of the connecting process.
32		PMIX_GRPID "pmix.egid" (uint32_t)
33		Effective group ID of the connecting process.

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_TIMEOUT "pmix.timeout" (int)

Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

1 2

3

5

6 7

8

9 10 Request validation of a credential by the PMIx server library or the host environment. This version of the API is generally preferred in scenarios where the host environment may have to contact a remote credential service. Provision is made for the system to return additional information (e.g., possible authorization limitations) beyond simple authentication.

CHAPTER 16

23 24

Server-Specific Interfaces

2		First, PMIx provides a set of APIs by which the host can request specific services from its library. This includes:
4 5 6 7 8		 collecting inventory to support scheduling algorithms, providing subsystems with an opportunity to precondition their resources for optimized application support, generating regular expressions, registering information to be passed to client processes, and requesting information on behalf of a remote process.
0 1		Note that the host always has access to all PMIx client APIs - the functions listed below are in addition to those available to a PMIx client.
2 3 4 5		Second, the host can provide a set of callback functions by which the PMIx server library can pass requests upward for servicing by the host. These include notifications of client connection and finalize, as well as requests by clients for information and/or services that the PMIx server library does not itself provide.
6	16.1	Server Initialization and Finalization
7		Initialization and finalization routines for PMIx servers.
8	16.1.1	PMIx_server_init
9		Summary Initialize the PMIx server.
1	PMIx v1.0	Format
2		pmix_status_t
3		PMIx_server_init(pmix_server_module_t *module,

pmix_info_t info[], size_t ninfo);

1	INOUT module
2	<pre>pmix_server_module_t structure (handle)</pre>
3	IN info
4	Array of pmix_info_t structures (array of handles)
5	IN ninfo
6	Number of elements in the <i>info</i> array (size_t)
7	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant.
	Required Attributes
8	The following attributes are required to be supported by all PMIx libraries:
9 10	PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*) Name of the namespace to use for this PMIx server.
l1 l2	<pre>PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t) Rank of this PMIx server.</pre>
13	<pre>PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*)</pre>
14	Top-level temporary directory for all client processes connected to this server, and where the
15	PMIx server will place its tool rendezvous point and contact information.
16	PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*)
17	Temporary directory for this system, and where a PMIx server that declares itself to be a
18	system-level server will place a tool rendezvous point and contact information.
19	PMIX_SERVER_TOOL_SUPPORT "pmix.srvr.tool" (bool)
20	The host RM wants to declare itself as willing to accept tool connection requests.
14	
21 22	PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool) The host RM wants to declare itself as being the local system server for PMIx connection
23	requests.
24	PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)
25	The host RM wants to declare itself as being the local session server for PMIx connection
26	requests.
27	<pre>PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool)</pre>
28	Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes
29	(e.g., logging to email).
30	PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)
31	Server is supporting system scheduler and desires access to appropriate WLM-supporting
32	features. Indicates that the library is to be initialized for scheduler support.
	A .

	→ Optional Attributes
1	The following attributes are optional for implementers of PMIx libraries:
2 3 4	PMIX_USOCK_DISABLE "pmix.usock.disable" (bool) Disable legacy UNIX socket (usock) support. If the library supports Unix socket connections, this attribute may be supported for disabling it.
5 6 7	PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.
8 9 10	<pre>PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool) Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.</pre>
11 12 13 14	PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute may be supported for reporting the URI.
15 16 17 18	PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used.
19 20 21 22	PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are <i>not</i> to be used.
23 24 25	<pre>PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int) The IPv4 port to be used If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used.</pre>
26 27 28	<pre>PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used.</pre>
29 30 31	PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it.
32 33 34	PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it.

PMIX_SERVER_REMOTE_CONNECTIONS "pmix.srvr.remote" (bool)

Allow connections from remote tools. Forces the PMIx server to not exclusively use loopback device. If the library supports connections from remote tools, this attribute may be supported for enabling or disabling it.

PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)

The host shall progress the PMIx library via calls to PMIx Progress

PMIX EVENT BASE "pmix.evbase" (void*)

Pointer to an **event_base** to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base *must* be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.

PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t)

Provide a pointer to an implementation-specific description of the local node topology.

PMIX SERVER SHARE TOPOLOGY "pmix.srvr.share" (bool)

The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients. The PMIx server will perform the necessary actions to scalably expose the description to the local clients. This includes creating any required shared memory backing stores and/ or XML representations, plus ensuring that all necessary key-value pairs for clients to access the description are included in the job-level information provided to each client. All required files are to be installed under the effective PMIX_SERVER_TMPDIR directory. The PMIx server library is responsible for cleaning up any artifacts (e.g., shared memory backing files or cached key-value pairs) at library finalize.

PMIX_SERVER_ENABLE_MONITORING "pmix.srv.monitor" (bool) Enable PMIx internal monitoring by the PMIx server.

PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool)

The nodes comprising the session are homogeneous - i.e., they each contain the same number of identical packages, fabric interfaces, GPUs, and other devices.

Description

Initialize the PMIx server support library, and provide a pointer to a <code>pmix_server_module_t</code> structure containing the caller's callback functions. The array of <code>pmix_info_t</code> structs is used to pass additional info that may be required by the server when initializing. For example, it may include the <code>PMIX_SERVER_TOOL_SUPPORT</code> attribute, thereby indicating that the daemon is willing to accept connection requests from tools.

Advice to PMIx server hosts

Providing a value of **NULL** for the *module* argument is permitted, as is passing an empty *module*structure. Doing so indicates that the host environment will not provide support for multi-node operations such as **PMIx_Fence**, but does intend to support local clients access to information.

16.1.2 PMIx_server_finalize

Summary

Finalize the PMIx server library.

Format

PMIx v1.0

5

6

7

8

9

10 11

12

13

15 16

17

18

19 20

21 22

23 24

25 26

27

28

29 30

31

pmix_status_t

PMIx_server_finalize(void);

Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Finalize the PMIx server support library, terminating all connections to attached tools and any local clients. All memory usage is released.

16.1.3 Server Initialization Attributes

These attributes are used to direct the configuration and operation of the PMIx server library by passing them into PMIx_server_init.

```
PMIX TOPOLOGY2 "pmix.topo2" (pmix topology t)
```

Provide a pointer to an implementation-specific description of the local node topology.

PMIX SERVER SHARE TOPOLOGY "pmix.srvr.share" (bool)

The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients.

PMIX_USOCK_DISABLE "pmix.usock.disable" (bool)

Disable legacy UNIX socket (usock) support.

PMIX SOCKET MODE "pmix.sockmode" (uint32 t)

POSIX *mode* t (9 bits valid).

PMIX_SINGLE_LISTENER "pmix.sing.listnr" (bool)

Use only one rendezvous socket, letting priorities and/or environment parameters select the active transport.

```
PMIX_SERVER_TOOL_SUPPORT "pmix.srvr.tool" (bool)
```

The host RM wants to declare itself as willing to accept tool connection requests.

PMIX_SERVER_REMOTE_CONNECTIONS "pmix.srvr.remote" (bool)

1		Allow connections from remote tools. Forces the PMIx server to not exclusively use
2		loopback device.
3		PMIX_SERVER_SYSTEM_SUPPORT "pmix.srvr.sys" (bool)
4		The host RM wants to declare itself as being the local system server for PMIx connection
5		requests.
6		PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool)
7		The host RM wants to declare itself as being the local session server for PMIx connection
8		requests.
9		PMIX_SERVER_START_TIME "pmix.srvr.strtime" (char*)
0		Time when the server started - i.e., when the server created it's rendezvous file (given in
11		ctime string format).
12		PMIX_SERVER_TMPDIR "pmix.srvr.tmpdir" (char*)
13		Top-level temporary directory for all client processes connected to this server, and where the
14		PMIx server will place its tool rendezvous point and contact information.
15		PMIX_SYSTEM_TMPDIR "pmix.sys.tmpdir" (char*)
16		Temporary directory for this system, and where a PMIx server that declares itself to be a
17		system-level server will place a tool rendezvous point and contact information.
8		PMIX_SERVER_ENABLE_MONITORING "pmix.srv.monitor" (bool)
19		Enable PMIx internal monitoring by the PMIx server.
20		PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*)
21		Name of the namespace to use for this PMIx server.
22		PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t)
23		Rank of this PMIx server.
24		PMIX_SERVER_GATEWAY "pmix.srv.gway" (bool)
25		Server is acting as a gateway for PMIx requests that cannot be serviced on backend nodes
26		(e.g., logging to email).
27		PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool)
28		Server is supporting system scheduler and desires access to appropriate WLM-supporting
29		features. Indicates that the library is to be initialized for scheduler support.
30		PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)
31		The host shall progress the PMIx library via calls to PMIx_Progress
32		PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool)
33		The nodes comprising the session are homogeneous - i.e., they each contain the same
34		number of identical packages, fabric interfaces, GPUs, and other devices.
35	16.2	Server Support Functions
36 37		The following APIs allow the RM daemon that hosts the PMIx server library to request specific services from the PMIx library.
) /		services from the Fivilly horary.
38	16.2.1	PMIx_generate_regex
39		Summary
10		Generate a compressed representation of the input string.

Format PMIx v1.0 pmix status t PMIx_generate_regex(const char *input, char **output); IN input String to process (string) **OUT** output Compressed representation of *input* (array of bytes)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

Given a comma-separated list of *input* values, generate a reduced size representation of the input that can be passed down to the PMIx server library's **PMIx_server_register_nspace** API for parsing. The order of the individual values in the *input* string is preserved across the operation. The caller is responsible for releasing the returned data.

The precise compressed representations will be implementation specific. The regular expression itself is not required to be a printable string nor to obey typical string constraints (e.g., include a **NULL** terminator byte). However, all PMIx implementations are required to include a colon-delimited **NULL**-terminated string at the beginning of the output representation that can be printed for diagnostic purposes and identifies the method used to generate the representation. The following identifiers are reserved by the PMIx Standard:

- "raw:\0" indicates that the expression following the identifier is simply the comma-delimited input string (no processing was performed).
- "pmix:\0" a PMIx-unique regular expression represented as a NULL-terminated string following the identifier.
- "blob:\0" a PMIx-unique regular expression that is not represented as a **NULL**-terminated string following the identifier. Additional implementation-specific metadata may follow the identifier along with the data itself. For example, a compressed binary array format based on the *zlib* compression package, with the size encoded in the space immediately following the identifier.

Communicating the resulting output should be done by first packing the returned expression using the PMIx_Data_pack, declaring the input to be of type PMIX_REGEX, and then obtaining the resulting blob to be communicated using the PMIX_DATA_BUFFER_UNLOAD macro. The reciprocal method can be used on the remote end prior to passing the regex into PMIx_server_register_nspace. The pack/unpack routines will ensure proper handling of the data based on the regex prefix.

16.2.2 PMIx_generate_ppn

2 Summary

PMIx v1.0

3

7 8

9 10

11

12

13

14 15

16

17

18

19 20

22

23

24

25

26

27

28 29

30

Generate a compressed representation of the input identifying the processes on each node.

```
Format
```

IN input

String to process (string)

OUT ppn

Compressed representation of *input* (array of bytes)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

Description

The input shall consist of a semicolon-separated list of ranges representing the ranks of processes on each node of the job - e.g., "1-4; 2-5; 8, 10, 11, 12; 6, 7, 9". Each field of the input must correspond to the node name provided at that position in the input to PMIx_generate_regex. Thus, in the example, ranks 1-4 would be located on the first node of the comma-separated list of names provided to PMIx_generate_regex, and ranks 2-5 would be on the second name in the list.

Rules governing the format of the returned regular expression are the same as those specified for **PMIx generate regex**, as detailed here.

16.2.3 PMIx_server_register_nspace

Summary

Setup the data about a particular namespace.

Format

```
PMIx v1.0
```

void *cbdata);

1	IN	nspace
2		Character array of maximum size PMIX_MAX_NSLEN containing the namespace identifier
3		(string)
4	IN	nlocalprocs
5		number of local processes (integer)
6	IN	info
7 8	IN	Array of info structures (array of handles) ninfo
9	114	Number of elements in the <i>info</i> array (integer)
10	IN	cbfunc
11		Callback function pmix_op_cbfunc_t to be executed upon completion of the operation.
12		A NULL function reference indicates that the function is to be executed as a blocking
13		operation (function reference)
14	IN	cbdata
15		Data to be passed to the callback function (memory reference)
16	Retu	arns one of the following:
17	• P	MIX_SUCCESS, indicating that the request is being processed by the host environment - result
18	w	ill be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
19	fu	unction prior to returning from the API.
20	• P	MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
21		eturned success - the cbfunc will not be called
22	• a	PMIx error constant indicating either an error in the input or that the request was immediately
23		rocessed and failed - the <i>cbfunc</i> will not be called
	▼-	Required Attributes
24	The	following attributes are required to be supported by all PMIx libraries:
25	рмт	X_REGISTER_NODATA "pmix.reg.nodata" (bool)
26		Registration is for this namespace only, do not copy job data.
27	DMT	X_SESSION_INFO_ARRAY "pmix.ssn.arr" (pmix_data_array_t)
28	PMI	Provide an array of pmix_info_t containing session-realm information. The
29	4	PMIX_SESSION_ID attribute is required to be included in the array.
30	PMI	X_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t)
31		Provide an array of pmix_info_t containing job-realm information. The
32		PMIX_SESSION_ID attribute of the <i>session</i> containing the <i>job</i> is required to be included in
33		the array whenever the PMIx server library may host multiple sessions (e.g., when executing
34		with a host RM daemon). As information is registered one job (aka namespace) at a time via
35		the PMIx_server_register_nspace API, there is no requirement that the array
36		contain either the PMIX_NSPACE or PMIX_JOBID attributes when used in that context

 (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

PMIX_APP_INFO_ARRAY "pmix.app.arr" (pmix_data_array_t)

Provide an array of **pmix_info_t** containing application-realm information. The **PMIX_NSPACE** or **PMIX_JOBID** attributes of the *job* containing the application, plus its **PMIX_APPNUM** attribute, must to be included in the array when the array is *not* included as part of a call to **PMIx_server_register_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX_PROC_INFO_ARRAY "pmix.pdata" (pmix_data_array_t)

Provide an array of <code>pmix_info_t</code> containing process-realm information. The <code>PMIX_RANK</code> and <code>PMIX_NSPACE</code> attributes, or the <code>PMIX_PROCID</code> attribute, are required to be included in the array when the array is not included as part of a call to <code>PMIx_server_register_nspace</code> - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the <code>PMIX_RANK</code> or the <code>PMIX_PROCID</code> attribute must be included (the others are optional).

PMIX_NODE_INFO_ARRAY "pmix.node.arr" (pmix_data_array_t)

Provide an array of **pmix_info_t** containing node-realm information. At a minimum, either the **PMIX_NODEID** or **PMIX_HOSTNAME** attribute is required to be included in the array, though both may be included.

Host environments are required to provide a wide range of session-, job-, application-, node-, and process-realm information, and may choose to provide a similarly wide range of optional information. The information is broadly separated into categories based on the *data realm* definitions explained in Section 6.1, and retrieved according to the rules detailed in Section 6.2.

Session-realm information may be passed as individual <code>pmix_info_t</code> entries, or as part of a <code>pmix_data_array_t</code> using the <code>PMIX_SESSION_INFO_ARRAY</code> attribute. The list of data referenced in this way shall include:

- PMIX_UNIV_SIZE "pmix.univ.size" (uint32_t)
 - Maximum number of process that can be simultaneously executing in a session. Note that this attribute is equivalent to the **PMIX_MAX_PROCS** attribute for the *session* realm it is included in the PMIx Standard for historical reasons.
- PMIX_MAX_PROCS "pmix.max.size" (uint32_t)

Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the *job* realm. Must be provided if **PMIX_UNIV_SIZE** is not given. Requires use of the **PMIX_SESSION_INFO** attribute to avoid ambiguity when retrieving it.

• PMIX_SESSION_ID "pmix.session.id" (uint32_t)

1	Session identifier assigned by the scheduler.
2	plus the following optional information:
3 4 5	 PMIX_CLUSTER_ID "pmix.clid" (char*) A string name for the cluster this allocation is on. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
6 7 8	 PMIX_ALLOCATED_NODELIST "pmix.alist" (char*) Comma-delimited list or regular expression of all nodes in the specified realm regardless of whether or not they currently host processes. Defaults to the job realm.
9 10 11	• PMIX_RM_NAME "pmix.rm.name" (char*) String name of the RM. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
12 13 14	 PMIX_RM_VERSION "pmix.rm.version" (char*) RM version string. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
15 16 17	 PMIX_SERVER_HOSTNAME "pmix.srvr.host" (char*) Host where target PMIx server is located. As this information is not related to the namespace, it is best passed using the PMIx_server_register_resources API.
18 19 20	Job-realm information may be passed as individual pmix_info_t entries, or as part of a pmix_data_array_t using the PMIX_JOB_INFO_ARRAY attribute. The list of data referenced in this way shall include:
21 22 23	• PMIX_SERVER_NSPACE "pmix.srv.nspace" (char*) Name of the namespace to use for this PMIx server. Identifies the namespace of the PMIx server itself
24 25	• PMIX_SERVER_RANK "pmix.srv.rank" (pmix_rank_t) Rank of this PMIx server. Identifies the rank of the PMIx server itself.
26 27 28 29 30	 PMIX_NSPACE "pmix.nspace" (char*) Namespace of the job - may be a numerical value expressed as a string, but is often an alphanumeric string carrying information solely of use to the system. Required to be unique within the scope of the host environment. Identifies the namespace of the job being registered.
31 32 33	• PMIX_JOBID "pmix.jobid" (char*) Job identifier assigned by the scheduler to the specified job - may be identical to the namespace, but is often a numerical value expressed as a string (e.g., "12345.3").
34 35	• PMIX_JOB_SIZE "pmix.job.size" (uint32_t) Total number of processes in the specified job across all contained applications. Note that

36

37

this value can be different from PMIX_MAX_PROCS. For example, users may choose to

subdivide an allocation (running several jobs in parallel within it), and dynamic

1 2 3	programming models may support adding and removing processes from a running <i>job</i> on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.
4 5 6 7 8	• PMIX_MAX_PROCS "pmix.max.size" (uint32_t) Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the job realm. Retrieval of this attribute defaults to the job level unless an appropriate specification is given (e.g., PMIX_SESSION_INFO).
9 10 11	 PMIX_NODE_MAP "pmix.nmap" (char*) Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
12 13 14	 PMIX_PROC_MAP "pmix.pmap" (char*) Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
15	plus the following optional information:
16 17	 PMIX_NPROC_OFFSET "pmix.offset" (pmix_rank_t) Starting global rank of the specified job.
18 19 20	 PMIX_JOB_NUM_APPS "pmix.job.napps" (uint32_t) Number of applications in the specified job. This is a required attribute if more than one application is included in the job.
21 22 23 24	 PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.
25 26 27 28	 PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.
29 30 31 32	 PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
33 34	• PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.
35 36 37	• PMIX_ANL_MAP "pmix.anlmap" (char*) Process map equivalent to PMIX_PROC_MAP expressed in Argonne National Laboratory's PMI-1/PMI-2 notation. Defaults to the <i>job</i> realm.

2	Resource Manager will cleanup assigned temporary directory trees.
3 4	PMIX_CRYPTO_KEY "pmix.sec.key" (pmix_byte_object_t) Blob containing crypto key.
5 6 7	If more than one application is included in the namespace, then the host environment is also required to supply data consisting of the following items for each application in the job, passed as a <code>pmix_data_array_t</code> using the <code>PMIX_APP_INFO_ARRAY</code> attribute:
8 9 10	• PMIX_APPNUM "pmix.appnum" (uint32_t) The application number within the job in which the specified process is a member. This attribute must appear at the beginning of the array.
11 12 13	• PMIX_APP_SIZE "pmix.app.size" (uint32_t) Number of processes in the specified application, regardless of their execution state - i.e., this number may include processes that either failed to start or have already terminated.
14 15 16 17 18	• PMIX_MAX_PROCS "pmix.max.size" (uint32_t) Maximum number of processes that can be executed in the specified realm. Typically, this is a constraint imposed by a scheduler or by user settings in a hostfile or other resource description. Defaults to the <i>job</i> realm. Requires use of the PMIX_APP_INFO attribute to avoid ambiguity when retrieving it.
19 20	• PMIX_APPLDR "pmix.aldr" (pmix_rank_t) Lowest rank in the specified application.
21 22 23 24	 PMIX_WDIR "pmix.wdir" (char*) Working directory for spawned processes. This attribute is required for all registrations, but may be provided as an individual pmix_info_t entry if only one application is included in the namespace.
25 26 27 28	• PMIX_APP_ARGV "pmix.app.argv" (char*) Consolidated argv passed to the spawn command for the given application (e.g., "./myapp arg1 arg2 arg3"). This attribute is required for all registrations, but may be provided as an individual pmix_info_t entry if only one application is included in the namespace.
29	plus the following optional information:
30 31 32	• PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*) Returns an array of char* string names of the process sets in which the given process is a member.
33 34 35 36	• PMIX_APP_MAP_TYPE "pmix.apmap.type" (char*) Type of mapping used to layout the application (e.g., cyclic). This attribute may be provided as an individual pmix_info_t entry if only one application is included in the namespace.
37	• PMIX_APP_MAP_REGEX "pmix.apmap.regex" (char*)

1 Regular expression describing the result of the process mapping. This attribute may be 2 provided as an individual pmix info t entry if only one application is included in the namespace. 3 4 The data may also include attributes provided by the host environment that identify the programming model (as specified by the user) being executed within the application. The PMIx 5 server library may utilize this information to customize the environment to fit that model (e.g., 6 7 adding environmental variables specified by the corresponding standard for that model): 8 • PMIX PROGRAMMING MODEL "pmix.pqm.model" (char*) 9 Programming model being initialized (e.g., "MPI" or "OpenMP"). • PMIX MODEL LIBRARY NAME "pmix.mdl.name" (char*) 10 Programming model implementation ID (e.g., "OpenMPI" or "MPICH"). 11 • PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char*) 12 Programming model version string (e.g., "2.1.1"). 13 14 Node-realm information may be passed as individual pmix info t entries if only one node will 15 host processes from the job being registered, or as part of a pmix data array t using the PMIX NODE INFO ARRAY attribute when multiple nodes are involved in the job. The list of data 16 referenced in this way shall include: 17 • PMIX_NODEID "pmix.nodeid" (uint32_t) 18 Node identifier expressed as the node's index (beginning at zero) in an array of nodes 19 within the active session. The value must be unique and directly correlate to the 20 **PMIX_HOSTNAME** of the node - i.e., users can interchangeably reference the same 21 22 location using either the PMIX HOSTNAME or corresponding PMIX_NODEID. 23 • PMIX HOSTNAME "pmix.hname" (char*) 24 Name of the host, as returned by the **gethostname** utility or its equivalent. As this information is not related to the namespace, it can be passed using the 25 PMIx_server_register_resources API. However, either it or the 26 27 **PMIX_NODEID** must be included in the array to properly identify the node.

• PMIX_HOSTNAME_ALIASES "pmix.alias" (char*)

Comma-delimited list of names by which the target node is known. As this information is not related to the namespace, it is best passed using the **PMIx_server_register_resources** API.

• PMIX_LOCAL_SIZE "pmix.local.size" (uint32_t)

Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the **PMIX_APP_INFO** and the **PMIX_APPNUM** qualifiers are given.

- PMIX_NODE_SIZE "pmix.node.size" (uint32_t)

 Number of processes across all jobs that are executing upon the node.
- PMIX_LOCALLDR "pmix.lldr" (pmix_rank_t)

28

29

30 31

32

33

34 35

36

Comma-delimited list of ranks that are executing on the local node within the specified 4 namespace – shortcut for **PMIx_Resolve_peers** for the local node. 5 plus the following information for the server's own node: 6 7 • PMIX TMPDIR "pmix.tmpdir" (char*) Full path to the top-level temporary directory assigned to the session. 8 9 • PMIX NSDIR "pmix.nsdir" (char*) Full path to the temporary directory assigned to the specified job, under PMIX TMPDIR. 10 • PMIX_LOCAL_PROCS "pmix.lprocs" (pmix_proc_t array) 11 Array of pmix_proc_t of all processes executing on the local node – shortcut for 12 PMIx Resolve peers for the local node and a NULL namespace argument. The 13 process identifier is ignored for this attribute. 14 15 The data may also include the following optional information for the server's own node: • PMIX_LOCAL_CPUSETS "pmix.lcpus" (pmix_data_array_t) 16 A pmix data array t array of string representations of the PU binding bitmaps 17 applied to each local peer on the caller's node upon launch. Each string shall begin with 18 19 the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself. The array shall be in the same order as the processes returned by 20 PMIX LOCAL PEERS for that namespace. 21 22 • PMIX AVAIL PHYS MEMORY "pmix.pmem" (uint64 t) 23 Total available physical memory on a node. As this information is not related to the namespace, it can be passed using the PMIx_server_register_resources API. 24 and the following optional information for other nodes: 25 26 • PMIX MAX PROCS "pmix.max.size" (uint32 t) Maximum number of processes that can be executed in the specified realm. Typically, this 27 is a constraint imposed by a scheduler or by user settings in a hostfile or other resource 28 description. Defaults to the job realm. Requires use of the PMIX_NODE_INFO attribute 29 30 to avoid ambiguity when retrieving it. Process-realm information shall include the following data for each process in the job, passed as a 31 32 pmix_data_array_t using the PMIX_PROC_INFO_ARRAY attribute: 33 • PMIX_RANK "pmix.rank" (pmix_rank_t) 34 Process rank within the job, starting from zero. • PMIX_APPNUM "pmix.appnum" (uint32_t) 35 36 The application number within the job in which the specified process is a member. This attribute may be omitted if only one application is present in the namespace. 37

Lowest rank within the specified job on the node (defaults to current node in absence of

PMIX HOSTNAME or PMIX NODEID qualifier).

• PMIX LOCAL PEERS "pmix.lpeers" (char*)

1

• PMIX_APP_RANK "pmix.apprank" (pmix_rank_t)

Rank of the specified process within its application. This attribute may be omitted if only one application is present in the namespace.

• PMIX_GLOBAL_RANK "pmix.grank" (pmix_rank_t)

Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and end at random times, this is defined as a continually growing number - i.e., it is not dynamically adjusted as individual jobs and processes are started or terminated.

• PMIX_LOCAL_RANK "pmix.lrank" (uint16_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

• PMIX_NODE_RANK "pmix.nrank" (uint16_t)

Rank of the specified process on its node spanning all jobs- refers to the numerical location (starting from zero) of the process on its node when counting all processes (regardless of job) that share the node, ordered by their overall rank within the job. The value represents a snapshot in time when the specified process was started on its node and is not dynamically adjusted as processes from other jobs are started or terminated on the node.

• PMIX NODEID "pmix.nodeid" (uint32 t)

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the **PMIX_HOSTNAME** of the node - i.e., users can interchangeably reference the same location using either the **PMIX_HOSTNAME** or corresponding **PMIX_NODEID**.

• PMIX REINCARNATION "pmix.reinc" (uint32 t)

Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5

• PMIX_SPAWNED "pmix.spawned" (bool)

true if this process resulted from a call to **PMIx_Spawn**. Lack of inclusion (i.e., a return status of **PMIX_ERR_NOT_FOUND**) corresponds to a value of **false** for this attribute.

plus the following information for processes that are local to the server:

• PMIX_LOCALITY_STRING "pmix.locstr" (char*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to <code>PMIx_Get_relative_locality</code> for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to <code>PMIx_Get</code> for the locality string of a process that returns <code>PMIX_ERR_NOT_FOUND</code> indicates that the process is not executing on the same node.

1 2	 PMIX_PROCDIR "pmix.pdir" (char*) Full path to the subdirectory under PMIX_NSDIR assigned to the specified process.
3 4 5 6 7 8	• PMIX_PACKAGE_RANK "pmix.pkgrank" (uint16_t) Rank of the specified process on the <i>package</i> where this process resides - refers to the numerical location (starting from zero) of the process on its package when counting only those processes from the same job that share the package, ordered by their overall rank within that job. Note that processes that are not bound to PUs within a single specific package cannot have a package rank.
9 10 11	and the following optional information - note that some of this information can be derived from information already provided by other attributes, but it may be included here for ease of retrieval by users:
12 13	• PMIX_HOSTNAME "pmix.hname" (char*) Name of the host, as returned by the gethostname utility or its equivalent.
14 15 16 17	• PMIX_CPUSET "pmix.cpuset" (char*) A string representation of the PU binding bitmap applied to the process upon launch. The string shall begin with the name of the library that generated it (e.g., "hwloc") followed by a colon and the bitmap string itself.
18 19	• PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*) Bitmap applied to the process upon launch.
20 21 22 23	• PMIX_DEVICE_DISTANCES "pmix.dev.dist" (pmix_data_array_t) Return an array of pmix_device_distance_t containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.
24	
25	Attributes not directly provided by the host environment may be derived by the PMIx server library
26	from other required information and included in the data made available to the server library's

Description

clients.

27

28

29

Pass job-related information to the PMIx server library for distribution to local client processes.

Advice to PMIx server hosts

Host environments are required to execute this operation prior to starting any local application process within the given namespace.

The PMIx server must register all namespaces that will participate in collective operations with local processes. This means that the server must register a namespace even if it will not host any local processes from within that namespace if any local process of another namespace might at some point perform an operation involving one or more processes from the new namespace. This is necessary so that the collective operation can identify the participants and know when it is locally complete.

The caller must also provide the number of local processes that will be launched within this namespace. This is required for the PMIx server library to correctly handle collectives as a collective operation call can occur before all the local processes have been started.

A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

Advice to users

The number of local processes for any given namespace is generally fixed at the time of application launch. Calls to PMIx Spawn result in processes launched in their own namespace, not that of their parent. However, it is possible for processes to migrate to another node via a call to PMIx Job_control_nb, thus resulting in a change to the number of local processes on both the initial node and the node to which the process moved. It is therefore critical that applications not migrate processes without first ensuring that PMIx-based collective operations are not in progress, and that no such operations be initiated until process migration has completed.

1

2 3

4

5

6 7

8

9

10

11 12

13

14 15

16

17

18

16.2.3.1 Namespace registration attributes

2

3

4

5

6

7

8

9

10

11 12

13

14

15

16 17

18 19

20

21

22

23 24

25

26 27

28 29

30

31

32

33

34 35

36

37 38

39

40

41

The following attributes are defined specifically for use with the PMIx server register nspace API: PMIX REGISTER NODATA "pmix.reg.nodata" (bool) Registration is for this namespace only, do not copy job data.

The following attributes are used to assemble information according to its data realm (session, job, application, node, or process as defined in Section 6.1) for registration where ambiguity may exist see 16.2.3.2 for examples of their use.

PMIX SESSION INFO ARRAY "pmix.ssn.arr" (pmix data array t) Provide an array of **pmix info t** containing session-realm information. The **PMIX SESSION ID** attribute is required to be included in the array.

PMIX_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t) Provide an array of **pmix** info t containing job-realm information. The **PMIX SESSION** ID attribute of the session containing the job is required to be included in the array whenever the PMIx server library may host multiple sessions (e.g., when executing with a host RM daemon). As information is registered one job (aka namespace) at a time via the PMIx server register nspace API, there is no requirement that the array contain either the PMIX NSPACE or PMIX JOBID attributes when used in that context (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

PMIX APP INFO ARRAY "pmix.app.arr" (pmix data array t) Provide an array of pmix info t containing application-realm information. The PMIX NSPACE or PMIX JOBID attributes of the job containing the application, plus its PMIX APPNUM attribute, must to be included in the array when the array is not included as part of a call to PMIx server register nspace - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX_PROC_INFO_ARRAY "pmix.pdata" (pmix_data_array_t) Provide an array of pmix info t containing process-realm information. The PMIX RANK and PMIX NSPACE attributes, or the PMIX PROCID attribute, are required to be included in the array when the array is not included as part of a call to PMIx server register nspace - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the PMIX_RANK or the PMIX_PROCID attribute must be included (the others are optional).

PMIX NODE INFO ARRAY "pmix.node.arr" (pmix data array t) Provide an array of pmix info t containing node-realm information. At a minimum, either the PMIX_NODEID or PMIX_HOSTNAME attribute is required to be included in the array, though both may be included.

Note that these assemblages can be used hierarchically:

• a PMIX JOB INFO ARRAY might contain multiple PMIX APP INFO ARRAY elements, each describing values for a specific application within the job.

- a PMIX_JOB_INFO_ARRAY could contain a PMIX_NODE_INFO_ARRAY for each node hosting processes from that job, each array describing job-level values for that node.
- a PMIX_SESSION_INFO_ARRAY might contain multiple PMIX_JOB_INFO_ARRAY
 elements, each describing a job executing within the session. Each job array could, in turn,
 contain both application and node arrays, thus providing a complete picture of the active
 operations within the allocation.

Advice to PMIx library implementers

PMIx implementations must be capable of properly parsing and storing any hierarchical depth of information arrays. The resulting stored values are must to be accessible via both **PMIx_Get** and **PMIx_Query_info_nb** APIs, assuming appropriate directives are provided by the caller.

16.2.3.2 Assembling the registration information

The following description is not intended to represent the actual layout of information in a given PMIx library. Instead, it is describes how information provided in the *info* parameter of the **PMIx_server_register_nspace** shall be organized for proper processing by a PMIx server library. The ordering of the various information elements is arbitrary - they are presented in a top-down hierarchical form solely for clarity in reading.

Advice to PMIx server hosts -

Creating the *info* array of data requires knowing in advance the number of elements required for the array. This can be difficult to compute and somewhat fragile in practice. One method for resolving the problem is to create a linked list of objects, each containing a single <code>pmix_info_t</code> structure. Allocation and manipulation of the list can then be accomplished using existing standard methods. Upon completion, the final *info* array can be allocated based on the number of elements on the list, and then the values in the list object <code>pmix_info_t</code> structures transferred to the corresponding array element utilizing the <code>PMIX_INFO_XFER</code> macro.

A common building block used in several areas is the construction of a regular expression identifying the nodes involved in that area - e.g., the nodes in a *session* or *job*. PMIx provides several tools to facilitate this operation, beginning by constructing an argy-like array of node names. This array is then passed to the **PMIx_generate_regex** function to create a regular expression parseable by the PMIx server library, as shown below:

```
C
```

```
char **nodes = NULL;
char *nodelist;
char *regex;
size_t n;
pmix_status_t rc;
pmix_info_t info;
/* loop over an array of nodes, adding each
 * name to the array */
for (n=0; n < num_nodes; n++) {
    /* filter the nodes to ignore those not included
     * in the target range (session, job, etc.). In
     * this example, all nodes are accepted */
    PMIX_ARGV_APPEND(&nodes, node[n]->name);
}
/* join into a comma-delimited string */
nodelist = PMIX ARGV JOIN(nodes, ',');
/* release the array */
PMIX_ARGV_FREE (nodes);
/* generate regex */
rc = PMIx_generate_regex(nodelist, &regex);
/* release list */
free (nodelist);
/* pass the regex as the value to the PMIX_NODE_MAP key */
PMIX_INFO_LOAD(&info, PMIX_NODE_MAP, regex, PMIX_REGEX);
/* release the regex */
free (regex);
```

1

2

3

4

5

6

7 8

9

10

11

12 13

14 15

16

17

18 19 20

21 22 23

24 25

26 27

28 29

30 31

32

33

34

35

36 37

38

Changing the filter criteria allows the construction of node maps for any level of information. A description of the returned regular expression is provided here.

A similar method is used to construct the map of processes on each node from the namespace being registered. This may be done for each information level of interest (e.g., to identify the process map for the entire *job* or for each *application* in the job) by changing the search criteria. An example is shown below for the case of creating the process map for a *job*:

```
1
            char **ndppn;
2
            char rank[30];
3
            char **ppnarray = NULL;
4
            char *ppn;
5
            char *localranks;
6
            char *regex;
7
            size_t n, m;
8
            pmix_status_t rc;
9
            pmix_info_t info;
10
            /* loop over an array of nodes */
11
            for (n=0; n < num nodes; n++) {
12
13
                /* for each node, construct an array of ranks on that node */
14
                ndppn = NULL;
15
                for (m=0; m < node[n] \rightarrow num procs; m++) {
16
                    /* ignore processes that are not part of the target job */
17
                    if (!PMIX CHECK NSPACE(targetjob, node[n]->proc[m].nspace)) {
18
                         continue;
19
20
                    snprintf(rank, 30, "%d", node[n]->proc[m].rank);
                    PMIX_ARGV_APPEND(&ndppn, rank);
21
22
23
                /* convert the array into a comma-delimited string of ranks */
                localranks = PMIX_ARGV_JOIN(ndppn, ',');
24
                /* release the local array */
25
26
                PMIX ARGV FREE (ndppn);
                /* add this node's contribution to the overall array */
27
28
                PMIX_ARGV_APPEND(&ppnarray, localranks);
29
                /* release the local list */
                free(localranks);
30
31
            }
32
33
            /* join into a semicolon-delimited string */
34
            ppn = PMIX_ARGV_JOIN(ppnarray, ';');
35
            /* release the array */
36
37
            PMIX_ARGV_FREE (ppnarray);
38
39
            /* generate ppn regex */
40
            rc = PMIx_generate_ppn(ppn, &regex);
41
42
            /* release list */
```

```
1     free(ppn);
2
3     /* pass the regex as the value to the PMIX_PROC_MAP key */
4     PMIX_INFO_LOAD(&info, PMIX_PROC_MAP, regex, PMIX_REGEX);
5     /* release the regex */
```

free (regex);

 \sim

Note that the PMIX_NODE_MAP and PMIX_PROC_MAP attributes are linked in that the order of entries in the process map must match the ordering of nodes in the node map - i.e., there is no provision in the PMIx process map regular expression generator/parser pair supporting an out-of-order node or a node that has no corresponding process map entry (e.g., a node with no processes on it). Armed with these tools, the registration *info* array can be constructed as follows:

• Session-level information includes all session-specific values. In many cases, only two values (PMIX_SESSION_ID and PMIX_UNIV_SIZE) are included in the registration array. Since both of these values are session-specific, they can be specified independently - i.e., in their own pmix_info_t elements of the info array. Alternatively, they can be provided as a pmix_data_array_t array of pmix_info_t using the PMIX_SESSION_INFO_ARRAY attribute and identifed by including the PMIX_SESSION_ID attribute in the array - this is required in cases where non-specific attributes (e.g., PMIX_NUM_NODES or PMIX_NODE_MAP) are passed to describe aspects of the session. Note that the node map can include nodes not used by the job being registered as no corresponding process map is specified.

The *info* array at this point might look like (where the labels identify the corresponding attribute - e.g., "Session ID" corresponds to the **PMIX SESSION_ID** attribute):




Figure 16.1.: Session-level information elements

Job-level information includes all job-specific values such as PMIX_JOB_SIZE,
 PMIX_JOB_NUM_APPS, and PMIX_JOBID. Since each invocation of
 PMIX_server_register_nspace describes a single job, job-specific values can be specified independently - i.e., in their own pmix_info_t elements of the info array.
 Alternatively, they can be provided as a pmix_data_array_t array of pmix_info_t identified by the PMIX_JOB_INFO_ARRAY attribute - this is required in cases where non-specific attributes (e.g., PMIX_NODE_MAP) are passed to describe aspects of the job. Note

that since the invocation only involves a single namespace, there is no need to include the **PMIX NSPACE** attribute in the array.

Upon conclusion of this step, the *info* array might look like:




Figure 16.2.: Job-level information elements

Note that in this example, PMIX_NUM_NODES is not required as that information is contained in the PMIX_NODE_MAP attribute. Similarly, PMIX_JOB_SIZE is not technically required as that information is contained in the PMIX_PROC_MAP when combined with the corresponding node map - however, there is no issue with including the job size as a separate entry.

The example also illustrates the hierarchical use of the PMIX_NODE_INFO_ARRAY attribute. In this case, we have chosen to pass several job-related values for each node - since those values are non-unique across the job, they must be passed in a node-info container. Note that the choice of what information to pass into the PMIx server library versus what information to derive from other values at time of request is left to the host environment. PMIx implementors in turn may, if they choose, pre-parse registration data to create expanded views (thus enabling faster response to requests at the expense of memory footprint) or to compress views into tighter representations (thus trading minimized footprint for longer response times).

Application-level information includes all application-specific values such as PMIX_APP_SIZE

and PMIX_APPLDR. If the *job* contains only a single *application*, then the application-specific values can be specified independently - i.e., in their own pmix_info_t elements of the *info* array - or as a pmix_data_array_t array of pmix_info_t using the PMIX_APP_INFO_ARRAY attribute and identified by including the PMIX_APPNUM attribute in the array. Use of the array format is must in cases where non-specific attributes (e.g., PMIX_NODE_MAP) are passed to describe aspects of the application.

However, in the case of a job consisting of multiple applications, all application-specific values for each application must be provided using the **PMIX_APP_INFO_ARRAY** format, each identified by its **PMIX_APPNUM** value.

Upon conclusion of this step, the *info* array might look like that shown in 16.3, assuming there are two applications in the job being registered:




Figure 16.3.: Application-level information elements

- Process-level information includes an entry for each process in the job being registered, each
 entry marked with the PMIX_PROC_INFO_ARRAY attribute. The rank of the process must be
 the first entry in the array this provides efficiency when storing the data. Upon conclusion of
 this step, the info array might look like the diagram in 16.4:
- For purposes of this example, node-level information only includes values describing the local node i.e., it does not include information about other nodes in the job or session. In many cases, the values included in this level are unique to it and can be specified independently i.e., in their own pmix_info_t elements of the *info* array. Alternatively, they can be provided as a




Figure 16.4.: Process-level information elements

pmix_data_array_t array of pmix_info_t using the PMIX_NODE_INFO_ARRAY
attribute - this is required in cases where non-specific attributes are passed to describe aspects of
the node, or where values for multiple nodes are being provided.

The node-level information requires two elements that must be constructed in a manner similar to that used for the node map. The **PMIX_LOCAL_PEERS** value is computed based on the processes on the local node, filtered to select those from the job being registered, as shown below using the tools provided by PMIx:

```
char **ndppn = NULL;
char rank[30];
char *localranks;
size t m;
pmix_info_t info;
for (m=0; m < mynode->num_procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob, mynode->proc[m].nspace)) {
        continue;
    snprintf(rank, 30, "%d", mynode->proc[m].rank);
    PMIX ARGV APPEND (&ndppn, rank);
/* convert the array into a comma-delimited string of ranks */
localranks = PMIX ARGV JOIN(ndppn, ',');
/* release the local array */
PMIX ARGV FREE (ndppn);
/* pass the string as the value to the PMIX_LOCAL_PEERS key */
PMIX_INFO_LOAD(&info, PMIX_LOCAL_PEERS, localranks, PMIX_STRING);
/* release the list */
free(localranks);
```

The PMIX_LOCAL_CPUSETS value is constructed in a similar manner. In the provided example, it is assumed that an Hardware Locality (HWLOC) cpuset representation (a comma-delimited string of processor IDs) of the processors assigned to each process has previously been generated and stored on the process description. Thus, the value can be constructed as shown below:

```
char **ndcpus = NULL;
char *localcpus;
size_t m;
pmix_info_t info;

for (m=0; m < mynode->num_procs; m++) {
    /* ignore processes that are not part of the target job */
    if (!PMIX_CHECK_NSPACE(targetjob,mynode->proc[m].nspace)) {
        continue;
```

```
}
    PMIX_ARGV_APPEND(&ndcpus, mynode->proc[m].cpuset);

}
/* convert the array into a colon-delimited string */
localcpus = PMIX_ARGV_JOIN(ndcpus, ':');
/* release the local array */
PMIX_ARGV_FREE(ndcpus);

/* pass the string as the value to the PMIX_LOCAL_CPUSETS key */
PMIX_INFO_LOAD(&info, PMIX_LOCAL_CPUSETS, localcpus, PMIX_STRING);

/* release the list */
free(localcpus);
```

Note that for efficiency, these two values can be computed at the same time.

The final *info* array might therefore look like the diagram in 16.5:




Figure 16.5.: Final information array

16.2.4 PMIx_server_deregister_nspace Summary Deregister a namespace. 3 Format PMIx v1.0 5 void PMIx_server_deregister_nspace(const pmix_nspace_t nspace, 6 pmix op cbfunc t cbfunc, void *cbdata); IN 7 nspace Namespace (string) 8 9 IN cbfunc 10 Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the function is to be executed as a blocking operation. (function reference) 11 IN 12 cbdata Data to be passed to the callback function (memory reference) 13 **Description** 14 15 Deregister the specified *nspace* and purge all objects relating to it, including any client information from that namespace. This is intended to support persistent PMIx servers by providing an 16 opportunity for the host RM to tell the PMIx server library to release all memory for a completed 17 18 job. Note that the library must not invoke the callback function prior to returning from the API, and that a **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation. 19 16.2.5 PMIx server register resources Summary 21 22 Register non-namespace related information with the local PMIx server library. 23 Format PMIx v4.024 pmix_status_t 25 PMIx_server_register_resources(pmix_info_t info[], size_t ninfo, 26 pmix_op_cbfunc_t cbfunc, 27 void *cbdata); IN info 28 Array of info structures (array of handles) 29 30 IN ninfo 31 Number of elements in the *info* array (integer)

IN 1 cbfunc 2 Callback function pmix op cbfunc t. A NULL function reference indicates that the function is to be executed as a blocking operation (function reference) 3 4 IN cbdata 5 Data to be passed to the callback function (memory reference) **Description** 6 7 Pass information about resources not associated with a given namespace to the PMIx server library 8 for distribution to local client processes. This includes information on fabric devices, GPUs, and 9 other resources. All information provided through this API shall be made available to each job as part of its job-level information. Duplicate information provided with the 10 11 PMIx server register nspace API shall override any information provided by this 12 function for that namespace, but only for that specific namespace. Advice to PMIx server hosts 13 Note that information passed in this manner could also have been included in a call to 14 PMIx server register nspace - e.g., as part of a PMIX NODE INFO ARRAY array. This API is provided as a logical alternative for code clarity, especially where multiple jobs may be 15 supported by a single PMIx server library instance, to avoid multiple registration of static resource 16 information. 17 18 A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation. 16.2.6 PMIx server deregister resources 19 Summary 20 Remove specified non-namespace related information from the local PMIx server library. 21 22 **Format** PMIx v4.023 pmix status t PMIx server_deregister_resources(pmix_info_t info[], size_t ninfo, 24 25 pmix_op_cbfunc_t cbfunc,

27 IN info
28 Array of info structures (array of handles)
29 IN ninfo
30 Number of elements in the *info* array (integer)
31 IN cbfunc

Callback function <code>pmix_op_cbfunc_t</code>. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference) <code>cbdata</code>

Data to be passed to the callback function (memory reference)

ĪN

32

33 34

Description

Remove information about resources not associated with a given namespace from the PMIx server library. Only the *key* fields of the provided *info* array shall be used for the operation - the associated values shall be ignored except where they serve as qualifiers to the request. For example, to remove a specific fabric device from a given node, the *info* array might include a PMIX_NODE_INFO_ARRAY containing the PMIX_NODEID or PMIX_HOSTNAME identifying the node hosting the device, and the PMIX_FABRIC_DEVICE_NAME specifying the device to be

Advice to PMIx server hosts

removed. Alternatively, the device could be removed using only the PMIX DEVICE ID as this is

As information not related to namespaces is considered *static*, there is no requirement that the host environment deregister resources prior to finalizing the PMIx server library. The server library shall properly cleanup as part of its normal finalize operations. Deregistration of resources is only required, therefore, when the host environment determines that client processes should no longer have access to that information.

A **NULL** *cbfunc* reference indicates that the function is to be executed as a blocking operation.

16.2.7 PMIx_server_register_client

unique across the overall system.

Summary

Register a client process with the PMIx server library.

Format

```
PMIx v1.0
```

```
IN proc

pmix_proc_t structure (handle)
```

IN uid user id (integer)

IN gid

group id (integer)

IN server_object (memory reference)

IN 1 cbfunc 2 Callback function pmix op cbfunc t. A NULL function reference indicates that the function is to be executed as a blocking operation (function reference) 3 4 IN cbdata 5 Data to be passed to the callback function (memory reference) 6 Returns one of the following: 7 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 8 will be returned in the provided cbfunc. Note that the library must not invoke the callback function prior to returning from the API. 9 10 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 11 • a PMIx error constant indicating either an error in the input or that the request was immediately 12 13 processed and failed - the cbfunc will not be called **Description** 14 Register a client process with the PMIx server library. 15 16 The host server can also, if it desires, provide an object it wishes to be returned when a server function is called that relates to a specific process. For example, the host server may have an object 17 18 that tracks the specific client. Passing the object to the library allows the library to provide that 19 object to the host server during subsequent calls related to that client, such as a 20 pmix server client connected2 fn t function. This allows the host server to access the object without performing a lookup based on the client's namespace and rank. 21 Advice to PMIx server hosts -22 Host environments are required to execute this operation prior to starting the client process. The expected user ID and group ID of the child process allows the server library to properly authenticate 23 clients as they connect by requiring the two values to match. Accordingly, the detected user and 24 group ID's of the connecting process are not included in the 25 26 pmix_server_client_connected2_fn_t server module function. Advice to PMIx library implementers -For security purposes, the PMIx server library should check the user and group ID's of a 27 28 connecting process against those provided for the declared client process identifier via the 29 PMIx server register client prior to completing the connection.

Summarv 2 Deregister a client and purge all data relating to it. 3 **Format** PMIx v1.0 5 void 6 PMIx server deregister client(const pmix proc t *proc, pmix_op_cbfunc_t cbfunc, void *cbdata); 7 8 IN proc 9 pmix proc t structure (handle) IN cbfunc 10 11 Callback function pmix op cbfunc t. A NULL function reference indicates that the 12 function is to be executed as a blocking operation (function reference) IN 13 cbdata 14 Data to be passed to the callback function (memory reference) Description 15 16 The PMIx server deregister nspace API will delete all client information for that 17 namespace. The PMIx server library will automatically perform that operation upon disconnect of all local clients. This API is therefore intended primarily for use in exception cases, but can be 18 called in non-exception cases if desired. Note that the library must not invoke the callback function 19 20 prior to returning from the API. 16.2.9 PMIx server setup fork 21 Summary 22 23 Setup the environment of a child process to be forked by the host. 24 Format PMIx v1.0 25 pmix_status_t 26 PMIx_server_setup_fork(const pmix_proc_t *proc, 27 char ***env); IN 28 proc 29 pmix proc t structure (handle) IN 30 31 Environment array (array of strings) 32 Returns **PMIX SUCCESS** or a negative value corresponding to a PMIx error constant.

PMIx_server_deregister_client

16.2.8

Description

1

3

5 6

7

8

10

11

12

13

14

15

16

17

18

19

20 21

22

23

24 25

26

27

Setup the environment of a child process to be forked by the host so it can correctly interact with the PMIx server.

The PMIx client needs some setup information so it can properly connect back to the server. This function will set appropriate environmental variables for this purpose, and will also provide any environmental variables that were specified in the launch command (e.g., via PMIx_Spawn) plus other values (e.g., variables required to properly initialize the client's fabric library).

Advice to PMIx server hosts -

Host environments are required to execute this operation prior to starting the client process.

16.2.10 PMIx_server_dmodex_request

Summary

Define a function by which the host server can request modex data from the local PMIx server.

Format

```
PMIx v1.0
```

PMIx_server_dmodex_request(const pmix_proc_t *proc,

pmix_dmodex_response_fn_t cbfunc,

void *cbdata);

IN proc

pmix proc t structure (handle)

IN cbfunc

pmix status t

Callback function pmix dmodex response fn t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMTX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- a PMIx error constant indicating an error in the input the *cbfunc* will not be called

Description

Define a function by which the host server can request modex data from the local PMIx server. Traditional wireup procedures revolve around the per-process posting of data (e.g., location and endpoint information) via the PMIx_Put and PMIx_Commit functions followed by a PMIx_Fence barrier that globally exchanges the posted information. However, the barrier operation represents a signficant time impact at large scale.

PMIx supports an alternative wireup method known as *Direct Modex* that replaces the barrier-based exchange of all process-posted information with on-demand fetch of a peer's data. In place of the barrier operation, data posted by each process is cached on the local PMIx server. When a process requests the information posted by a particular peer, it first checks the local cache to see if the data is already available. If not, then the request is passed to the local PMIx server, which subsequently requests that its RM host request the data from the RM daemon on the node where the specified peer process is located. Upon receiving the request, the RM daemon passes the request into its PMIx server library using the PMIx_server_dmodex_request function, receiving the response in the provided *cbfunc* once the indicated process has posted its information. The RM daemon then returns the data to the requesting daemon, who subsequently passes the data to its PMIx server library for transfer to the requesting client.

Advice to users

While direct modex allows for faster launch times by eliminating the barrier operation, per-peer retrieval of posted information is less efficient. Optimizations can be implemented - e.g., by returning posted information from all processes on a node upon first request - but in general direct modex remains best suited for sparsely connected applications.

16.2.10.1 Server Direct Modex Response Callback Function

The PMIx server dmodex request callback function.

Summary

Provide a function by which the local PMIx server library can return connection and other data posted by local application processes to the host resource manager.

```
Format
1
   PMIx v1.0
2
               typedef void (*pmix_dmodex_response_fn_t)(
                                        pmix status t status,
 3
                                        char *data, size_t sz,
 4
                                        void *cbdata);
5
               IN
                    status
6
 7
                   Returned status of the request (pmix_status_t)
8
               IN
                   Pointer to a data "blob" containing the requested information (handle)
9
               IN
10
                   Number of bytes in the data blob (integer)
11
               IN
12
                    cbdata
                   Data passed into the initial call to PMIx_server_dmodex_request (memory reference)
13
               Description
14
               Define a function to be called by the PMIx server library for return of information posted by a local
15
               application process (via PMIx_Put with subsequent PMIx_Commit) in response to a request
16
17
               from the host RM. The returned data blob is owned by the PMIx server library and will be free'd
18
               upon return from the function.
    16.2.11
                 PMIx_server_setup_application
20
               Summary
               Provide a function by which a launcher can request application-specific setup data prior to launch of
21
22
               a job.
               Format
23
   PMIx v2.0
24
               pmix_status_t
25
               PMIx_server_setup_application(const pmix_nspace_t nspace,
                                             pmix_info_t info[], size_t ninfo,
26
                                             pmix_setup_application_cbfunc_t cbfunc,
27
28
                                             void *cbdata);
29
                    nspace
30
                   namespace (string)
               IN
                    info
31
32
                   Array of info structures (array of handles)
```

1 2 3 4 5 6	 IN ninfo Number of elements in the <i>info</i> array (integer) IN cbfunc Callback function pmix_setup_application_cbfunc_t (function reference) IN cbdata Data to be passed to the <i>cbfunc</i> callback function (memory reference)
7	Returns one of the following:
8 9 10	 PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>. Note that the library must not invoke the callback function prior to returning from the API.
11	• a PMIx error constant indicating either an error in the input - the <i>cbfunc</i> will not be called
	Required Attributes
12	PMIx libraries that support this operation are required to support the following:
13 14	PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool) Harvest and include relevant environmental variables.
15 16	PMIX_SETUP_APP_NONENVARS ""pmix.setup.nenv" (bool) Include all relevant data other than environmental variables.
17 18	PMIX_SETUP_APP_ALL "pmix.setup.all" (bool) Include all relevant data.
19 20 21 22	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
223 24 25 26 27 28 29 33 33 34 34 35	The key to be used when accessing this requested fabric allocation. The fabric allocation will be returned/stored as a pmix_info_t whose first element is composed of this key and the allocated resource description. The type of the included value depends upon the fabric support. For example, a TCP allocation might consist of a comma-delimited string of socket ranges such as "32000-32100, 33005, 38123-38146". Additional array entries will consist of any provided resource request directives, along with their assigned values. Examples include: pmix_alloc_fabric_type - the type of resources provided; pmix_alloc_fabric_plane - if applicable, what plane the resources were assigned from; pmix_alloc_gandwidth ; pmix_alloc_bandwidth ; pmix_alloc_fabric_sec_key - a security key for the requested fabric allocation. NOTE: the array contents may differ from those requested, especially if pmix_info_requested , was not set in the request.
)) 7	PMIX_ALLOG FARRIC CEC VEY "main allog accel" (pmin but a chiest t)

1	Request that the allocation include a fabric security key for the spawned job.
2	<pre>PMIX_ALLOC_FABRIC_TYPE "pmix.alloc.nettype" (char*)</pre>
4 5	PMIX_ALLOC_FABRIC_PLANE "pmix.alloc.netplane" (char*) ID string for the fabric plane to be used for the requested allocation.
6 7	PMIX_ALLOC_FABRIC_ENDPTS "pmix.alloc.endpts" (size_t) Number of endpoints to allocate per <i>process</i> in the job.
8 9	PMIX_ALLOC_FABRIC_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t) Number of endpoints to allocate per <i>node</i> for the job.
0 1 2	PMIX_PROC_MAP "pmix.pmap" (char*) Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
3 4 5	PMIX_NODE_MAP "pmix.nmap" (char*) Regular expression of nodes currently hosting processes in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the <i>job</i> realm.
	▼ Optional Attributes
6	PMIx libraries that support this operation may support the following:
7 8 9	PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float) Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.
20 21	<pre>PMIX_ALLOC_FABRIC_QOS "pmix.alloc.netqos" (char*) Fabric quality of service level for the job being requested in an allocation request.</pre>
22 23 24 25 26 27	PMIX_SESSION_INFO "pmix.ssn.info" (bool) Return information regarding the session realm of the target process. In this context, indicates that the information provided in the PMIX_NODE_MAP is for the entire session and not just the indicated namespace. Thus, subsequent calls to this API may omit node-level information - e.g., the library may not need to include information on the devices on each node in a subsequent call.
28 29 30	The following optional attributes may be provided by the host environment to identify the programming model (as specified by the user) being executed within the application. The PMIx server library may utilize this information to harvest/forward model-specific environmental variables, record the programming model associated with the application, etc.
32 33	• PMIX_PROGRAMMING_MODEL "pmix.pgm.model" (char*) Programming model being initialized (e.g., "MPI" or "OpenMP").
34	• PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)

1 Programming model implementation ID (e.g., "OpenMPI" or "MPICH"). 2 • PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char*) Programming model version string (e.g., "2.1.1"). 3 **Description** 4 5 Provide a function by which the RM can request application-specific setup data (e.g., environmental 6 variables, fabric configuration and security credentials) from supporting PMIx server library subsystems prior to initiating launch of a job. 7 8 This is defined as a non-blocking operation in case contributing subsystems need to perform some potentially time consuming action (e.g., query a remote service) before responding. The returned 9 10 data must be distributed by the host environment and subsequently delivered to the local PMIx server on each node where application processes will execute, prior to initiating execution of those 11 12 processes. Advice to PMIx server hosts Host environments are required to execute this operation prior to launching a job. In addition to 13 supported directives, the *info* array must include a description of the *job* using the 14 PMIX NODE MAP and PMIX PROC MAP attributes. 15 16 Note that the function can be called on a per-application basis if the PMIX_PROC_MAP and 17 PMIX NODE MAP are provided only for the corresponding application (as opposed to the entire job) each time. 18 Advice to PMIx library implementers 19 Support for harvesting of environmental variables and providing of local configuration information by the PMIx implementation is optional. 20 **Server Setup Application Callback Function** 16.2.11.1 22 The PMIx server setup application callback function. Summary 23 Provide a function by which the resource manager can receive application-specific environmental 24 variables and other setup data prior to launch of an application. 25

```
Format
1
   PMIx v2.0
2
               typedef void (*pmix_setup_application_cbfunc_t)(
 3
                                             pmix status t status,
                                             pmix_info_t info[], size_t ninfo,
 4
                                             void *provided_cbdata,
5
                                             pmix_op_cbfunc_t cbfunc, void *cbdata);
6
               IN
                    status
7
                   returned status of the request (pmix status t)
8
9
               IN
                   info
10
                   Array of info structures (array of handles)
               IN
11
12
                   Number of elements in the info array (integer)
13
               IN
                   provided_cbdata
                   Data originally passed to call to PMIx_server_setup_application (memory
14
                   reference)
15
               IN
                   cbfunc
16
                   pmix_op_cbfunc_t function to be called when processing completed (function reference)
17
18
               IN
                    cbdata
19
                   Data to be passed to the cbfunc callback function (memory reference)
               Description
20
               Define a function to be called by the PMIx server library for return of application-specific setup
21
22
               data in response to a request from the host RM. The returned info array is owned by the PMIx
23
               server library and will be free'd when the provided cbfunc is called.
                 Server Setup Application Attributes
    16.2.11.2
              Attributes specifically defined for controlling contents of application setup data.
25 PMIx v3.0
               PMIX SETUP APP ENVARS "pmix.setup.env" (bool)
26
                    Harvest and include relevant environmental variables.
27
               PMIX SETUP APP NONENVARS ""pmix.setup.nenv" (bool)
28
29
                     Include all relevant data other than environmental variables.
30
               PMIX SETUP APP ALL "pmix.setup.all" (bool)
                    Include all relevant data.
31
    16.2.12
                 PMIx Register attributes
               Summary
33
34
               Register host environment attribute support for a function.
```

Format 1 PMIx v4.0 2 pmix status t 3 PMIx Register attributes (char *function, 4 pmix regattr t attrs[], size_t nattrs); 5 6 IN function 7 String name of function (string) 8 IN attrs Array of pmix regattr t describing the supported attributes (handle) 9 10 IN nattrs Number of elements in attrs (size_t) 11 12 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. **Description** 13 14 The PMIx_Register_attributes function is used by the host environment to register with its PMIx server library the attributes it supports for each pmix server module t function. 15 16 The function is the string name of the server module function (e.g., "register events", 17 "validate credential", or "allocate") whose attributes are being registered. See the **pmix regattr** t entry for a description of the *attrs* array elements. 18 19 Note that the host environment can also query the library (using the PMIx Query_info_nb 20 API) for its attribute support both at the server, client, and tool levels once the host has executed 21 **PMIx_server_init** since the server will internally register those values. Advice to PMIx server hosts -22 Host environments are strongly encouraged to register all supported attributes immediately after 23 initializing the library to ensure that user requests are correctly serviced.

Advice to PMIx library implementers -

PMIx implementations are *required* to register all internally supported attributes for each API during initialization of the library (i.e., when the process calls their respective PMIx init function). Specifically, the implementation *must not* register supported attributes upon first call to a given API as this would prevent users from discovering supported attributes prior to first use of an API.

It is the implementation's responsibility to associate registered attributes for a given <code>pmix_server_module_t</code> function with their corresponding user-facing API. Supported attributes *must* be reported to users in terms of their support for user-facing APIs, broken down by the level (see Section 5.4.6) at which the attribute is supported.

Note that attributes can/will be registered on an API for each level. It is *required* that the implementation support user queries for supported attributes on a per-level basis. Duplicate registrations at the *same* level for a function *shall* return an error - however, duplicate registrations at *different* levels *shall* be independently tracked.

16.2.12.1 Attribute registration constants

Constants supporting attribute registration.

PMIX_ERR_REPEAT_ATTR_REGISTRATION The attributes for an identical function have already been registered at the specified level (host, server, or client).

16.2.12.2 Attribute registration structure

The **pmix_regattr_t** structure is used to register attribute support for a PMIx function.

```
PMIx v4.0
            typedef struct pmix_regattr {
19
20
                 char *name;
                 pmix_key_t *string;
21
22
                 pmix_data_type_t type;
23
                 pmix_info_t *info;
                 size t ninfo;
24
25
                 char **description;
26
             } pmix_regattr_t;;
```

Note that in this structure:

- the *name* is the actual name of the attribute e.g., "PMIX MAX PROCS"
- the *string* is the literal string value of the attribute e.g., "pmix.max.size" for the **PMIX_MAX_PROCS** attribute
- type must be a PMIx data type identifying the type of data associated with this attribute.

1

2

3

5

6 7

8

9

10

11

12

14

15

16

17 18

27

28

29 30

- the info array contains machine-usable information regarding the range of accepted values. This may include entries for PMIX_MIN_VALUE, PMIX_MAX_VALUE, PMIX_ENUM_VALUE, or a combination of them. For example, an attribute that supports all positive integers might delineate it by including a pmix_info_t with a key of PMIX_MIN_VALUE, type of PMIX_INT, and value of zero. The lack of an entry for PMIX_MAX_VALUE indicates that there is no ceiling to the range of accepted values.
- ninfo indicates the number of elements in the info array
- The description field consists of a NULL-terminated array of strings describing the attribute, optionally including a human-readable description of the range of accepted values e.g., "ALL POSITIVE INTEGERS", or a comma-delimited list of enum value names. No correlation between the number of entries in the description and the number of elements in the info array is implied or required.

The attribute *name* and *string* fields must be **NULL**-terminated strings composed of standard alphanumeric values supported by common utilities such as *strcmp*.

Although not strictly required, both PMIx library implementers and host environments are strongly encouraged to provide both human-readable and machine-parsable descriptions of supported attributes when registering them.

16.2.12.3 Attribute registration structure descriptive attributes

The following attributes relate to the nature of the values being reported in the **pmix_regattr_t** structures.

```
PMIX MAX VALUE "pmix.descr.maxval" (varies)
```

Used in **pmix_regattr_t** to describe the maximum valid value for the associated attribute.

```
PMIX_MIN_VALUE "pmix.descr.minval" (varies)
```

Used in **pmix_regattr_t** to describe the minimum valid value for the associated attribute.

```
PMIX_ENUM_VALUE "pmix.descr.enum" (char*)
```

Used in **pmix_regattr_t** to describe accepted values for the associated attribute. Numerical values shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values defined by constant names via a typical C-language enum declaration) must be provided as their numerical equivalent.

16.2.12.4 Attribute registration structure support macros

The following macros are provided to support the **pmix_regattr_t** structure.

Initialize the regattr structure

Initialize the **pmix** regattr t fields

PMIx v4.0

		· ·
1		PMIX_REGATTR_CONSTRUCT (m)
		C
2		<pre>IN m Pointer to the structure to be initialized (pointer to pmix_regattr_t)</pre>
4 5		Destruct the regattr structure Destruct the pmix_regattr_t fields, releasing all strings.
	PMIx v4.0	
6		PMIX_REGATTR_DESTRUCT (m)
		C
7 8		<pre>IN m Pointer to the structure to be destructed (pointer to pmix_regattr_t)</pre>
9		Create a regattr array
10		Allocate and initialize an array of pmix_regattr_t structures.
	PMIx v4.0	C
4 4	I WIIX VT.O	DMTV DECAMED CDEAME ()
11		PMIX_REGATTR_CREATE(m, n)
12		INOUT m
13		Address where the pointer to the array of pmix_regattr_t structures shall be stored
14		(handle)
15		IN n
16		Number of structures to be allocated (size_t)
. –		Free a regetty avecy
17 18		Free a regattr array
10		Release an array of pmix_regattr_t structures.
	PMIx v4.0	
19		PMIX_REGATTR_FREE (m, n)
		C
20		INOUT m
21		Pointer to the array of pmix_regattr_t structures (handle)
22		IN n
23		Number of structures in the array (size_t)

```
Load a regattr structure
 1
 2
               Load values into a pmix regattr t structure. The macro can be called multiple times to add as
               many strings as desired to the same structure by passing the same address and a NULL key to the
 3
 4
               macro. Note that the t type value must be given each time.
   PMIx v4.0
 5
               PMIX_REGATTR_LOAD(a, n, k, t, ni, v)
               IN
                     а
 6
 7
                    Pointer to the structure to be loaded (pointer to pmix_proc_t)
 8
               IN
 9
                    String name of the attribute (string)
               IN
10
                    Key value to be loaded (pmix key t)
11
               IN
12
                    Type of data associated with the provided key (pmix data type t)
13
               IN
14
15
                    Number of pmix info t elements to be allocated in info (size t)
16
               IN
17
                    One-line description to be loaded (more can be added separately) (string)
18
               Transfer a regattr to another regattr
               Non-destructively transfer the contents of a pmix_regattr_t structure to another one.
19
   PMIx v4.0
               PMIX_REGATTR_XFER(m, n)
20
               INOUT m
21
22
                    Pointer to the destination pmix_regattr_t structure (handle)
               IN
23
24
                    Pointer to the source pmix_regattr_t structure (handle)
    16.2.13
                  PMIx server setup local support
               Summary
26
               Provide a function by which the local PMIx server can perform any application-specific operations
27
28
               prior to spawning local clients of a given application.
```

1	Format
PMIx v2 2 3 4 5 6	<pre>pmix_status_t PMIx_server_setup_local_support(const pmix_nspace_t nspace,</pre>
7 8 9	IN nspace Namespace (string) IN info
10 11 12 13 14 15	Array of info structures (array of handles) IN ninfo Number of elements in the info array (size_t) IN cbfunc Callback function pmix_op_cbfunc_t. A NULL function reference indicates that the function is to be executed as a blocking operation (function reference) IN cbdata
17 18	Data to be passed to the callback function (memory reference) Returns one of the following:
19 20 21	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
22 23	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
24 25	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
26 27 28 29 30 31	Description Provide a function by which the local PMIx server can perform any application-specific operations prior to spawning local clients of a given application. For example, a fabric library might need to setup the local driver for "instant on" addressing. The data provided in the <i>info</i> array is the data returned to the host RM by the callback function executed as a result of a call to PMIx_server_setup_application .

Advice to PMIx server hosts

Host environments are required to execute this operation prior to starting any local application processes from the specified namespace if information was obtained from a call to **PMIx_server_setup_application**.

Host environments must register the *nspace* using **PMIx_server_register_nspace** prior to calling this API to ensure that all namespace-related information required to support this function is available to the library. This eliminates the need to include any of the registration information in the *info* array passed to this API.

16.2.14 PMIx_server_IOF_deliver

Summary

Provide a function by which the host environment can pass forwarded Input/Output (IO) to the PMIx server library for distribution to its clients.

Format

PMIx v3.0

1

2

4

5

7

9

10 11

12

13 14

15

16

17

18

19

20

21

22

23 24

25 26

27

28

29

30 31

32

33

C

IN source

Pointer to pmix proc t identifying source of the IO (handle)

IN channel

IO channel of the data (pmix_iof_channel_t)

IN bo

Pointer to pmix byte object t containing the payload to be delivered (handle)

IN info

Array of pmix info t metadata describing the data (array of handles)

N ninfo

Number of elements in the *info* array (size_t)

IN cbfunc

Callback function **pmix_op_cbfunc_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned *success* the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Description

Provide a function by which the host environment can pass forwarded IO to the PMIx server library for distribution to its clients. The PMIx server library is responsible for determining which of its clients have actually registered for the provided data and delivering it. The *cbfunc* callback function will be called once the PMIx server library no longer requires access to the provided data.

16.2.15 PMIx_server_collect_inventory

Summary

Collect inventory of resources on a node.

Format

```
PMIx v3.0
```

1 2

3

4

5

6 7

8

9

10

11

12

13

15

16

17

18

19

20

21

22

23

24

25

26

27 28

29

30 31

32

pmix_status_t

pmix_info_cbfunc_t cbfunc,
void *cbdata);

void *cbdata);

IN directives

Array of pmix_info_t directing the request (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function to return collected data (pmix info cbfunc t function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. In the event the function returns an error, the *cbfunc* will not be called.

Description

1

3

5

6 7

8

10

12 13

14

17

18 19

20

21

24

25

26

27

28 29

30

31

32

33

34

Provide a function by which the host environment can request its PMIx server library collect an inventory of local resources. Supported resources depends upon the PMIx implementation, but may include the local node topology and fabric interfaces.

Advice to PMIx server hosts

This is a non-blocking API as it may involve somewhat lengthy operations to obtain the requested information. Inventory collection is expected to be a rare event – at system startup and upon command from a system administrator. Inventory updates are expected to initiate a smaller operation involving only the changed information. For example, replacement of a node would generate an event to notify the scheduler with an inventory update without invoking a global inventory operation.

16.2.16 PMIx_server_deliver_inventory

Summary

Pass collected inventory to the PMIx server library for storage.

Format

```
15 pmix_st
16 PMIx_se
```

PMIx v3.0

```
22 IN info
23 Array
```

Array of **pmix_info_t** containing the inventory (array of handles)

IN ninfo

Number of elements in the *info* array (size_t)

IN directives

Array of **pmix_info_t** directing the request (array of handles)

IN ndirs

Number of elements in the *directives* array (size_t)

IN cbfunc

Callback function **pmix_op_cbfunc_t**. A **NULL** function reference indicates that the function is to be executed as a blocking operation (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

- **PMIX_SUCCESS**, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the library must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

Description

Provide a function by which the host environment can pass inventory information obtained from a node (as a result of a call to <code>PMIx_server_collect_inventory</code>) to the PMIx server library for storage. Inventory data is subsequently used by the PMIx server library for allocations in response to <code>PMIx_server_setup_application</code>, and may be available to the library's host via the <code>PMIx_Get</code> API (depending upon PMIx implementation). The <code>cbfunc</code> callback function will be called once the PMIx server library no longer requires access to the provided data.

6 16.2.17 PMIx_server_generate_locality_string

Summary

Generate a PMIx locality string from a given cpuset.

Format

PMIx v4.0

1 2

3

4

5

6

7

8

9

10

11

12

13 14

15

17 18

19

20

21

22

23

24

25

26 27

28

PMIx_server_generate_locality_string(const pmix_cpuset_t *cpuset,

char **locality);

IN cpuset

Pointer to a pmix_cpuset_t containing the bitmap of assigned PUs (handle)

OUT locality

pmix_status_t

String representation of the PMIx locality corresponding to the input bitmap (char*)

Returns either **PMIX_SUCCESS** indicating that the returned string contains the locality, or an appropriate PMIx error constant.

Description

Provide a function by which the host environment can generate a PMIx locality string for inclusion in the call to PMIx_server_register_nspace. This function shall only be called for local client processes, with the returned locality included in the job-level information (via the PMIX_LOCALITY_STRING attribute) provided to local clients. Local clients can use these strings as input to determine the relative locality of their local peers via the PMIx_Get_relative_locality API.

The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a colon. The remainder of the string shall represent the corresponding locality as expressed by the underlying implementation.

11 16.2.18 PMIx_server_generate_cpuset_string

Summary

Generate a PMIx string representation of the provided cpuset.

Format

PMIx v4.0

IN cpuset

Pointer to a pmix cpuset t containing the bitmap of assigned PUs (handle)

OUT cpuset_string

String representation of the input bitmap (char*)

Returns either **PMIX_SUCCESS** indicating that the returned string contains the representation, or an appropriate PMIx error constant.

Description

Provide a function by which the host environment can generate a string representation of the cpuset bitmap for inclusion in the call to **PMIx_server_register_nspace**. This function shall only be called for local client processes, with the returned string included in the job-level information (via the **PMIX_CPUSET** attribute) provided to local clients. Local clients can use these strings as input to obtain their PU bindings via the **PMIx_Parse_cpuset_string** API.

The function is required to return a string prefixed by the *source* field of the provided *cpuset* followed by a colon. The remainder of the string shall represent the PUs to which the process is bound as expressed by the underlying implementation.

```
16.2.18.1 Cpuset Structure
 2
               The pmix_cpuset_t structure contains a character string identifying the source of the bitmap
 3
               (e.g., "hwloc") and a pointer to the corresponding implementation-specific structure (e.g.,
               hwloc_cpuset_t).
 4
   PMIx v4.0
5
               typedef struct pmix_cpuset {
6
                    char *source;
 7
                    void *bitmap;
8
               } pmix_cpuset_t;
    16.2.18.2 Cpuset support macros
               The following macros support the pmix cpuset t structure.
10
               Initialize the cpuset structure
11
               Initialize the pmix_cpuset_t fields.
12
   PMIx v4.0
13
               PMIX CPUSET CONSTRUCT (m)
               IN
14
15
                    Pointer to the structure to be initialized (pointer to pmix_cpuset_t)
               Destruct the cpuset structure
16
17
               Destruct the pmix_cpuset_t fields.
   PMIx v4.0
               PMIX CPUSET DESTRUCT (m)
18
               IN
19
                    Pointer to the structure to be destructed (pointer to pmix_cpuset_t)
20
21
               Create a couset array
22
               Allocate and initialize a pmix_cpuset_t array.
   PMIx v4.0
23
               PMIX_CPUSET_CREATE (m, n)
               INOUT m
24
                    Address where the pointer to the array of pmix_cpuset_t structures shall be stored
25
                    (handle)
26
               ĺΝ
27
                    n
28
                    Number of structures to be allocated (size_t)
```

```
Release a cpuset array
 1
 2
               Deconstruct and free a pmix cpuset t array.
   PMIx v4.0
 3
               PMIX CPUSET FREE (m, n)
               INOUT m
 4
                    Address the array of pmix cpuset t structures to be released (handle)
 5
               IN
 6
 7
                    Number of structures in the array (size_t)
    16.2.19
                 PMIx server define process set
               Summary
 9
               Define a PMIx process set.
10
               Format
11
   PMIx v4.0
12
               pmix status t
13
               PMIx server define process set(const pmix proc t members[],
14
                                                         size t nmembers,
                                                         char *pset name);
15
               IN
                    members
16
17
                    Pointer to an array of pmix_proc_t containing the identifiers of the processes in the
                    process set (handle)
18
               IN
                    nmembers
19
20
                    Number of elements in members (integer)
               IN
21
                    pset name
22
                    String name of the process set being defined (char*)
               Returns either PMIX_SUCCESS or an appropriate PMIx error constant.
23
24
               Description
               Provide a function by which the host environment can create a process set. The PMIx server shall
25
               alert all local clients of the new process set (including process set name and membership) via the
26
               PMIX PROCESS SET DEFINE event.
27

    Advice to PMIx server hosts -

               The host environment is responsible for ensuring:
28

    consistent knowledge of process set membership across all involved PMIx servers; and

29
30

    that process set names do not conflict with system-assigned namespaces within the scope of the

31
```

16.2.20 PMIx_server_delete_process_set

Summary

2

7

8 9

10

13 14

15

16

18

19

20 21

22

23

24

25

26

27

28

29

30

31

PMIx v4.0

Delete a PMIx process set name

Format

5 pmix_status_t
6 PMIx_server_delete_process_set(char *pset_name);

IN pset name

String name of the process set being deleted (char*)

Returns either **PMIX_SUCCESS** or an appropriate PMIx error constant.

Description

Provide a function by which the host environment can delete a process set name. The PMIx server shall alert all local clients of the process set name being deleted via the

PMIX_PROCESS_SET_DELETE event. Deletion of the name has no impact on the member processes.

Advice to PMIx server hosts -

The host environment is responsible for ensuring consistent knowledge of process set membership across all involved PMIx servers.

16.3 Server Function Pointers

PMIx utilizes a "function-shipping" approach to support for implementing the server-side of the protocol. This method allows RMs to implement the server without being burdened with PMIx internal details. When a request is received from the client, the corresponding server function will be called with the information.

Any functions not supported by the RM can be indicated by a **NULL** for the function pointer. PMIx implementations are required to return a **PMIX_ERR_NOT_SUPPORTED** status to all calls to functions that require host environment support and are not backed by a corresponding server module entry. Host environments may, if they choose, include a function pointer for operations they have not yet implemented and simply return **PMIX_ERR_NOT_SUPPORTED**.

Functions that accept directives (i.e., arrays of <code>pmix_info_t</code> structures) must check any provided directives for those marked as <code>required</code> via the <code>PMIX_INFO_REQD</code> flag. PMIx client and server libraries are required to mark any such directives with the <code>PMIX_INFO_REQD_PROCESSED</code> flag should they have handled the request. Any required directive that has not been marked therefore becomes the responsibility of the host environment. If a required directive that hasn't been

processed by a lower level cannot be supported by the host, then the

PMIX_ERR_NOT_SUPPORTED error constant must be returned. If the directive can be processed
by the host, then the host shall do so and mark the attribute with the

PMIX_INFO_REQD_PROCESSED flag.

The host RM will provide the function pointers in a **pmix_server_module_t** structure passed to **PMIx_server_init**. The module structure and associated function references are defined in this section.

Advice to PMIx server hosts -

For performance purposes, the host server is required to return as quickly as possible from all functions. Execution of the function is thus to be done asynchronously so as to allow the PMIx server support library to handle multiple client requests as quickly and scalably as possible.

All data passed to the host server functions is "owned" by the PMIX server support library and must not be free'd. Data returned by the host server via callback function is owned by the host server, which is free to release it upon return from the callback

16.3.1 pmix_server_module_t Module

Summary

1

2

3

5

6

7

8

9

10

11 12

13

15

16

17

List of function pointers that a PMIx server passes to PMIx_server_init during startup.

Format

```
18
            typedef struct pmix server module 4 0 0 t {
19
                /* vlx interfaces */
20
                pmix server client connected fn t
                                                      client connected;
                                                                          // DEPRECATED
                pmix server client finalized fn t
21
                                                      client finalized;
22
                pmix server abort fn t
                                                      abort:
                pmix_server_fencenb_fn t
23
                                                      fence_nb;
24
                pmix_server_dmodex_req_fn_t
                                                      direct_modex;
25
                pmix_server_publish_fn_t
                                                      publish;
26
                pmix_server_lookup_fn_t
                                                      lookup;
27
                pmix_server_unpublish_fn_t
                                                      unpublish;
                pmix_server_spawn_fn_t
28
                                                      spawn;
29
                pmix_server_connect_fn_t
                                                      connect;
30
                pmix server disconnect fn t
                                                      disconnect;
                pmix_server_register_events_fn_t
31
                                                      register_events;
                pmix_server_deregister_events_fn_t
32
                                                      deregister_events;
33
                pmix_server_listener_fn_t
                                                      listener;
34
                /* v2x interfaces */
35
                pmix server notify event fn t
                                                      notify event;
```

```
1
                pmix_server_query_fn_t
                                                       query;
2
                                                       tool_connected;
                pmix server tool connection fn t
3
                pmix server log fn t
                                                       log;
4
                pmix server alloc fn t
                                                       allocate:
5
                pmix_server_job_control_fn_t
                                                       job control;
6
                pmix server monitor fn t
                                                       monitor;
7
                /* v3x interfaces */
8
                pmix server get cred fn t
                                                       get credential;
9
                pmix server validate cred fn t
                                                       validate credential;
10
                pmix_server_iof_fn_t
                                                       iof_pull;
11
                pmix_server_stdin_fn_t
                                                       push_stdin;
                /* v4x interfaces */
12
13
                pmix server grp fn t
                                                       group;
14
                pmix_server_fabric_fn_t
                                                       fabric;
15
                pmix_server_client_connected2_fn_t
                                                       client_connected2;
            } pmix_server_module_t;
16

    Advice to PMIx server hosts
```

correlate each provided function pointer with the correct member of the

16.3.2 pmix_server_client_connected_fn_t

Summary

time.

Notify the host server that a client connected to this server. This function module entry has been **DEPRECATED** in favor of **pmix server client connected2** fn t.

Note that some PMIx implementations require the use of C99-style designated initializers to clearly

pmix server module t structure as the location/ordering of struct members may change over

17

18 19

20

22

1		Format
	<i>PMIx v1.0</i>	· · · · · · · · · · · · · · · · · · ·
2		<pre>typedef pmix_status_t (*pmix_server_client_connected_fn_t)(</pre>
3		<pre>const pmix_proc_t *proc,</pre>
4		<pre>void* server_object,</pre>
5		pmix_op_cbfunc_t cbfunc,
6		void *cbdata);
		C
7		IN proc
8		pmix_proc_t structure (handle)
9		IN server_object
10		object reference (memory reference)
11		IN cbfunc
12		Callback function pmix_op_cbfunc_t (function reference)
13		IN cbdata
14		Data to be passed to the callback function (memory reference)
15		Returns one of the following:
16		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
17		will be returned in the provided cbfunc. Note that the host must not invoke the callback function
8		prior to returning from the API.
19		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
20		returned <i>success</i> - the <i>cbfunc</i> will not be called
21		• a PMIx error constant indicating either an error in the input or that the request was immediately
22		processed and failed - the <i>cbfunc</i> will not be called
23		Description
24		This function module entry has been DEPRECATED in favor of
25		<pre>pmix_server_client_connected2_fn_t. If both functions are provided, the PMIx</pre>
26		library will ignore this function module entry in favor of its replacement.
27	16.3.3	pmix_server_client_connected2_fn_t
	101010	
28		Summary
29		Notify the host server that a client connected to this server - this version of the original function
30		definition has been extended to include an array of pmix_info_t , thereby allowing the PMIx
31		server library to pass additional information identifying the client to the host environment.

It is possible that only a subset of the clients in a namespace call **PMIx_Init**. The server's **pmix_server_client_connected2_fn_t** implementation should therefore not depend on

35

36

37

by setting pmix server client connected2 fn t to NULL.

1 being called once per rank in a namespace or delay calling the callback function until all ranks have 2 connected. However, the host may rely on the pmix server client connected2 fn t function module entry being called for a given rank prior to any other function module entries 3 4 being executed on behalf of that rank. 16.3.4 pmix_server_client_finalized_fn_t Summary 6 7 Notify the host environment that a client called **PMIx_Finalize**. **Format** PMIx v1.09 typedef pmix_status_t (*pmix_server_client_finalized_fn_t)(const pmix_proc_t *proc, 10 void* server_object, 11 pmix op cbfunc t cbfunc, 12 void *cbdata); 13 14 IN proc pmix_proc_t structure (handle) 15 IN server_object 16 object reference (memory reference) 17 IN cbfunc 18 19 Callback function **pmix_op_cbfunc_t** (function reference) IN 20 cbdata Data to be passed to the callback function (memory reference) 21 22 Returns one of the following: 23 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided cbfunc. Note that the host must not invoke the callback function 24 prior to returning from the API. 25 26 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 27 returned success - the cbfunc will not be called 28 a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called 29

Description

Notify the host environment that a client called **PMIx_Finalize**. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server support library to release the client. The server_object parameter will be the value of the server_object parameter passed to **PMIx_server_register_client** by the host server when registering the connecting client. If provided, an implementation of **pmix_server_client_finalized_fn_t** is only required to call the callback function designated. A host server can choose to not be notified when clients finalize by setting **pmix_server_client_finalized_fn_t** to **NULL**.

Note that the host server is only being informed that the client has called **PMIx_Finalize**. The client might not have exited. If a client exits without calling **PMIx_Finalize**, the server support library will not call the **pmix_server_client_finalized_fn_t** implementation.

Advice to PMIx server hosts

This operation is an opportunity for a host server to update the status of the tasks it manages. It is also a convenient and well defined time to release resources used to support that client.

void *cbdata);

16.3.5 pmix_server_abort_fn_t

Summary

Notify the host environment that a local client called **PMIx_Abort**.

Format

```
PMIx v1.0
```

IN	proc
	<pre>pmix_proc_t structure identifying the process requesting the abort (handle)</pre>
IN	server_object
	object reference (memory reference)
IN	status
	exit status (integer)
IN	msg
	exit status message (string)
IN	procs
	Array of pmix_proc_t structures identifying the processes to be terminated (array of
	handles)
IN	nprocs
	Number of elements in the <i>procs</i> array (integer)
IN	cbfunc
	Callback function <pre>pmix_op_cbfunc_t</pre> (function reference)
IN	cbdata
	Data to be passed to the callback function (memory reference)
Reti	urns one of the following:
	8

- PMIX_SUCCESS, indicating that the request is being processed by the host environment result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.
- PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned *success* the *cbfunc* will not be called
- PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED indicating that the host environment supports this API, but the request includes processes that the host environment cannot abort e.g., if the request is to abort subsets of processes from a namespace, or processes outside of the caller's own namespace, and the host environment does not permit such operations. In this case, none of the specified processes will be terminated the *cbfunc* will not be called
- PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module the *cbfunc* will not be called
- a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed the *cbfunc* will not be called

1 **Description**2 A local client care

3

5

6

7

9

10

11

20

21 22

23

24

25

26 27

28

29

30

31

32

33

34 35

36

PMIx v1.0

A local client called **PMIx_Abort**. Note that the client will be in a blocked state until the host server executes the callback function, thus allowing the PMIx server library to release the client. The array of *procs* indicates which processes are to be terminated. A **NULL** for the *procs* array indicates that all processes in the caller's namespace are to be aborted, including itself - this is the equivalent of passing a **pmix_proc_t** array element containing the caller's namespace and a rank value of **PMIX RANK WILDCARD**.

16.3.6 pmix_server_fencenb_fn_t

Summary

At least one client called either PMIx_Fence or PMIx_Fence nb.

Format

```
12
            typedef pmix status t (*pmix server fencenb fn t)(
13
                                           const pmix proc t procs[],
14
                                           size t nprocs,
                                           const pmix_info_t info[],
15
16
                                           size_t ninfo,
17
                                           char *data, size_t ndata,
18
                                           pmix_modex_cbfunc_t cbfunc,
19
                                           void *cbdata);
                                               C
```

IN procs

Array of pmix_proc_t structures identifying operation participants(array of handles)

IN nprocs

Number of elements in the *procs* array (integer)

IN info

Array of info structures (array of handles)

IN ninfo

Number of elements in the *info* array (integer)

IN data

(string)

IN ndata

(integer)

IN cbfunc

Callback function **pmix** modex cbfunc t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

W	MIX_SUCCESS, indicating that the request is being processed by the host environment - result rill be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function rior to returning from the API.
re	MIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not e called
	PMIx error constant indicating either an error in the input or that the request was immediately rocessed and failed - the <i>cbfunc</i> will not be called
▼ -	
PM	Ix libraries are required to pass any provided attributes to the host environment for processing.
The	following attributes are required to be supported by all host environments:
.	Collect all data posted by the participants using PMIx_Put that has been committed via PMIx_Commit, making the collection locally available to each participant at the end of the operation. By default, this will include all job-level information that was locally generated by PMIx servers unless excluded using the PMIX_COLLECT_GENERATED_JOB_INFO attribute.
▼ -	Optional Attributes
The	following attributes are optional for host environments:
PMI	TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
	Advice to PMIx server hosts
TT	
mar	t environment are required to return PMIX_ERR_NOT_SUPPORTED if passed an attributed ked as PMIX_INFO_REQD that they do not support, even if support for that attribute is onal.
_	

Description

All local clients in the provided array of *procs* called either **PMIx_Fence** or **PMIx_Fence_nb**. In either case, the host server will be called via a non-blocking function to execute the specified operation once all participating local processes have contributed. All processes in the specified *procs* array are required to participate in the **PMIx_Fence/PMIx_Fence_nb** operation. The callback is to be executed once every daemon hosting at least one participant has called the host server's **pmix server fencenb fn t** function.

The provided data is to be collectively shared with all PMIx servers involved in the fence operation, and returned in the modex *cbfunc*. A **NULL** data value indicates that the local processes had no data to contribute.

The array of *info* structs is used to pass user-requested options to the server. This can include directives as to the algorithm to be used to execute the fence operation. The directives are optional unless the **PMIX_INFO_REQD** flag has been set - in such cases, the host RM is required to return an error if the directive cannot be met.

——— Advice to PMIx library implementers -

The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective. Data received from each node must be simply concatenated to form an aggregated unit, as shown in the following example:

```
uint8_t *blob1, *blob2, *total;
size_t sz_blob1, sz_blob2, sz_total;

sz_total = sz_blob1 + sz_blob2;
total = (uint8_t*)malloc(sz_total);
memcpy(total, blob1, sz_blob1);
memcpy(&total[sz_blob1], blob2, sz_blob2);
```

Note that the ordering of the data blobs does not matter. The host is responsible for free'ing the *data* object passed to it by the PMIx server library.

16.3.6.1 Modex Callback Function

```
2
               Summary
 3
               The pmix_modex_cbfunc_t is used by the pmix_server_fencenb_fn_t and
 4
               pmix_server_dmodex_req_fn_t PMIx server operations to return modex Business Card
               Exchange (BCX) data.
 5
   PMIx v1.0
6
               typedef void (*pmix_modex_cbfunc_t)
 7
                     (pmix_status_t status,
8
                     const char *data, size t ndata,
9
                     void *cbdata,
                     pmix_release_cbfunc_t release_fn,
10
                     void *release_cbdata);
11
               IN
12
                    status
13
                    Status associated with the operation (handle)
14
               IN
                    data
15
                    Data to be passed (pointer)
               IN
                    ndata
16
17
                    size of the data (size t)
               IN
                    cbdata
18
                    Callback data passed to original API call (memory reference)
19
20
               IN
                    release fn
                    Callback for releasing data (function pointer)
21
22
               IN
                    release cbdata
23
                    Pointer to be passed to release fn (memory reference)
24
               Description
25
               A callback function that is solely used by PMIx servers, and not clients, to return modex BCX data
               in response to "fence" and "get" operations. The returned blob contains the data collected from
26
27
               each server participating in the operation.
```

16.3.7 pmix_server_dmodex_req_fn_t

Summary

29 30

31

Used by the PMIx server to request its local host contact the PMIx server on the remote node that hosts the specified process to obtain and return a direct modex blob for that process.

1	1.0	Format
	x v1.0	
2		<pre>typedef pmix_status_t (*pmix_server_dmodex_req_fn_t)(</pre>
3		const pmix_proc_t *proc,
4		<pre>const pmix_info_t info[],</pre>
5		size_t ninfo,
6 7		<pre>pmix_modex_cbfunc_t cbfunc,</pre>
1		<pre>void *cbdata);</pre>
8		IN proc
9		<pre>pmix_proc_t structure identifying the process whose data is being requested (handle)</pre>
0		IN info
1		Array of info structures (array of handles)
2		IN ninfo
3		Number of elements in the <i>info</i> array (integer)
4		IN cbfunc
5		Callback function pmix_modex_cbfunc_t (function reference)
6		IN cbdata
7		Data to be passed to the callback function (memory reference)
8		Returns one of the following:
9 !0		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function
21		prior to returning from the API.
22		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
23		request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
24		be called
25		• a PMIx error constant indicating either an error in the input or that the request was immediately
26		processed and failed - the <i>cbfunc</i> will not be called
		Required Attributes
27		PMIx libraries are required to pass any provided attributes to the host environment for processing.
28		All host environments are required to support the following attributes:
29		<pre>PMIX_REQUIRED_KEY "pmix.req.key" (char*)</pre>
30		Identifies a key that must be included in the requested information. If the specified key is not
31		already available, then the PMIx servers are required to delay response to the dmodex
32		request until either the key becomes available or the request times out.

Optional Attributes The following attributes are optional for host environments that support this operation: 1 2 PMIX TIMEOUT "pmix.timeout" (int) 3 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. 5 6 Description 7 Used by the PMIx server to request its local host contact the PMIx server on the remote node that hosts the specified proc to obtain and return any information that process posted via calls to 8 PMIx Put and PMIx Commit. 9 10 The array of *info* structs is used to pass user-requested options to the server. This can include a 11 timeout to preclude an indefinite wait for data that may never become available. The directives are optional unless the mandatory flag has been set - in such cases, the host RM is required to return an 12 error if the directive cannot be met. 13 16.3.7.1 **Dmodex attributes** 14 15 PMIX_REQUIRED_KEY "pmix.req.key" (char*) 16 Identifies a key that must be included in the requested information. If the specified key is not already available, then the PMIx servers are required to delay response to the dmodex 17 request until either the key becomes available or the request times out. 18 pmix_server_publish_fn_t 16.3.8 Summary 20 21 Publish data per the PMIx API specification. **Format** 22 PMIx v1.0 23 typedef pmix_status_t (*pmix_server_publish_fn_t)(

24

25 26

27

28

const pmix_proc_t *proc,
const pmix_info_t info[],

pmix_op_cbfunc_t cbfunc,

size_t ninfo,

void *cbdata);

	_
•	
١.	- 1

1	IN proc
2	<pre>pmix_proc_t structure of the process publishing the data (handle)</pre>
3	IN info
4 5	Array of info structures (array of handles) IN ninfo
6	Number of elements in the <i>info</i> array (integer)
7	IN cbfunc
8	Callback function pmix_op_cbfunc_t (function reference)
9	IN cbdata
10	Data to be passed to the callback function (memory reference)
11	Returns one of the following:
12 13 14	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
15 16	• PMIX_OPERATION_SUCCEEDED , indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
17 18 19	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
20 21	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	Required Attributes
22 23	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:
24 25	<pre>PMIX_USERID "pmix.euid" (uint32_t)</pre>
26	PMIX_GRPID "pmix.egid" (uint32_t)
27	Effective group ID of the connecting process.
28	
29	Host environments that implement this entry point are required to support the following attributes:
30	PMIX_RANGE "pmix.range" (pmix_data_range_t)
31 32	Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.
33	<pre>PMIX_PERSISTENCE "pmix.persist" (pmix_persistence_t)</pre>

Declare how long the datastore shall retain the provided data. The datastore is to delete the 1 2 data upon reaching the persistence criterion. Optional Attributes The following attributes are optional for host environments that support this operation: 3 4 PMIX TIMEOUT "pmix.timeout" (int) 5 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 6 caused by multiple layers (client, server, and host) simultaneously timing the operation. 7 **Description** 8 Publish data per the PMIx_Publish specification. The callback is to be executed upon 9 completion of the operation. The default data range is left to the host environment, but expected to 10 be PMIX_RANGE_SESSION, and the default persistence PMIX_PERSIST_SESSION or their 11 12 equivalent. These values can be specified by including the respective attributed in the *info* array. The persistence indicates how long the server should retain the data. 13 ——— Advice to PMIx server hosts -The host environment is not required to guarantee support for any specific range - i.e., the 14 environment does not need to return an error if the data store doesn't support a specified range so 15 16 long as it is covered by some internally defined range. However, the server must return an error (a) 17 if the key is duplicative within the storage range, and (b) if the server does not allow overwriting of published info by the original publisher - it is left to the discretion of the host environment to allow 18 info-key-based flags to modify this behavior. 19 20 The PMIX_USERID and PMIX_GRPID of the publishing process will be provided to support authorization-based access to published information and must be returned on any subsequent 21 22 lookup request.

16.3.9 pmix_server_lookup_fn_t

Summary

24

25

Lookup published data.

Format 1 PMIx v1.0 2 typedef pmix status t (*pmix server lookup fn t)(const pmix proc t *proc, 3 char **keys, 4 5 const pmix_info_t info[], size_t ninfo, 6 7 pmix_lookup_cbfunc_t cbfunc, 8 void *cbdata); IN 9 proc pmix_proc_t structure of the process seeking the data (handle) 10 IN 11 (array of strings) 12 IN info 13 14 Array of info structures (array of handles) 15 IN ninfo Number of elements in the *info* array (integer) 16 IN cbfunc 17 Callback function **pmix lookup cbfunc t** (function reference) 18 19 IN cbdata Data to be passed to the callback function (memory reference) 20 21 Returns one of the following: • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 22 will be returned in the provided cbfunc. Note that the host must not invoke the callback function 23 24 prior to returning from the API. • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 25 26 returned success - the cbfunc will not be called 27 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the 28 request, even though the function entry was provided in the server module - the cbfunc will not be called 29 30 • a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the cbfunc will not be called 31 Required Attributes 32 PMIx libraries are required to pass any provided attributes to the host environment for processing. 33 In addition, the following attributes are required to be included in the passed *info* array: PMIX_USERID "pmix.euid" (uint32_t) 34 35 Effective user ID of the connecting process.

PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process. Host environments that implement this entry point are required to support the following attributes: PMIX RANGE "pmix.range" (pmix data range t) Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it. PMIX_WAIT "pmix.wait" (int) Caller requests that the PMIx server wait until at least the specified number of values are found (a value of zero indicates all and is the default). Optional Attributes The following attributes are optional for host environments that support this operation: PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the **PMIX_ERR_TIMEOUT** error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation. Description Lookup published data. The host server will be passed a **NULL**-terminated array of string keys identifying the data being requested. The array of *info* structs is used to pass user-requested options to the server. The default data range is left to the host environment, but expected to be PMIX RANGE SESSION. This can include a wait flag to indicate that the server should wait for all data to become available before executing the callback function, or should immediately callback with whatever data is available. In addition, a timeout can be specified on the wait to preclude an indefinite wait for data that may never be published. Advice to PMIx server hosts -The PMIX_USERID and PMIX_GRPID of the requesting process will be provided to support authorization-based access to published information. The host environment is not required to guarantee support for any specific range - i.e., the environment does not need to return an error if the data store doesn't support a specified range so long as it is covered by some internally defined range.

1

2

4 5

6

7

8

9

10

11 12

13

14

15

16 17

18 19

20

21

22

23

24

25

26 27

28

1 16.3.10 pmix_server_unpublish_fn_t

2 3		Summary Delete data from the data store.
4		Format
	PMIx v1.0	
5 6 7 8 9 10		<pre>typedef pmix_status_t (*pmix_server_unpublish_fn_t)(</pre>
12 13 14 15 16 17 18 19 20 21 22 23		<pre>IN proc pmix_proc_t structure identifying the process making the request (handle) IN keys</pre>
25 26 27		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
28 29		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
30 31 32		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
33 34		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called

Required Attributes PMIx libraries are required to pass any provided attributes to the host environment for processing. 1 In addition, the following attributes are required to be included in the passed *info* array: 2 3 PMIX USERID "pmix.euid" (uint32 t) Effective user ID of the connecting process. 5 PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process. 6 7 Host environments that implement this entry point are required to support the following attributes: 8 9 PMIX RANGE "pmix.range" (pmix data range t) 10 Define constraints on the processes that can access the provided data. Only processes that 11 meet the constraints are allowed to access it. Optional Attributes 12 The following attributes are optional for host environments that support this operation: 13 PMIX TIMEOUT "pmix.timeout" (int) 14 Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 15 caused by multiple layers (client, server, and host) simultaneously timing the operation. 16 Description 17 18 Delete data from the data store. The host server will be passed a **NULL**-terminated array of string keys, plus potential directives such as the data range within which the keys should be deleted. The 19 20 default data range is left to the host environment, but expected to be PMIX RANGE SESSION. The callback is to be executed upon completion of the delete procedure. 21 Advice to PMIx server hosts -The PMIX_USERID and PMIX_GRPID of the requesting process will be provided to support 22 authorization-based access to published information. The host environment is not required to 23 24 guarantee support for any specific range - i.e., the environment does not need to return an error if

the data store doesn't support a specified range so long as it is covered by some internally defined

25

26

range.

16.3.11 pmix_server_spawn_fn_t

Summary 2 3 Spawn a set of applications/processes as per the **PMIx** Spawn API. Format PMIx v1.0 5 typedef pmix status t (*pmix server spawn fn t) (const pmix_proc_t *proc, 6 const pmix_info_t job_info[], 7 8 size t ninfo, 9 const pmix app t apps[], 10 size t napps, pmix spawn cbfunc t cbfunc, 11 12 void *cbdata); IN 13 proc pmix_proc_t structure of the process making the request (handle) 14 15 IN job info 16 Array of info structures (array of handles) 17 IN ninfo Number of elements in the *jobinfo* array (integer) 18 IN 19 apps 20 Array of **pmix** app t structures (array of handles) 21 IN napps Number of elements in the *apps* array (integer) 22 23 IN cbfunc 24 Callback function pmix spawn cbfunc t (function reference) IN 25 cbdata 26 Data to be passed to the callback function (memory reference) 27 Returns one of the following: 28 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 29 will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API. 30 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 31 32 returned success - the cbfunc will not be called 33 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the cbfunc will not 34 35 be called

• a PMIx error constant indicating either an error in the input or that the request was immediately 1 2 processed and failed - the cbfunc will not be called Required Attributes PMIx server libraries are required to pass any provided attributes to the host environment for 3 processing. In addition, the following attributes are required to be included in the passed *info* array: 4 5 PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process. 6 PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process. 8 9 PMIX_SPAWNED "pmix.spawned" (bool) true if this process resulted from a call to PMIx_Spawn. Lack of inclusion (i.e., a return 10 status of PMIX ERR NOT FOUND) corresponds to a value of false for this attribute. 11 12 PMIX_PARENT_ID "pmix.parent" (pmix_proc_t) Process identifier of the parent process of the specified process - typically used to identify 13 14 the application process that caused the job containing the specified process to be spawned (e.g., the process that called **PMIx_Spawn**). 15 16 PMIX_REQUESTOR_IS_TOOL "pmix.req.tool" (bool) The requesting process is a PMIx tool. 17 PMIX_REQUESTOR_IS_CLIENT "pmix.req.client" (bool) 18 The requesting process is a PMIx client. 19 20 21 Host environments that provide this module entry point are required to pass the PMIX_SPAWNED 22 and PMIX_PARENT_ID attributes to all PMIx servers launching new child processes so those 23 values can be returned to clients upon connection to the PMIx server. In addition, they are required 24 to support the following attributes when present in either the job_info or the info array of an element of the apps array: 25 PMIX_WDIR "pmix.wdir" (char*) 26 Working directory for spawned processes. 27 PMIX_SET_SESSION_CWD "pmix.ssncwd" (bool) 28 Set the current working directory to the session working directory assigned by the RM - can 29 be assigned to the entire job (by including attribute in the job_info array) or on a 30 31 per-application basis in the *info* array for each pmix app t. PMIX_PREFIX "pmix.prefix" (char*) 32 Prefix to use for starting spawned processes - i.e., the directory where the executables can be 33 found. 34 PMIX HOST "pmix.host" (char*) 35

1	Comma-delimited list of hosts to use for spawned processes.
2	PMIX_HOSTFILE "pmix.hostfile" (char*) Hostfile to use for spawned processes.
	▼ Optional Attributes
4	The following attributes are optional for host environments that support this operation:
5 6	PMIX_ADD_HOSTFILE "pmix.addhostfile" (char*) Hostfile containing hosts to add to existing allocation.
7 8	PMIX_ADD_HOST "pmix.addhost" (char*) Comma-delimited list of hosts to add to the allocation.
9 10	PMIX_PRELOAD_BIN "pmix.preloadbin" (bool) Preload executables onto nodes prior to executing launch procedure.
11 12	<pre>PMIX_PRELOAD_FILES "pmix.preloadfiles" (char*) Comma-delimited list of files to pre-position on nodes prior to executing launch procedure.</pre>
13 14 15	<pre>PMIX_PERSONALITY "pmix.pers" (char*) Name of personality corresponding to programming model used by application - supported values depend upon PMIx implementation.</pre>
16 17	PMIX_DISPLAY_MAP "pmix.dispmap" (bool) Display process mapping upon spawn.
18 19	PMIX_PPR "pmix.ppr" (char*) Number of processes to spawn on each identified resource.
20 21 22 23	<pre>PMIX_MAPBY "pmix.mapby" (char*) Process mapping policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping policy used for the provided namespace. Supported values are launcher specific.</pre>
24 25 26 27	<pre>PMIX_RANKBY "pmix.rankby" (char*) Process ranking policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the ranking algorithm used for the provided namespace. Supported values are launcher specific.</pre>
28 29 30 31	PMIX_BINDTO "pmix.bindto" (char*) Process binding policy - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the binding policy used for the provided namespace. Supported values are launcher specific.
32 33	PMIX_STDIN_TGT "pmix.stdin" (uint32_t) Spawned process rank that is to receive any forwarded stdin.
34	<pre>PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)</pre>

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the Intermediate Launcher (IL) retain the ability to forward the information to the designated targets.

PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_DEBUGGER_DAEMONS "pmix.debugger" (bool)

Included in the <code>pmix_info_t</code> array of a <code>pmix_app_t</code>, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole <code>pmix_app_t</code> in a <code>PMIx_Spawn</code> request, then the <code>PMIX_DEBUG_TARGET</code> attribute must also be provided (in either the <code>job_info</code> or in the <code>info</code> array of the <code>pmix_app_t</code>) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> nor <code>PMIX_DEBUG_DAEMONS_PER_NODE</code> is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

PMIX TAG OUTPUT "pmix.tagout" (bool)

Tag **stdout/stderr** with the identity of the source process - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX TIMESTAMP OUTPUT "pmix.tsout" (bool)

Timestamp output - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX_MERGE_STDERR_STDOUT "pmix.mergeerrout" (bool)

Merge **stdout** and **stderr** streams - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

PMIX_OUTPUT_TO_FILE "pmix.outfile" (char*)

Direct output (both stdout and stderr) into files of form "**<filename>.rank**" - can be assigned to the entire job (by including attribute in the *job_info* array) or on a per-application basis in the *info* array for each **pmix_app_t**.

1 2	PMIX_INDEX_ARGV "pmix.indxargv" (bool) Mark the argv with the rank of the process.
3 4 5 6	PMIX_CPUS_PER_PROC "pmix.cpuperproc" (uint32_t) Number of PUs to assign to each rank - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PUs/process assigned to the provided namespace.
7 8	PMIX_NO_PROCS_ON_HEAD "pmix.nolocal" (bool) Do not place processes on the head node.
9 0 1	<pre>PMIX_NO_OVERSUBSCRIBE "pmix.noover" (bool) Do not oversubscribe the nodes - i.e., do not place more processes than allocated slots on a node.</pre>
2 3	PMIX_REPORT_BINDINGS "pmix.repbind" (bool) Report bindings of the individual processes.
4 5 6 7	<pre>PMIX_CPU_LIST "pmix.cpulist" (char*) List of PUs to use for this job - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the PU list used for the provided namespace.</pre>
8 9	PMIX_JOB_RECOVERABLE "pmix.recover" (bool) Application supports recoverable operations.
20 21	PMIX_JOB_CONTINUOUS "pmix.continuous" (bool) Application is continuous, all failed processes should be immediately restarted.
22 23 24 25	<pre>PMIX_MAX_RESTARTS "pmix.maxrestarts" (uint32_t) Maximum number of times to restart a process - when accessed using PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the max restarts for the provided namespace.</pre>
26 27 28 29	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description 1 2 Spawn a set of applications/processes as per the **PMIx** Spawn API. Note that applications are not 3 required to be MPI or any other programming model. Thus, the host server cannot make any 4 assumptions as to their required support. The callback function is to be executed once all processes 5 have been started. An error in starting any application or process in this request shall cause all 6 applications and processes in the request to be terminated, and an error returned to the originating 7 caller. 8 Note that a timeout can be specified in the job info array to indicate that failure to start the 9 requested job within the given time should result in termination to avoid hangs. 16.3.11.1 Server spawn attributes 10 11 PMIX_REQUESTOR_IS_TOOL "pmix.req.tool" (bool) 12 The requesting process is a PMIx tool. 13 PMIX REQUESTOR IS CLIENT "pmix.req.client" (bool) 14 The requesting process is a PMIx client. 16.3.12 pmix server connect fn t 15 Summary 16 Record the specified processes as *connected*. 17 **Format** 18 PMIx v1.0 typedef pmix_status_t (*pmix_server_connect_fn_t)(19 20 const pmix_proc_t procs[], 21 size_t nprocs, 22 const pmix info t info[], size t ninfo, 23 24 pmix op cbfunc t cbfunc, 25 void *cbdata); IN 26 procs Array of pmix_proc_t structures identifying participants (array of handles) 27 IN 28 nprocs Number of elements in the *procs* array (integer) 29 IN info 30 Array of info structures (array of handles) 31 32 IN ninfo Number of elements in the *info* array (integer) 33

Callback function **pmix_op_cbfunc_t** (function reference)

ĪΝ

34

35

cbfunc

1 2	IN cbdata Data to be passed to the callback function (memory reference)
3	Returns one of the following:
4 5 6	• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
7 8	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
9 0 1	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
2	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼
4	PMIx libraries are required to pass any provided attributes to the host environment for processing.
	▼ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7 8 9	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.

Description

1

3

4

5

6 7

8

10

13

Record the processes specified by the *procs* array as *connected* as per the PMIx definition. The callback is to be executed once every daemon hosting at least one participant has called the host server's **pmix_server_connect_fn_t** function, and the host environment has completed any supporting operations required to meet the terms of the PMIx definition of *connected* processes.

- Advice to PMIx library implementers

The PMIx server library is required to aggregate participation by local clients, passing the request to the host environment once all local participants have executed the API.

Advice to PMIx server hosts

The host will receive a single call for each collective operation. It is the responsibility of the host to identify the nodes containing participating processes, execute the collective across all participating nodes, and notify the local PMIx server library upon completion of the global collective.

11 16.3.13 pmix_server_disconnect_fn_t

12 Summary

Disconnect a previously connected set of processes.

1		Format		
	<i>PMIx v1.0</i>	▼		
2		<pre>typedef pmix_status_t (*pmix_server_disconnect_fn_t)(</pre>		
3		<pre>const pmix_proc_t procs[],</pre>		
4		size_t nprocs,		
5		<pre>const pmix_info_t info[],</pre>		
6		size_t ninfo,		
7		<pre>pmix_op_cbfunc_t cbfunc,</pre>		
8		<pre>void *cbdata);</pre>		
		C		
9		IN procs		
0		Array of pmix_proc_t structures identifying participants (array of handles)		
11		IN nprocs		
12		Number of elements in the <i>procs</i> array (integer)		
13		IN info		
14		Array of info structures (array of handles)		
15		IN ninfo		
16		Number of elements in the <i>info</i> array (integer)		
17		IN cbfunc		
8		Callback function <pre>pmix_op_cbfunc_t</pre> (function reference)		
19		IN cbdata		
20		Data to be passed to the callback function (memory reference)		
21		Returns one of the following:		
22		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result		
23		will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function		
24		prior to returning from the API.		
25		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and		
26		returned <i>success</i> - the <i>cbfunc</i> will not be called		
27		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the		
28		request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not		
29		be called		
30		• a PMIx error constant indicating either an error in the input or that the request was immediately		
31		processed and failed - the <i>cbfunc</i> will not be called		
		Required Attributes		
32		PMIx libraries are required to pass any provided attributes to the host environment for processing.		

	▼ Optional Attributes
1	The following attributes are optional for host environments that support this operation:
2 3 4 5	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
6	Description
7	Disconnect a previously connected set of processes. The callback is to be executed once every
8	daemon hosting at least one participant has called the host server's has called the
9	<pre>pmix_server_disconnect_fn_t function, and the host environment has completed any</pre>
0	required supporting operations.
	Advice to PMIx library implementers —
1	The PMIx server library is required to aggregate participation by local clients, passing the request
2	to the host environment once all local participants have executed the API.
	Advice to PMIx server hosts
3	The host will receive a single call for each collective operation. It is the responsibility of the host to
4	identify the nodes containing participating processes, execute the collective across all participating
5	nodes, and notify the local PMIx server library upon completion of the global collective.
6	A PMIX_ERR_INVALID_OPERATION error must be returned if the specified set of procs was
7	not previously <i>connected</i> via a call to the pmix_server_connect_fn_t function.

18 16.3.14 pmix_server_register_events_fn_t

Summary

19 20

Register to receive notifications for the specified events.

1		Format
	<i>PMIx v1.0</i>	
2		<pre>typedef pmix_status_t (*pmix_server_register_events_fn_t)(</pre>
3		<pre>pmix_status_t *codes,</pre>
4		size_t ncodes,
5		<pre>const pmix_info_t info[],</pre>
6		size_t ninfo,
7		<pre>pmix_op_cbfunc_t cbfunc,</pre>
8		<pre>void *cbdata);</pre>
		C
9		IN codes
10		Array of pmix_status_t values (array of handles)
11		IN ncodes
12		Number of elements in the <i>codes</i> array (integer)
13		IN info
14		Array of info structures (array of handles)
15		IN ninfo
16		Number of elements in the <i>info</i> array (integer)
17		IN cbfunc
18		Callback function pmix_op_cbfunc_t (function reference)
19		IN cbdata
20		Data to be passed to the callback function (memory reference)
21		Returns one of the following:
22		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
23		will be returned in the provided cbfunc. Note that the host must not invoke the callback function
24		prior to returning from the API.
25		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
26		returned <i>success</i> - the <i>cbfunc</i> will not be called
27		
27 28		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
20 29		be called
30		• a PMIx error constant indicating either an error in the input or that the request was immediately
31		processed and failed - the <i>cbfunc</i> will not be called
		▼ Required Attributes
32		PMIx libraries are required to pass any provided attributes to the host environment for processing.
33		In addition, the following attributes are required to be included in the passed <i>info</i> array:
34		PMIX_USERID "pmix.euid" (uint32_t)
35		Effective user ID of the connecting process.

1 2	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
3 4 5	Description Register to receive notifications for the specified status codes. The <i>info</i> array included in this API is reserved for possible future directives to further steer notification. Advice to PMIx library implementers
6 7	The PMIx server library must track all client registrations for subsequent notification. This module function shall only be called when:
8 9 0	 the client has requested notification of an environmental code (i.e., a PMIx codes in the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER, inclusive) or codes that lies outside the defined PMIx range of constants; and
1 2	• the PMIx server library has not previously requested notification of that code - i.e., the host environment is to be contacted only once a given unique code value
	Advice to PMIx server hosts
3 4 5 6	The host environment is required to pass to its PMIx server library all non-environmental events that directly relate to a registered namespace without the PMIx server library explicitly requesting them. Environmental events are to be translated to their nearest PMIx equivalent code as defined in the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER (inclusive).

17 16.3.15 pmix_server_deregister_events_fn_t

Summary

18

19

Deregister to receive notifications for the specified events.

1	PMIx v1.0	Format
2 3 4 5 6	T WIX VI.O	<pre>typedef pmix_status_t (*pmix_server_deregister_events_fn_t)(</pre>
		C
7 8		IN codes Array of pmix_status_t values (array of handles)
9		IN ncodes Number of elements in the <i>codes</i> array (integer)
1 2 3 4		IN cbfunc Callback function pmix_op_cbfunc_t (function reference) IN cbdata Data to be passed to the callback function (memory reference)
15		Returns one of the following:
16 17 18		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function prior to returning from the API.
19 20		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
21 22 23		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
24 25		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
26 27 28		Description Deregister to receive notifications for the specified events to which the PMIx server has previously registered.
		Advice to PMIx library implementers —
29 30		The PMIx server library must track all client registrations. This module function shall only be called when:
31 32 33		• the library is deregistering environmental codes (i.e., a PMIx codes in the range between PMIX_EVENT_SYS_BASE and PMIX_EVENT_SYS_OTHER, inclusive) or codes that lies outside the defined PMIx range of constants; and

 no client (including the server library itself) remains registered for notifications on any included code - i.e., a code should be included in this call only when no registered notifications against it remain.

16.3.16 pmix_server_notify_event_fn_t

Summary

Notify the specified processes of an event.

```
Format
```

```
PMIx v2.0
```

1

3

5

6

8

16

17

18 19

20

21

22

23

24

25 26

27

28

29

30 31

32

33

34

typedef pmix_status_t (*pmix_server_notify_event_fn_t)(

pmix_status_t code,
const pmix_proc_t *source,
pmix_data_range_t range,
pmix_info_t info[],
size_t ninfo,
pmix_op_cbfunc_t cbfunc,
void *cbdata);

IN code

The **pmix_status_t** event code being referenced structure (handle)

IN source

pmix_proc_t of process that generated the event (handle)

IN range

pmix_data_range_t range over which the event is to be distributed (handle)

IN info

Optional array of **pmix_info_t** structures containing additional information on the event (array of handles)

C

IN ninfo

Number of elements in the *info* array (integer)

IN cbfunc

Callback function **pmix_op_cbfunc_t** (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following:

• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function prior to returning from the API.

• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and 1 returned success - the cbfunc will not be called 2 3 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the 4 request, even though the function entry was provided in the server module - the cbfunc will not be called 5 • a PMIx error constant indicating either an error in the input or that the request was immediately 6 processed and failed - the cbfunc will not be called 7 Required Attributes PMIx libraries are required to pass any provided attributes to the host environment for processing. 8 Host environments that provide this module entry point are required to support the following 9 attributes: 10 PMIX_RANGE "pmix.range" (pmix_data_range_t) 11 Define constraints on the processes that can access the provided data. Only processes that 12 meet the constraints are allowed to access it. 13 **Description** 14 15 Notify the specified processes (described through a combination of range and attributes provided in the *info* array) of an event generated either by the PMIx server itself or by one of its local clients. 16 The process generating the event is provided in the source parameter, and any further descriptive 17 18 information is included in the info array. Note that the PMIx server library is not allowed to echo any event given to it by its host via the 19 PMIx Notify event API back to the host through the 20 pmix_server_notify_event_fn_t server module function. 21 Advice to PMIx server hosts — 22 The callback function is to be executed once the host environment no longer requires that the PMIx 23 server library maintain the provided data structures. It does not necessarily indicate that the event 24 has been delivered to any process, nor that the event has been distributed for delivery

16.3.17 pmix_server_listener_fn_t

Summary

Register a socket the host server can monitor for connection requests.

26

Format 1 PMIx v1.0 2 typedef pmix_status_t (*pmix_server_listener_fn_t)(3 int listening sd, pmix connection obfunc t obfunc, 4 void *cbdata); 5 IN incoming sd 6 7 (integer) 8 IN cbfunc 9 Callback function pmix connection cbfunc t (function reference) IN 10 cbdata (memory reference) 11 Returns PMIX_SUCCESS indicating that the request is accepted, or a negative value corresponding 12 to a PMIx error constant indicating that the request has been rejected. 13 Description 14 Register a socket the host environment can monitor for connection requests, harvest them, and then 15 16 call the PMIx server library's internal callback function for further processing. A listener thread is 17 essential to efficiently harvesting connection requests from large numbers of local clients such as occur when running on large SMPs. The host server listener is required to call accept on the 18 incoming connection request, and then pass the resulting socket to the provided cbfunc. A NULL 19 for this function will cause the internal PMIx server to spawn its own listener thread. 20 **PMIx Client Connection Callback Function** 16.3.17.1 21 22 Summary Callback function for incoming connection request from a local client. 23 Format 24 PMIx v1.025 typedef void (*pmix_connection_cbfunc_t)(26 int incoming sd, void *cbdata); 27 IN incoming_sd (integer) 28 IN 29 cbdata (memory reference) 30 31 Description Callback function for incoming connection requests from local clients - only used by host 32

environments that wish to directly handle socket connection requests.

16.3.18 pmix_server_query_fn_t

Summary 2 3 Query information from the resource manager. Format PMIx v2.0 5 typedef pmix status t (*pmix server query fn t) (6 pmix proc t *proct, 7 pmix_query_t *queries, 8 size_t nqueries, 9 pmix info cbfunc t cbfunc, 10 void *cbdata); IN 11 proct 12 pmix proc t structure of the requesting process (handle) IN queries 13 14 Array of **pmix query t** structures (array of handles) 15 IN nqueries Number of elements in the *queries* array (integer) 16 IN 17 cbfunc Callback function pmix_info_cbfunc_t (function reference) 18 19 IN cbdata Data to be passed to the callback function (memory reference) 20 21 Returns one of the following: 22 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 23 will be returned in the provided *cbfunc*. Note that the host must not invoke the callback function 24 prior to returning from the API. 25 • PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned *success* - the *cbfunc* will not be called 26 27 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the 28 request, even though the function entry was provided in the server module - the cbfunc will not be called 29 30 • a PMIx error constant indicating either an error in the input or that the request was immediately 31 processed and failed - the *cbfunc* will not be called

	▼ Required Attributes
1 2	PMIx libraries are required to pass any provided attributes to the host environment for processing. In addition, the following attributes are required to be included in the passed <i>info</i> array:
3 4	PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
5 6	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
	✓ Optional Attributes
7	The following attributes are optional for host environments that support this operation:
8 9	<pre>PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*) Request a comma-delimited list of active namespaces. NO QUALIFIERS.</pre>
10 11 12	<pre>PMIX_QUERY_JOB_STATUS "pmix.qry.jst" (pmix_status_t) Status of a specified, currently executing job. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose status is being queried.</pre>
13 14	<pre>PMIX_QUERY_QUEUE_LIST "pmix.qry.qlst" (char*) Request a comma-delimited list of scheduler queues. NO QUALIFIERS.</pre>
15 16 17 18	<pre>PMIX_QUERY_QUEUE_STATUS "pmix.qry.qst" (char*) Returns status of a specified scheduler queue, expressed as a string. OPTIONAL QUALIFIERS: PMIX_ALLOC_QUEUE naming specific queue whose status is being requested.</pre>
19 20 21 22	PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
23 24 25 26 27 28 29	PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*) Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.
30 31	PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool) Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.
32 33	PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool) Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.

1 2 3 4	PMIX_QUERY_MEMORY_USAGE "pmix.qry.mem" (bool) Return information on memory usage for the processes indicated in the qualifiers. OPTIONAL QUALIFIERS: PMIX_NSPACE and PMIX_RANK, or PMIX_PROCID of specific process(es) whose memory usage is being requested.
5 6	PMIX_QUERY_LOCAL_ONLY "pmix.qry.local" (bool) Constrain the query to local information only. NO QUALIFIERS.
7 8	PMIX_QUERY_REPORT_AVG "pmix.qry.avg" (bool) Report only average values for sampled information. NO QUALIFIERS.
9 0	PMIX_QUERY_REPORT_MINMAX "pmix.qry.minmax" (bool) Report minimum and maximum values. NO QUALIFIERS.
1 2	<pre>PMIX_QUERY_ALLOC_STATUS "pmix.query.alloc" (char*) String identifier of the allocation whose status is being requested. NO QUALIFIERS.</pre>
3 4 5 6	PMIX_TIME_REMAINING "pmix.time.remaining" (char*) Query number of seconds (uint32_t) remaining in allocation for the specified namespace. OPTIONAL QUALIFIERS: PMIX_NSPACE of the namespace whose info is being requested (defaults to allocation containing the caller).
7 8 9	Description Query information from the host environment. The query will include the namespace/rank of the process that is requesting the info, an array of pmix_query_t describing the request, and a callback function/data for the return. Advice to PMIx library implementers
?1 ?2	The PMIx server library should not block in this function as the host environment may, depending upon the information being requested, require significant time to respond.
o 1621	19 pmix converteel connection for t

Summary

Register that a tool has connected to the server.

```
Format
1
   PMIx v2.0
2
              typedef void (*pmix_server_tool_connection_fn_t)(
 3
                                                    pmix_info_t info[], size_t ninfo,
                                                    pmix tool connection cbfunc t cbfunc,
 4
                                                    void *cbdata);
5
              IN
                   info
6
 7
                   Array of pmix_info_t structures (array of handles)
8
              IN
                  ninfo
9
                   Number of elements in the info array (integer)
              IN
10
                  cbfunc
                   Callback function pmix tool connection cbfunc t (function reference)
11
              IN
12
                  cbdata
                   Data to be passed to the callback function (memory reference)
13
                                              Required Attributes
              PMIx libraries are required to pass the following attributes in the info array:
14
15
              PMIX_USERID "pmix.euid" (uint32_t)
                    Effective user ID of the connecting process.
16
              PMIX_GRPID "pmix.egid" (uint32_t)
17
                    Effective group ID of the connecting process.
18
19
              PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
                    Name of the namespace to use for this tool. This must be included only if the tool already
20
                    has an assigned namespace.
21
              PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)
22
23
                    Rank of this tool. This must be included only if the tool already has an assigned rank.
              PMIX_CREDENTIAL "pmix.cred" (char*)
24
25
                    Security credential assigned to the process.
```

Optional Attributes

The following attributes are optional for host environments that support this operation:

PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX FWD STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIX_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

PMIX VERSION INFO "pmix.version" (char*)

PMIx version of the library being used by the connecting process.

Description

Register that a tool has connected to the server, possibly requesting that the tool be assigned a namespace/rank identifier for further interactions. The <code>pmix_info_t</code> array is used to pass qualifiers for the connection request, including the effective uid and gid of the calling tool for authentication purposes.

If the tool already has an assigned process identifier, then this must be indicated in the *info* array. The host is responsible for checking that the provided namespace does not conflict with any currently known assignments, returning an appropriate error in the callback function if a conflict is found.

The host environment is solely responsible for authenticating and authorizing the connection using whatever means it deems appropriate. If certificates or other authentication information are required, then the tool must provide them. The conclusion of those operations shall be communicated back to the PMIx server library via the callback function.

Approval or rejection of the connection request shall be returned in the *status* parameter of the **pmix_tool_connection_cbfunc_t**. If the connection is refused, the PMIx server library must terminate the connection attempt. The host must not execute the callback function prior to returning from the API.

```
16.3.19.1
                 Tool connection attributes
 2
               Attributes associated with tool connections.
               PMIX USERID "pmix.euid" (uint32 t)
 3
 4
                    Effective user ID of the connecting process.
 5
               PMIX GRPID "pmix.eqid" (uint32 t)
                    Effective group ID of the connecting process.
6
               PMIX_VERSION_INFO "pmix.version" (char*)
 7
8
                    PMIx version of the library being used by the connecting process.
    16.3.19.2
                 PMIx Tool Connection Callback Function
9
               Summary
10
11
               Callback function for incoming tool connections.
               Format
12
   PMIx v2.0
               typedef void (*pmix_tool_connection_cbfunc_t)(
13
14
                                        pmix_status_t status,
                                        pmix_proc_t *proc, void *cbdata);
15
               IN
16
                    status
17
                   pmix status t value (handle)
               IN
18
                  proc
19
                   pmix_proc_t structure containing the identifier assigned to the tool (handle)
20
               IN
                   Data to be passed (memory reference)
21
               Description
22
23
               Callback function for incoming tool connections. The host environment shall provide a
               namespace/rank identifier for the connecting tool.
24
                                         Advice to PMIx server hosts -
25
               It is assumed that rank=0 will be the normal assignment, but allow for the future possibility of a
               parallel set of tools connecting, and thus each process requiring a unique rank.
26
    16.3.20
                 pmix server log fn t
28
               Summary
29
               Log data on behalf of a client.
```

```
Format
1
   PMIx v2.0
2
               typedef void (*pmix_server_log_fn_t)(
 3
                                        const pmix proc t *client,
                                        const pmix info t data[], size t ndata,
4
                                        const pmix_info_t directives[], size_t ndirs,
5
6
                                        pmix_op_cbfunc_t cbfunc, void *cbdata);
               IN
                    client
7
8
                   pmix_proc_t structure (handle)
9
               IN
                   data
                   Array of info structures (array of handles)
10
               IN
11
12
                   Number of elements in the data array (integer)
13
                   directives
14
                   Array of info structures (array of handles)
                  ndirs
15
               IN
                   Number of elements in the directives array (integer)
16
17
               IN
                   cbfunc
18
                   Callback function pmix_op_cbfunc_t (function reference)
19
               IN cbdata
                   Data to be passed to the callback function (memory reference)
20
                                              Required Attributes
21
               PMIx libraries are required to pass any provided attributes to the host environment for processing.
22
               In addition, the following attributes are required to be included in the passed info array:
               PMIX USERID "pmix.euid" (uint32_t)
23
24
                    Effective user ID of the connecting process.
25
               PMIX GRPID "pmix.egid" (uint32 t)
                    Effective group ID of the connecting process.
26
27
28
               Host environments that provide this module entry point are required to support the following
29
               attributes:
30
               PMIX LOG STDERR "pmix.log.stderr" (char*)
31
                    Log string to stderr.
32
               PMIX LOG STDOUT "pmix.log.stdout" (char*)
33
                    Log string to stdout.
34
               PMIX LOG SYSLOG "pmix.log.syslog" (char*)
```

Log data to syslog. Defaults to **ERROR** priority. Will log to global syslog if available, 1 2 otherwise to local syslog. Optional Attributes The following attributes are optional for host environments that support this operation: 3 4 PMIX LOG MSG "pmix.log.msg" (pmix byte object t) Message blob to be sent somewhere. 5 PMIX_LOG_EMAIL "pmix.log.email" (pmix_data_array_t) 6 Log via email based on **pmix_info_t** containing directives. 7 8 PMIX LOG EMAIL ADDR "pmix.log.emaddr" (char*) Comma-delimited list of email addresses that are to receive the message. 9 PMIX_LOG_EMAIL_SUBJECT "pmix.log.emsub" (char*) 10 11 Subject line for email. PMIX_LOG_EMAIL_MSG "pmix.log.emmsg" (char*) 12 Message to be included in email. 13 **Description** 14 Log data on behalf of a client. This function is not intended for output of computational results, but 15 16 rather for reporting status and error messages. The host must not execute the callback function prior to returning from the API. 17 16.3.21 pmix_server_alloc_fn_t 18 19 Summary 20 Request allocation operations on behalf of a client.

1		Foi	rmat
	<i>PMIx v2.0</i>		
2		typ	pedef pmix_status_t (*pmix_server_alloc_fn_t)(
3			<pre>const pmix_proc_t *client,</pre>
4			<pre>pmix_alloc_directive_t directive,</pre>
5			<pre>const pmix_info_t data[],</pre>
6			size_t ndata,
7			<pre>pmix_info_cbfunc_t cbfunc,</pre>
8			<pre>void *cbdata);</pre>
			C
9		IN	client
10			<pre>pmix_proc_t structure of process making request (handle)</pre>
11		IN	directive
12			Specific action being requested (pmix_alloc_directive_t)
13		IN	data
14			Array of info structures (array of handles)
15		IN	ndata
16			Number of elements in the <i>data</i> array (integer)
17		IN	cbfunc
18			Callback function pmix_info_cbfunc_t (function reference)
19		IN	cbdata
20			Data to be passed to the callback function (memory reference)
21		Retu	urns one of the following:
22			MIX_SUCCESS, indicating that the request is being processed by the host environment - result
23 24			fill be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function rior to returning from the API.
		-	
25			MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
26		re	eturned success - the cbfunc will not be called
27		• P	MIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
28		re	equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
29		b	e called
30		• a	PMIx error constant indicating either an error in the input or that the request was immediately
31			rocessed and failed - the <i>cbfunc</i> will not be called
		*	Required Attributes
20		DM (
32 33			Ix libraries are required to pass any provided attributes to the host environment for processing. ddition, the following attributes are required to be included in the passed <i>info</i> array:
J			
34		PMI	X_USERID "pmix.euid" (uint32_t)
35			Effective user ID of the connecting process.

1 2	PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
3	
4 5	Host environments that provide this module entry point are required to support the following attributes:
6 7 8	PMIX_ALLOC_ID "pmix.alloc.id" (char*) A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn.
9 0	<pre>PMIX_ALLOC_NUM_NODES "pmix.alloc.nnodes" (uint64_t) The number of nodes being requested in an allocation request.</pre>
1 2	<pre>PMIX_ALLOC_NUM_CPUS "pmix.alloc.ncpus" (uint64_t) Number of PUs being requested in an allocation request.</pre>
3 4	PMIX_ALLOC_TIME "pmix.alloc.time" (uint32_t) Total session time (in seconds) being requested in an allocation request.
	▼ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7	<pre>PMIX_ALLOC_NODE_LIST "pmix.alloc.nlist" (char*) Regular expression of the specific nodes being requested in an allocation request.</pre>
8 9 !0	<pre>PMIX_ALLOC_NUM_CPU_LIST "pmix.alloc.ncpulist" (char*) Regular expression of the number of PUs for each node being requested in an allocation request.</pre>
?1 ?2	<pre>PMIX_ALLOC_CPU_LIST "pmix.alloc.cpulist" (char*) Regular expression of the specific PUs being requested in an allocation request.</pre>
23 24 25	<pre>PMIX_ALLOC_MEM_SIZE "pmix.alloc.msize" (float) Number of Megabytes[base2] of memory (per process) being requested in an allocation request.</pre>
26 27 28 29	PMIX_ALLOC_FABRIC "pmix.alloc.net" (array) Array of pmix_info_t describing requested fabric resources. This must include at least: PMIX_ALLOC_FABRIC_ID, PMIX_ALLOC_FABRIC_TYPE, and PMIX_ALLOC_FABRIC_ENDPTS, plus whatever other descriptors are desired.
20	DMIV ALLOC FARRIC ID "priv allog notid" (chart)

1	The key to be used when accessing this requested fabric allocation. The fabric allocation
2	will be returned/stored as a pmix_data_array_t of pmix_info_t whose first
3	element is composed of this key and the allocated resource description. The type of the
4	included value depends upon the fabric support. For example, a TCP allocation might
5	consist of a comma-delimited string of socket ranges such as "32000-32100,
6	33005, 38123-38146". Additional array entries will consist of any provided resource
7	request directives, along with their assigned values. Examples include:
8	PMIX_ALLOC_FABRIC_TYPE - the type of resources provided;
9	PMIX_ALLOC_FABRIC_PLANE - if applicable, what plane the resources were assigned
10	from; PMIX_ALLOC_FABRIC_QOS - the assigned QoS; PMIX_ALLOC_BANDWIDTH -
11	the allocated bandwidth; PMIX_ALLOC_FABRIC_SEC_KEY - a security key for the
12	requested fabric allocation. NOTE: the array contents may differ from those requested,
13	especially if PMIX_INFO_REQD was not set in the request.

PMIX_ALLOC_BANDWIDTH "pmix.alloc.bw" (float)

Fabric bandwidth (in Megabits[base2]/sec) for the job being requested in an allocation request.

PMIX ALLOC FABRIC QOS "pmix.alloc.netgos" (char*)

Fabric quality of service level for the job being requested in an allocation request.

Description

Request new allocation or modifications to an existing allocation on behalf of a client. Several broad categories are envisioned, including the ability to:

- Request allocation of additional resources, including memory, bandwidth, and compute for an existing allocation. Any additional allocated resources will be considered as part of the current allocation, and thus will be released at the same time.
- Request a new allocation of resources. Note that the new allocation will be disjoint from (i.e., not affiliated with) the allocation of the requestor - thus the termination of one allocation will not impact the other.
- Extend the reservation on currently allocated resources, subject to scheduling availability and priorities.
- Return no-longer-required resources to the scheduler. This includes the *loan* of resources back to the scheduler with a promise to return them upon subsequent request.

The callback function provides a *status* to indicate whether or not the request was granted, and to provide some information as to the reason for any denial in the pmix info cbfunc t array of pmix_info_t structures.

16.3.22 pmix server job control fn t

Summary

Execute a job control action on behalf of a client.

14

15 16

17

18

19

20

21 22

23

24 25

26 27

28

29

30

31 32

33

34

35

36

I	D144 0 0	го	miai
	PMIx v2.0		
2		ty	<pre>pedef pmix_status_t (*pmix_server_job_control_fn_t)(</pre>
3			<pre>const pmix_proc_t *requestor,</pre>
4			<pre>const pmix_proc_t targets[],</pre>
5			size_t ntargets,
6			<pre>const pmix_info_t directives[],</pre>
7			size_t ndirs,
8			<pre>pmix_info_cbfunc_t cbfunc,</pre>
9			<pre>void *cbdata);</pre>
			C
10		IN	requestor
11			pmix_proc_t structure of requesting process (handle)
12		IN	targets
13			Array of proc structures (array of handles)
14		IN	ntargets
15			Number of elements in the <i>targets</i> array (integer)
16		IN	directives
17		114	Array of info structures (array of handles)
18		IN	ndirs
19		IIN	
		IN	Number of elements in the <i>info</i> array (integer)
20		IIN	
21		IN	Callback function pmix_info_cbfunc_t (function reference)
22		IIN	cbdata
23			Data to be passed to the callback function (memory reference)
24		Ret	urns one of the following:
25			PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
26			will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function
27			orior to returning from the API.
- ′		_	
28		• <u>F</u>	PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
29		r	eturned <i>success</i> - the <i>cbfunc</i> will not be called
30			PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
31			equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
32			be called
		D	to cancer
33		• a	PMIx error constant indicating either an error in the input or that the request was immediately
34		р	processed and failed - the <i>cbfunc</i> will not be called

Required Attributes PMIx libraries are required to pass any attributes provided by the client to the host environment for 1 processing. In addition, the following attributes are required to be included in the passed *info* array: 2 3 PMIX USERID "pmix.euid" (uint32 t) Effective user ID of the connecting process. 4 5 PMIX GRPID "pmix.eqid" (uint32 t) Effective group ID of the connecting process. 6 7 Host environments that provide this module entry point are required to support the following 8 9 attributes: 10 PMIX JOB CTRL ID "pmix.jctrl.id" (char*) 11 Provide a string identifier for this request. The user can provide an identifier for the requested operation, thus allowing them to later request status of the operation or to 12 terminate it. The host, therefore, shall track it with the request for future reference. 13 PMIX JOB CTRL PAUSE "pmix.jctrl.pause" (bool) 14 Pause the specified processes. 15 16 PMIX JOB CTRL RESUME "pmix.jctrl.resume" (bool) Resume ("un-pause") the specified processes. 17 18 PMIX JOB CTRL KILL "pmix.jctrl.kill" (bool) Forcibly terminate the specified processes and cleanup. 19 PMIX_JOB_CTRL_SIGNAL "pmix.jctrl.sig" (int) 20 Send given signal to specified processes. 21 PMIX JOB CTRL TERMINATE "pmix.jctrl.term" (bool) 22 Politely terminate the specified processes. 23 Optional Attributes The following attributes are optional for host environments that support this operation: 24 25 PMIX_JOB_CTRL_CANCEL "pmix.jctrl.cancel" (char*) Cancel the specified request - the provided request ID must match the 26 PMIX JOB_CTRL_ID provided to a previous call to PMIx_Job_control. An ID of 27 **NULL** implies cancel all requests from this requestor. 28 PMIX_JOB_CTRL_RESTART "pmix.jctrl.restart" (char*) 29 Restart the specified processes using the given checkpoint ID. 30 PMIX JOB CTRL CHECKPOINT "pmix.jctrl.ckpt" (char*) 31 Checkpoint the specified processes and assign the given ID to it. 32

```
PMIX_JOB_CTRL_CHECKPOINT_EVENT "pmix.jctrl.ckptev" (bool)
 1
 2
                     Use event notification to trigger a process checkpoint.
 3
               PMIX_JOB_CTRL_CHECKPOINT_SIGNAL "pmix.jctrl.ckptsig" (int)
                     Use the given signal to trigger a process checkpoint.
 4
 5
               PMIX_JOB_CTRL_CHECKPOINT_TIMEOUT "pmix.jctrl.ckptsig" (int)
 6
                     Time in seconds to wait for a checkpoint to complete.
 7
               PMIX JOB CTRL CHECKPOINT METHOD
8
               "pmix.jctrl.ckmethod" (pmix_data_array_t)
9
                     Array of pmix_info_t declaring each method and value supported by this application.
10
               PMIX_JOB_CTRL_PROVISION "pmix.jctrl.pvn" (char*)
11
                     Regular expression identifying nodes that are to be provisioned.
               PMIX_JOB_CTRL_PROVISION_IMAGE "pmix.jctrl.pvnimg" (char*)
12
13
                     Name of the image that is to be provisioned.
               PMIX_JOB_CTRL_PREEMPTIBLE "pmix.jctrl.preempt" (bool)
14
                     Indicate that the job can be pre-empted.
15
               Description
16
17
               Execute a job control action on behalf of a client. The targets array identifies the processes to
               which the requested job control action is to be applied. A NULL value can be used to indicate all
18
19
               processes in the caller's namespace. The use of PMIX RANK WILDCARD can also be used to
               indicate that all processes in the given namespace are to be included.
20
21
               The directives are provided as pmix info t structures in the directives array. The callback
```

function provides a status to indicate whether or not the request was granted, and to provide some

information as to the reason for any denial in the pmix info cbfunc t array of

5 16.3.23 pmix_server_monitor_fn_t

pmix_info_t structures.

Summary

22

23

24

26

27

Request that a client be monitored for activity.

1 DMI::2	Format
PMIx v2	
2	<pre>typedef pmix_status_t (*pmix_server_monitor_fn_t)(</pre>
3 4	<pre>const pmix_proc_t *requestor, const pmix_info_t *monitor,</pre>
5	pmix_status_t error,
6	const pmix_info_t directives[],
7	size_t ndirs,
8	pmix_info_cbfunc_t cbfunc,
9	void *cbdata);
•	C
10	IN requestor
11	pmix_proc_t structure of requesting process (handle)
12	IN monitor
13	<pre>pmix_info_t identifying the type of monitor being requested (handle)</pre>
14	IN error
15	Status code to use in generating event if alarm triggers (integer)
16	IN directives
17	Array of info structures (array of handles)
18	IN ndirs
19	Number of elements in the <i>info</i> array (integer)
20	IN cbfunc
21	Callback function <pre>pmix_info_cbfunc_t</pre> (function reference)
22	IN cbdata
23	Data to be passed to the callback function (memory reference)
24	Returns one of the following:
25 26	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the host must not invoke the callback function
27	prior to returning from the API.
28	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
29	returned <i>success</i> - the <i>cbfunc</i> will not be called
30	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
31	request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
32	be called
33	• a PMIx error constant indicating either an error in the input or that the request was immediately
34	processed and failed - the <i>cbfunc</i> will not be called
35 36	This entry point is only called for monitoring requests that are not directly supported by the PMIx server library itself.

→ Required Attributes	· · · · · · · ·
If supported by the PMIx server library, then the library must not pass any supported attributhe host environment. Any attributes provided by the client that are not directly supported be server library must be passed to the host environment if it provides this module entry. In ad the following attributes are required to be included in the passed <i>info</i> array:	by the
PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.	
PMIX_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.	
Host environments are not required to support any specific monitoring attributes.	
→ Optional Attributes	····
The following attributes may be implemented by a host environment.	
<pre>PMIX_MONITOR_ID "pmix.monitor.id" (char*) Provide a string identifier for this request.</pre>	
<pre>PMIX_MONITOR_CANCEL "pmix.monitor.cancel" (char*) Identifier to be canceled (NULL means cancel all monitoring for this process).</pre>	
PMIX_MONITOR_APP_CONTROL "pmix.monitor.appctrl" (bool) The application desires to control the response to a monitoring event - i.e., the application requesting that the host environment not take immediate action in response to the event terminating the job).	
PMIX_MONITOR_HEARTBEAT "pmix.monitor.mbeat" (void) Register to have the PMIx server monitor the requestor for heartbeats.	
<pre>PMIX_MONITOR_HEARTBEAT_TIME "pmix.monitor.btime" (uint32_t) Time in seconds before declaring heartbeat missed.</pre>	
<pre>PMIX_MONITOR_HEARTBEAT_DROPS "pmix.monitor.bdrop" (uint32_t) Number of heartbeats that can be missed before generating the event.</pre>	
<pre>PMIX_MONITOR_FILE "pmix.monitor.fmon" (char*) Register to monitor file for signs of life.</pre>	
PMIX_MONITOR_FILE_SIZE "pmix.monitor.fsize" (bool) Monitor size of given file is growing to determine if the application is running.	
<pre>PMIX_MONITOR_FILE_ACCESS "pmix.monitor.faccess" (char*) Monitor time since last access of given file to determine if the application is running</pre>	
<pre>PMIX_MONITOR_FILE_MODIFY "pmix.monitor.fmod" (char*) Monitor time since last modified of given file to determine if the application is runni</pre>	ng.

```
PMIX_MONITOR_FILE_CHECK_TIME "pmix.monitor.ftime" (uint32_t)
 1
 2
                     Time in seconds between checking the file.
               PMIX_MONITOR_FILE_DROPS "pmix.monitor.fdrop" (uint32_t)
 3
                     Number of file checks that can be missed before generating the event.
 4
               Description
5
               Request that a client be monitored for activity.
6
    16.3.24
                 pmix server get cred fn t
               Summary
8
9
               Request a credential from the host environment.
               Format
10
   PMIx v3.0
               typedef pmix_status_t (*pmix_server_get_cred_fn_t)(
11
12
                                                     const pmix_proc_t *proc,
                                                     const pmix_info_t directives[],
13
14
                                                     size t ndirs,
15
                                                     pmix credential cbfunc t cbfunc,
16
                                                     void *cbdata);
17
               IN
                    proc
18
                    pmix proc t structure of requesting process (handle)
19
               IN
                    directives
                    Array of info structures (array of handles)
20
21
               IN
                   ndirs
22
                    Number of elements in the info array (integer)
                  cbfunc
23
                    Callback function to return the credential (pmix_credential_cbfunc_t function
24
25
                    reference)
               IN
                    cbdata
26
                    Data to be passed to the callback function (memory reference)
27
               • PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
28
                 will be returned in the provided cbfunc
29
30
               • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the
                 request, even though the function entry was provided in the server module - the cbfunc will not
31
                 be called
32
33
               • a PMIx error constant indicating either an error in the input or that the request was immediately
34
                 processed and failed - the cbfunc will not be called
```

Required Attributes If the PMIx library does not itself provide the requested credential, then it is required to pass any 1 attributes provided by the client to the host environment for processing. In addition, it must include 2 the following attributes in the passed *info* array: 3 PMIX USERID "pmix.euid" (uint32 t) 4 Effective user ID of the connecting process. 5 6 PMIX GRPID "pmix.eqid" (uint32 t) 7 Effective group ID of the connecting process. **Optional Attributes** The following attributes are optional for host environments that support this operation: 8 9 PMIX CRED TYPE "pmix.sec.ctype" (char*) When passed in PMIx_Get_credential, a prioritized, comma-delimited list of desired 10 credential types for use in environments where multiple authentication mechanisms may be 11 available. When returned in a callback function, a string identifier of the credential type. 12 PMIX_TIMEOUT "pmix.timeout" (int) 13 Time in seconds before the specified operation should time out (zero indicating infinite) and 14 return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions 15 16 caused by multiple layers (client, server, and host) simultaneously timing the operation. Description 17 Request a credential from the host environment. 18 16.3.24.1 Credential callback function 19 Summary 20 21 Callback function to return a requested security credential

Format 1 PMIx v3.0 2 typedef void (*pmix_credential_cbfunc_t)(3 pmix status t status, 4 pmix byte object t *credential, pmix_info_t info[], size_t ninfo, 5 6 void *cbdata); IN status 7 8 pmix_status_t value (handle) 9 IN credential pmix_byte_object_t structure containing the security credential (handle) 10 IN 11 Array of provided by the system to pass any additional information about the credential - e.g., 12 the identity of the issuing agent. (handle) 13 14 IN ninfo 15 Number of elements in *info* (size t) IN cbdata 16 Object passed in original request (memory reference) 17 **Description** 18 Define a callback function to return a requested security credential. Information provided by the 19 issuing agent can subsequently be used by the application for a variety of purposes. Examples 20 21 include: • checking identified authorizations to determine what requests/operations are feasible as a means 22 23 to steering workflows • compare the credential type to that of the local SMS for compatibility 24 Advice to users 25 The credential is opaque and therefore understandable only by a service compatible with the issuer. The *info* array is owned by the PMIx library and is not to be released or altered by the receiving 26 27 party.

16.3.25 pmix_server_validate_cred_fn_t

Summary

Request validation of a credential.

28

29

1		Format
Pl	MIx v3.0	<u> </u>
2		<pre>typedef pmix_status_t (*pmix_server_validate_cred_fn_t)(</pre>
3		<pre>const pmix_proc_t *proc,</pre>
4		<pre>const pmix_byte_object_t *cred,</pre>
5		<pre>const pmix_info_t directives[],</pre>
6		size_t ndirs,
7		<pre>pmix_validation_cbfunc_t cbfunc,</pre>
8		<pre>void *cbdata);</pre>
		C
9		IN proc
0		<pre>pmix_proc_t structure of requesting process (handle)</pre>
1		IN cred
2		Pointer to <pre>pmix_byte_object_t</pre> containing the credential (handle)
3		IN directives
4		Array of info structures (array of handles)
5		IN ndirs
6		Number of elements in the <i>info</i> array (integer)
7		IN cbfunc
8		Callback function to return the result (pmix_validation_cbfunc_t function reference)
9		IN cbdata
20		Data to be passed to the callback function (memory reference)
21		Returns one of the following:
22 23		• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i>
24 25		• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
26 27 28		• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
!9 80		• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
		Required Attributes
31 32 33		If the PMIx library does not itself validate the credential, then it is required to pass any attributes provided by the client to the host environment for processing. In addition, it must include the following attributes in the passed <i>info</i> array:
84 85		PMIX_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.

1	<pre>PMIX_GRPID "pmix.egid" (uint32_t)</pre>
2	Effective group ID of the connecting process.
3	
4	Host environments are not required to support any specific attributes.
	▼ Optional Attributes
5	The following attributes are optional for host environments that support this operation:
6 7 8 9	PMIX_TIMEOUT "pmix.timeout" (int) Time in seconds before the specified operation should time out (zero indicating infinite) and return the PMIX_ERR_TIMEOUT error. Care should be taken to avoid race conditions caused by multiple layers (client, server, and host) simultaneously timing the operation.
10	Description
11	Request validation of a credential obtained from the host environment via a prior call to the
12	<pre>pmix_server_get_cred_fn_t module entry.</pre>
12	16.3.26 Credential validation callback function

SummaryCallback function for security credential validation.

Format 1 PMIx v3.0 2 typedef void (*pmix_validation_cbfunc_t)(3 pmix status t status, pmix info t info[], size t ninfo, 4 void *cbdata); 5 IN 6 status 7 pmix_status_t value (handle) 8 IN info 9 Array of pmix info t provided by the system to pass any additional information about the authentication - e.g., the effective userid and group id of the certificate holder, and any related 10 authorizations (handle) 11 IN ninfo 12 Number of elements in *info* (size t) 13 14 IN cbdata Object passed in original request (memory reference) 15 16 The returned status shall be one of the following: 17 • PMIX_SUCCESS, indicating that the request was processed and returned success (i.e., the credential was both valid and any information it contained was successfully processed). Details 18 of the result will be returned in the *info* array 19 • a PMIx error constant indicating either an error in the parsing of the credential or that the request 20 was refused 21 **Description** 22 Define a validation callback function to indicate if a provided credential is valid, and any 23 24 corresponding information regarding authorizations and other security matters. Advice to users 25 The precise contents of the array will depend on the host environment and its associated security 26 system. At the minimum, it is expected (but not required) that the array will contain entries for the 27 **PMIX_USERID** and **PMIX_GRPID** of the client described in the credential. The *info* array is owned by the PMIx library and is not to be released or altered by the receiving party. 28

16.3.27 pmix_server_iof_fn_t

Summary

30 31

Request the specified IO channels be forwarded from the given array of processes.

1	D144 2.0	Fo	rmat C
	PMIx v3.0		0
2		tyr	<pre>pedef pmix_status_t (*pmix_server_iof_fn_t)(</pre>
3			<pre>const pmix_proc_t procs[],</pre>
4			size_t nprocs,
5			<pre>const pmix_info_t directives[],</pre>
6			size_t ndirs,
7			<pre>pmix_iof_channel_t channels,</pre>
8			<pre>pmix_op_cbfunc_t cbfunc, void *cbdata);</pre>
9		IN	procs
10			Array pmix_proc_t identifiers whose IO is being requested (handle)
11		IN	nprocs
12			Number of elements in <i>procs</i> (size_t)
13		IN	directives
14			Array of pmix_info_t structures further defining the request (array of handles)
15		IN	ndirs
16			Number of elements in the <i>info</i> array (integer)
17		IN	channels
18		INI	Bitmask identifying the channels to be forwarded (pmix_iof_channel_t)
19		IN	cbfunc
20		INI	Callback function pmix_op_cbfunc_t (function reference)
21		IN	cbdata
22			Data to be passed to the callback function (memory reference)
23		Ret	urns one of the following:
24		• P	MIX_SUCCESS, indicating that the request is being processed by the host environment - result
25			will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
26			unction prior to returning from the API.
27		• P	MIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
28			eturned success - the cbfunc will not be called
29			MIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
30			equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
31		b	e called
32		• a	PMIx error constant indicating either an error in the input or that the request was immediately
33			processed and failed - the <i>cbfunc</i> will not be called

▼	
The fe	ollowing attributes are required to be included in the passed info array:
PMIX	C_USERID "pmix.euid" (uint32_t) Effective user ID of the connecting process.
РМІХ	E_GRPID "pmix.egid" (uint32_t) Effective group ID of the connecting process.
Host of	environments that provide this module entry point are required to support the following utes:
PMIX	The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
PMIX	In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.
PMIX	In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
▼	Optional Attributes
The fo	ollowing attributes may be supported by a host environment.
PMIX	Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
PMIX	Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive

```
Description
 1
 2
               Request the specified IO channels be forwarded from the given array of processes. An error shall be
               returned in the callback function if the requested service from any of the requested processes cannot
 3
 4
               be provided.

    Advice to PMIx library implementers -

 5
               The forwarding of stdin is a push process - processes cannot request that it be pulled from some
               other source. Requests including the PMIX_FWD_STDIN_CHANNEL channel will return a
 6
 7
               PMIX ERR NOT SUPPORTED error.
                  IOF delivery function
    16.3.27.1
               Summary
 9
               Callback function for delivering forwarded IO to a process.
10
11
               Format
   PMIx v3.0
12
               typedef void (*pmix iof cbfunc t) (
                                          size_t iofhdlr, pmix_iof_channel_t channel,
13
14
                                          pmix proc t *source, char *payload,
15
                                          pmix_info_t info[], size_t ninfo);
               IN
                    iofhdlr
16
17
                    Registration number of the handler being invoked (size_t)
               IN
                    channel
18
                    bitmask identifying the channel the data arrived on (pmix_iof_channel_t)
19
               IN
20
                    source
21
                    Pointer to a pmix proc t identifying the namespace/rank of the process that generated the
22
                    data (char*)
               IN
23
                    payload
                    Pointer to character array containing the data.
24
               IN
25
                    info
26
                    Array of pmix info t provided by the source containing metadata about the payload. This
27
                    could include PMIX IOF COMPLETE (handle)
28
                    ninfo
29
                    Number of elements in info (size_t)
```

Description

1 2

3

8

9

23

24 25

26

27 28

29

30

31

32

33

34

Define a callback function for delivering forwarded IO to a process. This function will be called whenever data becomes available, or a specified buffering size and/or time has been met.

Advice to users

4 Multiple strings may be included in a given payload, and the payload may not be **NULL** terminated. 5 The user is responsible for releasing the payload memory. The info array is owned by the PMIx 6 library and is not to be released or altered by the receiving party.

pmix server stdin fn t 16.3.28

Summary

Pass standard input data to the host environment for transmission to specified recipients.

10 **Format**

```
PMIx v3.0
11
             typedef pmix_status_t (*pmix_server_stdin_fn_t)(
12
                                            const pmix_proc_t *source,
13
                                            const pmix_proc_t targets[],
                                            size_t ntargets,
14
                                            const pmix_info_t directives[],
15
16
                                            size t ndirs,
                                            const pmix_byte_object_t *bo,
17
18
                                            pmix_op_cbfunc_t cbfunc, void *cbdata);
             IN
19
                 source
20
                 pmix_proc_t structure of source process (handle)
21
             IN
                 targets
                 Array of pmix_proc_t target identifiers (handle)
22
```

IN ntargets

Number of elements in the *targets* array (integer)

IN directives

Array of info structures (array of handles)

IN ndirs

Number of elements in the *info* array (integer)

IN

Pointer to pmix byte object t containing the payload (handle)

cbfunc

Callback function pmix_op_cbfunc_t (function reference)

IN cbdata

Data to be passed to the callback function (memory reference)

Returns one of the following: 1 • PMIX SUCCESS, indicating that the request is being processed by the host environment - result 2 will be returned in the provided cbfunc. Note that the library must not invoke the callback 3 4 function prior to returning from the API. 5 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and returned success - the cbfunc will not be called 6 7 • PMIX ERR NOT SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the *cbfunc* will not 8 be called 9 • a PMIx error constant indicating either an error in the input or that the request was immediately 10 processed and failed - the cbfunc will not be called 11 Required Attributes The following attributes are required to be included in the passed *info* array: 12 13 PMIX USERID "pmix.euid" (uint32 t) Effective user ID of the connecting process. 14 15 PMIX GRPID "pmix.eqid" (uint32 t) Effective group ID of the connecting process. 16 **Description** 17 18

Passes stdin to the host environment for transmission to specified recipients. The host environment is responsible for forwarding the data to all locations that host the specified *targets* and delivering the payload to the PMIx server library connected to those clients.

16.3.29 pmix server grp fn t

Summary

Request group operations (construct, destruct, etc.) on behalf of a set of processes.

19

20

22

1	D147 4.0	Fo	rmat C
_	PMIx v4.0		
2		ty	<pre>pedef pmix_status_t (*pmix_server_grp_fn_t)(</pre>
3			<pre>pmix_group_operation_t op,</pre>
4			char grp[],
5			<pre>const pmix_proc_t procs[],</pre>
6 7			size_t nprocs,
8			<pre>const pmix_info_t directives[],</pre>
9			size_t ndirs, pmix_info_cbfunc_t cbfunc,
0			void *cbdata);
Ü			C
1		IN	op
2			<pre>pmix_group_operation_t value indicating operation the host is requested to perform</pre>
3			(integer)
4		IN	grp
5			Character string identifying the group (string)
6		IN	procs
7			Array of pmix_proc_t identifiers of participants (handle)
8		IN	nprocs
9			Number of elements in the <i>procs</i> array (integer)
20		IN	directives
21			Array of info structures (array of handles)
22		IN	ndirs
23			Number of elements in the <i>info</i> array (integer)
24		IN	cbfunc
25			Callback function pmix_info_cbfunc_t (function reference)
26		IN	cbdata
27			Data to be passed to the callback function (memory reference)
28		Ret	urns one of the following:
9		• P	PMIX_SUCCESS, indicating that the request is being processed by the host environment - result
80			vill be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback
1			function prior to returning from the API.
2			PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and
3		re	eturned <i>success</i> - the <i>cbfunc</i> will not be called
4		• P	PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the
5			equest, even though the function entry was provided in the server module - the <i>cbfunc</i> will not
6			e called
37		• 0	PMIx error constant indicating either an error in the input or that the request was immediately
) / !R			processed and failed - the <i>ching</i> will not be called

	A constitution	100
Optional	Attribi	utes

The following attributes may be supported by a host environment.

PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool)

Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, <code>size_t</code> value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to <code>PMIX_RANGE_SESSION</code>.

PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool)

Group operation only involves local processes. PMIx implementations are *required* to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.

PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)

Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool)

Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is **false**.

PMIX_RANGE "pmix.range" (pmix_data_range_t)

Define constraints on the processes that can access the provided data. Only processes that meet the constraints are allowed to access it.

The following attributes may be included in the host's response:

```
PMIX_GROUP_ID "pmix.grp.id" (char*)
```

User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by including some user-specific or application-specific prefix or suffix to the string).

```
PMIX_GROUP_MEMBERSHIP "pmix.grp.mbrs" (pmix_data_array_t*)
```

Array pmix_proc_t identifiers identifying the members of the specified group.

```
PMIX_GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t)
```

Context identifier assigned to the group by the host RM.

```
PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)
```

Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

Description 1 2 Perform the specified operation across the identified processes, plus any special actions included in 3 the directives. Return the result of any special action requests in the callback function when the 4 operation is completed. Actions may include a request (PMIX GROUP ASSIGN CONTEXT ID) 5 that the host assign a unique numerical (size_t) ID to this group - if given, the PMIX_RANGE attribute will specify the range across which the ID must be unique (default to 6 7 PMIX RANGE SESSION). 16.3.29.1 **Group Operation Constants** PMIx v4.0The pmix_group_operation_t structure is a uint8_t value for specifying group operations. All values were originally defined in version 4 of the standard unless otherwise marked. 10 11 PMIX GROUP CONSTRUCT Construct a group composed of the specified processes - used by 12 a PMIx server library to direct host operation. 13 PMIX GROUP DESTRUCT Destruct the specified group - used by a PMIx server library to direct host operation. 14 16.3.30 pmix_server_fabric_fn_t Summary 16 Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process. 17 **Format** 18 PMIx v4.019 typedef pmix_status_t (*pmix_server_fabric_fn_t)(const pmix_proc_t *requestor, 20 pmix_fabric_operation_t op, 21 22 const pmix_info_t directives[], 23 size t ndirs, pmix info cbfunc t cbfunc, 24 25 void *cbdata); IN 26 requestor pmix_proc_t identifying the requestor (handle) 27 IN 28 29 pmix fabric operation t value indicating operation the host is requested to perform (integer) 30 directives 31 32 Array of info structures (array of handles) IN 33 ndirs 34 Number of elements in the *info* array (integer)

1	IN cbfunc
2	Callback function <pre>pmix_info_cbfunc_t</pre> (function reference)
3	IN cbdata
4	Data to be passed to the callback function (memory reference)
5	Returns one of the following:
6 7 8	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library must not invoke the callback function prior to returning from the API.
9 10	• PMIX_OPERATION_SUCCEEDED, indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will not be called
11 12 13	• PMIX_ERR_NOT_SUPPORTED, indicating that the host environment does not support the request, even though the function entry was provided in the server module - the <i>cbfunc</i> will not be called
14 15	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will not be called
	▼ Required Attributes
16 17	The following directives are required to be supported by all hosts to aid users in identifying the fabric and (if applicable) the device to whom the operation references:
18 19	<pre>PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric.</pre>
20 21	<pre>PMIX_FABRIC_IDENTIFIER "pmix.fab.id" (string) An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1).</pre>
22 23 24 25 26	PMIX_FABRIC_PLANE "pmix.fab.plane" (string) ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix_data_array_t of string identifiers for all fabric planes in the overall system.
27 28	PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
29	Description
30	Perform the specified operation. Return the result of any requests in the callback function when the
31 32	operation is completed. Operations may, for example, include a request for fabric information. See <pre>pmix_fabric_t</pre> for a list of expected information to be included in the response. Note that

using the **PMIX_FABRIC_DEVICE_INDEX** attribute.

requests for device index are to be returned in the callback function's array of pmix_info_t

CHAPTER 17

Tools and Debuggers

The term *tool* widely refers to programs executed by the user or system administrator on a command line. Tools frequently interact with either the SMS, user applications, or both to perform administrative and support functions. For example, a debugger tool might be used to remotely control the processes of a parallel application, monitoring their behavior on a step-by-step basis. Historically, such tools were custom-written for each specific host environment due to the customized and/or proprietary nature of the environment's interfaces.

The advent of PMIx offers the possibility for creating portable tools capable of interacting with multiple RMs without modification. Possible use-cases include:

- querying the status of scheduling queues and estimated allocation time for various resource options
- job submission and allocation requests
- querying job status for executing applications
- launching and monitoring applications

Enabling these capabilities requires some extensions to the PMIx Standard (both in terms of APIs and attributes), and utilization of client-side APIs for more tool-oriented purposes.

This chapter defines specific APIs related to tools, provides tool developers with an overview of the support provided by PMIx, and serves to guide RM vendors regarding roles and responsibilities of RMs to support tools. As the number of tool-specific APIs and attributes is fairly small, the bulk of the chapter serves to provide a "theory of operation" for tools and debuggers. Description of the APIs themselves is therefore deferred to the Section 17.5 later in the chapter.

17.1 Connection Mechanisms

The key to supporting tools lies in providing mechanisms by which a tool can connect to a PMIx server. Application processes are able to connect because their local RM daemon provides them with the necessary contact information upon execution. A command-line tool, however, isn't spawned by an RM daemon, and therefore lacks the information required for rendezvous with a PMIx server.

Once a tool has started, it initializes PMIx as a tool (via PMIx_tool_init) if its access is restricted to PMIx-based informational services such as PMIx_Query_info. However, if the

tool intends to start jobs, then it must include the **PMIX_LAUNCHER** attribute to inform the library of that intent so that the library can initialize and provide access to the corresponding support.

Support for tools requires that the PMIx server be initialized with an appropriate attribute indicating that tool connections are to be allowed. Separate attributes are provided to "fine-tune" this permission by allowing the environment to independently enable (or disable) connections from tools executing on nodes other than the one hosting the server itself. The PMIx server library shall provide an opportunity for the host environment to authenticate and approve each connection request from a specific tool by calling the <code>pmix_server_tool_connection_fn_t</code> "hook" provided in the server module for that purpose. Servers in environments that do not provide this "hook" shall automatically reject all tool connection requests.

Tools can connect to any local or remote PMIx server provided they are either explicitly given the required connection information, or are able to discover it via one of several defined rendezvous protocols. Connection discovery centers around the existence of *rendezvous files* containing the necessary connection information, as illustrated in Fig. 17.1.




Figure 17.1.: Tool rendezvous files

The contents of each rendezvous file are specific to a given PMIx implementation, but should at least contain the namespace and rank of the server along with its connection URI. Note that tools linked to one PMIx implementation are therefore unlikely to successfully connect to PMIx server libraries from another implementation.

The top of the directory tree is defined by either the PMIX_SYSTEM_TMPDIR attribute (if given) or the TMPDIR environmental variable. PMIx servers that are designated as *system servers* by including the PMIX_SERVER_SYSTEM_SUPPORT attribute when calling PMIX_SERVER_SYSTEM_SUPPORT attribute when calling PMIX_server_init will create a rendezvous file in this top-level directory. The filename will be of the form *pmix.sys.hostname*, where *hostname* is the string returned by the gethostname system call. Note that only one PMIx server on a node can be designated as the system server.

Non-system PMIx servers will create a set of three rendezvous files in the directory defined by either the **PMIX_SERVER_TMPDIR** attribute or the **TMPDIR** environmental variable:

pmix.host.tool.nspace where host is the string returned by the gethostname system call and
 nspace is the namespace of the server.

- *pmix.host.tool.pid* where *host* is the string returned by the **gethostname** system call and *pid* is the PID of the server.
- pmix.host.tool where host is the string returned by the **gethostname** system call. Note that servers which are not given a namespace-specific **PMIX_SERVER_TMPDIR** attribute may not generate this file due to conflicts should multiple servers be present on the node.

The files are identical and may be implemented as symlinks to a single instance. The individual file names are composed so as to aid the search process should a tool wish to connect to a server identified by its namespace or PID.

Servers will additionally provide a rendezvous file in any given location if the path (either absolute or relative) and filename is specified either during **PMIx_server_init** using the **PMIX_LAUNCHER_RENDEZVOUS_FILE** attribute, or by the

PMIX_LAUNCHER_RENDEZVOUS_FILE environmental variable prior to executing the process containing the server. This latter mechanism may be the preferred mechanism for tools such as debuggers that need to fork/exec a launcher (e.g., "mpiexec") and then rendezvous with it. This is described in more detail in Section 17.2.2.

Rendezvous file ownerships are set to the UID and GID of the server that created them, with permissions set according to the desires of the implementation and/or system administrator policy. All connection attempts are first governed by read access privileges to the target rendezvous file - thus, the combination of permissions, UID, and GID of the rendezvous files act as a first-level of security for tool access.

A tool may connect to as many servers at one time as the implementation supports, but is limited to designating only one such connection as its *primary* server. This is done to avoid confusion when the tool calls an API as to which server should service the request. The first server the tool connects to is automatically designated as the *primary* server.

Tools are allowed to change their primary server at any time via the **PMIx_tool_set_server** API, and to connect/disconnect from a server as many times as desired. Note that standing requests (e.g., event registrations) with the current primary server may be lost and/or may not be transferred when transitioning to another primary server - PMIx implementors are not required to maintain or transfer state across tool-server connections.

Tool process identifiers are assigned by one of the following methods:

- If PMIX_TOOL_NSPACE is given, then the namespace of the tool will be assigned that value.
 - If PMIX_TOOL_RANK is also given, then the rank of the tool will be assigned that value.
 - If **PMIX_TOOL_RANK** is not given, then the rank will be set to a default value of zero.
- If a process ID has not been provided, then one will be assigned by the host environment upon connection to a server. Users should note that the tool's process ID will be *invalid* until a

connection has been established.

Tool process identifiers remain constant across servers. Thus, it is critical that a system-wide unique namespace be provided if the tool itself sets the identifier, and that host environments provide a system-wide unique identifier in the case where the identifier is set by the server upon connection. The host environment is required to reject any connection request that fails to meet this criterion.

For simplicity, the following descriptions will refer to the:

- **PMIX_SYSTEM_TMPDIR** as the directory specified by either the **PMIX_SYSTEM_TMPDIR** attribute (if given) or the **TMPDIR** environmental variable.
- PMIX_SERVER_TMPDIR as the directory specified by either the PMIX_SERVER_TMPDIR attribute or the TMPDIR environmental variable.

The rendezvous methods are automatically employed for the initial tool connection during PMIx_tool_init unless the PMIX_TOOL_DO_NOT_CONNECT attribute is specified, and on all subsequent calls to PMIx_tool_attach_to_server.

14 17.1.1 Rendezvousing with a local server

Connection to a local PMIx server is pursued according to the following precedence chain based on attributes contained in the call to the PMIx tool init or

PMIx_tool_attach_to_server APIs. Servers to which the tool already holds a connection will be ignored. Except where noted, the PMIx library will return an error if the specified file cannot be found, the caller lacks permissions to read it, or the server specified within the file does not respond to or accept the connection — the library will not proceed to check for other connection options as the user specified a particular one to use.

Note that the PMIx implementation may choose to introduce a "delayed connection" protocol between steps in the precedence chain - i.e., the library may cycle several times, checking for creation of the rendezvous file each time after a delay of some period of time, thereby allowing the tool to wait for the server to create the rendezvous file before either returning an error or continuing to the next step in the chain.

- If PMIX_TOOL_ATTACHMENT_FILE is given, then the tool will attempt to read the specified file and connect to the server based on the information contained within it. The format of the attachment file is identical to the rendezvous files described in earlier in this section. An error will be returned if the specified file cannot be found.
- If PMIX_SERVER_URI or PMIX_TCP_URI is given, then connection will be attempted to the server at the specified URI. Note that it is an error for both of these attributes to be specified.

 PMIX_SERVER_URI is the preferred method as it is more generalized PMIX_TCP_URI is provided for those cases where the user specifically wants to use a TCP transport for the connection and wants to error out if one isn't available or cannot be used.
- If **PMIX_SERVER_PIDINFO** was provided, then the tool will search for a rendezvous file created by a PMIx server of the given PID in the **PMIX_SERVER_TMPDIR** directory. An error will be returned if a matching rendezvous file cannot be found.

- If **PMIX_SERVER_NSPACE** is given, then the tool will search for a rendezvous file created by a PMIx server of the given namespace in the **PMIX_SERVER_TMPDIR** directory. An error will be returned if a matching rendezvous file cannot be found.
 - If **PMIX_CONNECT_TO_SYSTEM** is given, then the tool will search for a system-level rendezvous file created by a PMIx server in the **PMIX_SYSTEM_TMPDIR** directory. An error will be returned if a matching rendezvous file cannot be found.
 - If **PMIX_CONNECT_SYSTEM_FIRST** is given, then the tool will look for a system-level rendezvous file created by a PMIx server in the **PMIX_SYSTEM_TMPDIR** directory. If found, then the tool will attempt to connect to it. In this case, no error will be returned if the rendezvous file is not found or connection is refused the PMIx library will silently continue to the next option.
 - By default, the tool will search the directory tree under the PMIX_SERVER_TMPDIR directory
 for rendezvous files of PMIx servers, attempting to connect to each it finds until one accepts the
 connection. If no rendezvous files are found, or all contacted servers refuse connection, then the
 PMIx library will return an error. No "delayed connection" protocols may be utilized at this point.

Note that there can be multiple local servers - one from the system plus others from launchers and active jobs. The PMIx tool connection search method is not guaranteed to pick a particular server unless directed to do so. Tools can obtain a list of servers available on their local node using the PMIx_Query_info APIs with the PMIX_QUERY_AVAIL_SERVERS key.

17.1.2 Connecting to a remote server

Connecting to remote servers is complicated due to the lack of access to the previously-described rendezvous files. Two methods are required to be supported, both based on the caller having explicit knowledge of either connection information or a path to a local file that contains such information:

- If **PMIX_TOOL_ATTACHMENT_FILE** is given, then the tool will attempt to read the specified file and connect to the server based on the information contained within it. The format of the attachment file is identical to the rendezvous files described in earlier in this section.
- If PMIX_SERVER_URI or PMIX_TCP_URI is given, then connection will be attempted to the server at the specified URI. Note that it is an error for both of these attributes to be specified.
 PMIX_SERVER_URI is the preferred method as it is more generalized PMIX_TCP_URI is provided for those cases where the user specifically wants to use the TCP transport for the connection and wants to error out if it isn't available or cannot be used.

Additional methods may be provided by particular PMIx implementations. For example, the tool may use *ssh* to launch a *probe* process onto the remote node so that the probe can search the **PMIX_SYSTEM_TMPDIR** and **PMIX_SERVER_TMPDIR** directories for rendezvous files, relaying the discovered information back to the requesting tool. If sufficient information is found to allow for remote connection, then the tool can use it to establish the connection. Note that this method is not required to be supported - it is provided here as an example and left to the discretion of PMIx implementors.

17.1.3 Attaching to running jobs

When attaching to a running job, the tool must connect to a PMIx server that is associated with that job - e.g., a server residing in the host environment's local daemon that spawned one or more of the job's processes, or the server residing in the launcher that is overseeing the job. Identifying an appropriate server can sometimes prove challenging, particularly in an environment where multiple job launchers may be in operation, possibly under control of the same user.

In cases where the user has only the one job of interest in operation on the local node (e.g., when engaged in an interactive session on the node from which the launcher was executed), the normal rendezvous file discovery method can often be used to successfully connect to the target job, even in the presence of jobs executed by other users. The permissions and security authorizations can, in many cases, reliably ensure that only the one connection can be made. However, this is not guaranteed in all cases.

The most common method, therefore, for attaching to a running job is to specify either the PID of the job's launcher or the namespace of the launcher's job (note that the launcher's namespace frequently differs from the namespace of the job it has launched). Unless the application processes themselves act as PMIx servers, connection must be to the servers in the daemons that oversee the application. This is typically either daemons specifically started by the job's launcher process, or daemons belonging to the host environment, that are responsible for starting the application's processes and oversee their execution.

Identifying the correct PID or namespace can be accomplished in a variety of ways, including:

- Using typical OS or host environment tools to obtain a listing of active jobs and perusing those to find the target launcher.
- Using a PMIx-based tool attached to a system-level server to query the active jobs and their command lines, thereby identifying the application of interest and its associated launcher.
- Manually recording the PID of the launcher upon starting the job.

Once the namespace and/or PID of the target server has been identified, either of the previous methods can be used to connect to it.

17.1.4 Tool initialization attributes

The following attributes are passed to the **PMIx_tool_init** API for use when initializing the PMIx library.

```
PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
Name of the namespace to use for this tool.

PMIX_TOOL_RANK "pmix.tool.rank" (uint32_t)
Rank of this tool.

PMIX_LAUNCHER "pmix.tool.launcher" (bool)
Tool is a launcher and needs to create rendezvous files.
```

1 17.1.5 Tool initialization environmental variables

2 3 4		The following environmental variables are used during PMIx_tool_init and PMIx_server_init to control various rendezvous-related operations when the process is started manually (e.g., on a command line) or by a fork/exec-like operation.
5 6 7 8 9		PMIX_LAUNCHER_RNDZ_URI Upon completing PMIx_server_init or PMIx_tool_init, the spawned launcher is to connect back to the spawning tool using the given URI so that the tool can provide directives (e.g., a PMIx_Spawn command) to it. PMIX_LAUNCHER_RNDZ_FILE Absolute path of file where the launcher is to store its connection information so that the
11	47.4.6	spawning tool can connect to it.
12	17.1.6	Tool connection attributes
13 14 15		These attributes are defined to assist PMIx-enabled tools to connect with a PMIx server by passing them into either the PMIx_tool_init or the PMIx_tool_attach_to_server APIs - thus, they are not typically accessed via the PMIx_Get API.
16 17		PMIX_SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t) PID of the target PMIx server for a tool.
18 19		PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool) The requester requires that a connection be made only to a local, system-level PMIx server.
20 21		PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool) Preferentially, look for a system-level PMIx server first.
22		PMIX_SERVER_URI "pmix.srvr.uri" (char*)
23 24		URI of the PMIx server to be contacted. PMIX_SERVER_HOSTNAME "pmix.srvr.host" (char*)
25		Host where target PMIx server is located.
26		PMIX_CONNECT_MAX_RETRIES "pmix.tool.mretries" (uint32_t)
27		Maximum number of times to try to connect to PMIx server - the default value is
28		implementation specific.
29		PMIX_CONNECT_RETRY_DELAY "pmix.tool.retry" (uint32_t)
30		Time in seconds between connection attempts to a PMIx server - the default value is
31		implementation specific.
32		PMIX_TOOL_DO_NOT_CONNECT "pmix.tool.nocon" (bool) The tool wants to use internal DMIx support but does not want to connect to a DMIx segment.
33 34		The tool wants to use internal PMIx support, but does not want to connect to a PMIx server. PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool)
35		The tool shall connect to a server if available, but otherwise continue to operate unconnected.
36		PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*)
37		Pathname of file containing connection information to be used for attaching to a specific
38		server.
39		<pre>PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*)</pre>

Pathname of file where the launcher is to store its connection information so that the spawning tool can connect to it. PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool) The server to which the tool is connecting shall be designated the *primary* server once connection has been accomplished. PMIX_WAIT_FOR_CONNECTION "pmix.wait.conn" (bool) Wait until the specified process has connected to the requesting tool or server, or the operation times out (if the **PMIX_TIMEOUT** directive is included in the request).

17.2 Launching Applications with Tools

Tool-directed launches require that the tool include the **PMIX_LAUNCHER** attribute when calling **PMIx_tool_init**. Two launch modes are supported:

- *Direct launch* where the tool itself is directly responsible for launching all processes, including debugger daemons, using either the RM or daemons launched by the tool i.e., there is no *intermediate launcher* (IL) such as *mpiexec*. The case where the tool is self-contained (i.e., uses its own daemons without interacting with an external entity such as the RM) lies outside the scope of this Standard; and
- *Indirect launch* where all processes are started via an IL such as *mpiexec* and the tool itself is not directly involved in launching application processes or debugger daemons. Note that the IL may utilize the RM to launch processes and/or daemons under the tool's direction.

Either of these methods can be executed interactively or by a batch script. Note that not all host environments may support the direct launch method.

22 17.2.1 Direct launch

In the direct-launch use-case (Fig. 17.2), the tool itself performs the role of the launcher. Once invoked, the tool connects to an appropriate PMIx server - e.g., a system-level server hosted by the RM. The tool is responsible for assembling the description of the application to be launched (e.g., by parsing its command line) into a spawn request containing an array of <code>pmix_app_t</code> applications and <code>pmix_info_t</code> job-level information. An allocation of resources may or may not have been made in advance – if not, then the spawn request must include allocation request information.

In addition to the attributes described in **PMIx_Spawn**, the tool may optionally wish to include the following tool-specific attributes in the *job_info* argument to that API (the debugger-related attributes are discussed in more detail in Section 17.4):

• PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its stdin to the indicated process. The local spawn agent should, therefore, ensure that the stdin channel to that process remains available. A rank of PMIX_RANK_WILDCARD indicates that all processes in the




Figure 17.2.: Direct Launch

spawned job are potential recipients. The requester will issue a call to **PMIx_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

• PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

- PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)
 - The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
- PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)

1	In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the
2	cache.
3 4 5	 PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
6 7 8 9 10 11	• PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be flushed to the callback upon a call to deregister the respective channel.
12 13 14 15	 PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.
16 17 18	 PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool) Requests that output be prefixed with the nspace,rank of the source and a string identifying the channel (stdout, stderr, etc.).
19 20 21	 PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool) Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.
22 23	• PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool) Requests that output be formatted in XML.
24 25 26 27	 PMIX_NOHUP "pmix.nohup" (bool) Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.
28 29 30 31 32 33 34 35 36 37	• PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool) Requests that the launcher generate the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note that the requester must register for these individual events, or capture and process them by registering a default event handler instead of individual handlers and then process the events based on the returned status code. Another common method is to register one event handler for all job-related events, with a separate handler for non-job events - see PMIx_Register_event_handler for details.

• PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)

Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred. Note that the requester must register for the event or capture and process it within a default event handler.

PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool) Requests that the launcher log the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log, subject to the logging attributes of Section 12.4.3.

• PMIX LOG COMPLETION "pmix.logcomp" (bool)

Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job using PMIx_Log, subject to the logging attributes of Section 12.4.3. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred.

• PMIX_DEBUG_STOP_ON_EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point.

• PMIX_DEBUG_STOP_IN_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have reached the pause point.

• PMIX_DEBUG_WAIT_FOR_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server

(by generating the PMIX_DEBUG_WAITING_FOR_NOTIFY event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the PMIX_DEBUGGER_RELEASE event. The launcher (RM or IL) is responsible for generating the PMIX_DEBUG_WAITING_FOR_NOTIFY event when all processes have indicated they are at the pause point.

The tool then calls the **PMIx_Spawn** API so that the PMIx library can communicate the spawn request to the server.

Upon receipt, the PMIx server library passes the spawn request to its host RM daemon for processing via the <code>pmix_server_spawn_fn_t</code> server module function. If this callback was not provided, then the PMIx server library will return the <code>PMIX_ERR_NOT_SUPPORTED</code> error status.

If an allocation must be made, then the host environment is responsible for communicating the request to its associated scheduler. Once resources are available, the host environment initiates the launch process to start the job. The host environment must parse the spawn request for relevant directives, returning an error if any required directive cannot be supported. Optional directives may be ignored if they cannot be supported.

Any error while executing the spawn request must be returned by **PMIx_Spawn** to the requester. Once the spawn request has succeeded in starting the specified processes, the request will return **PMIX_SUCCESS** back to the requester along with the namespace of the started job. Upon termination of the spawned job, the host environment must generate a **PMIX_EVENT_JOB_END** event for normal or abnormal termination if requested to do so. The event shall include:

- the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job;
- the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable;
- a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred; plus
- any other info provided by the host environment.

7 17.2.2 Indirect launch

In the indirect launch use-case, the application processes are started via an intermediate launcher (e.g., *mpiexec*) that is itself started by the tool (see Fig 17.3). Thus, at a high level, this is a two-stage launch procedure to start the application: the tool starts the IL, which then starts the applications. In practice, additional steps may be involved if, for example, the IL starts its own daemons to shepherd the application processes.

A key aspect of this operational mode is the avoidance of any requirement that the tool parse and/or understand the command line of the IL. Instead, the indirect launch support relies on **PMIx_Spawn** API to abstract the tool-launcher interaction required to start the IL and connect to it, and then uses a second call to **PMIx_Spawn** to request that the IL spawn the actual job.

The tool spawns the IL using the same procedure for launching an application - it assembles the description of the IL (e.g., by parsing its command line) into a spawn request containing an array of <code>pmix_app_t</code> and <code>pmix_info_t</code> job-level information. In addition, the tool must include the <code>PMIX_SPAWN_TOOL</code> attribute indicating that the application being spawned is a PMIx tool. An allocation of resources for the IL itself may or may not be required – if it is, then the allocation must be made in advance or the spawn request must include allocation request information.




Figure 17.3.: Indirect launch procedure

The tool may optionally wish to include the following tool-specific attributes in the *job_info* argument to **PMIx_Spawn** - note that these attributes refer to the behavior of the IL itself and not the eventual job to be launched:

- $\bullet \ \, \underline{ PMIX_FWD_STDIN} \ \, "pmix.fwd.stdin" \, \, (pmix_rank_t) \\$
 - The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx_IOF_push** to initiate the actual forwarding of information to specified targets this attribute simply requests that the IL retain the ability to forward the information to the designated targets.
- PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

 Requests that the ability to forward the stdout of the spawned processes be maintained.

 The requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for delivery of the forwarded output.
- PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)
 Requests that the ability to forward the stderr of the spawned processes be maintained.
 The requester will issue a call to PMIx_IOF_pull to specify the callback function and other options for delivery of the forwarded output.
- PMIX FWD STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

• PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t)

The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.

• PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool)

In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.

• PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool)

In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).

• PMIX IOF BUFFERING SIZE "pmix.iof.bsize" (uint32 t)

Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be *flushed* to the callback upon a call to deregister the respective channel.

• PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t)

Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

• PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)

Requests that output be prefixed with the nspace, rank of the source and a string identifying the channel (**stdout**, **stderr**, etc.).

• PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)

Requests that output be marked with the time at which the data was received by the tool - note that this will differ from the time at which the data was collected from the source.

• PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)

Requests that output be formatted in XML.

• PMIX_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

• PMIX_LAUNCHER_DAEMON "pmix.lnch.dmn" (char*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

• PMIX_FORKEXEC_AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

• PMIX_EXEC_AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

The tool then calls the **PMIx_Spawn** API so that the PMIx library can either communicate the spawn request to the server (if connected to one), or locally spawn the IL itself if not connected to a server and the PMIx implementation includes self-spawn support. **PMIx_Spawn** shall return an error if neither of these conditions is met.

Upon successful return from **PMIx_Spawn**:

- The namespace of the IL shall be returned in the *nspace* parameter of the **PMIx_Spawn** API (or in the **pmix_spawn_cbfunc_t** for the non-blocking form of that API).
- The tool shall be connected to the IL with the IL acting as the tool's *primary* server.

Once **PMIx_Spawn** has returned, the tool can proceed to spawn the actual application according to the procedure described in Section 17.2.1.

25 17.2.3 Tool spawn-related attributes

Tools are free to utilize the spawn attributes available to applications (see 11.2.4) when constructing a spawn request, but can also utilize the following attributes that are specific to tool-based spawn operations:

PMIX_FWD_STDIN "pmix.fwd.stdin" (pmix_rank_t)

The requester intends to push information from its **stdin** to the indicated process. The local spawn agent should, therefore, ensure that the **stdin** channel to that process remains available. A rank of **PMIX_RANK_WILDCARD** indicates that all processes in the spawned job are potential recipients. The requester will issue a call to **PMIx_IOF_push** to initiate the actual forwarding of information to specified targets - this attribute simply requests that the IL retain the ability to forward the information to the designated targets.

PMIX FWD STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDDIAG "pmix.fwd.stddiag" (bool)

Requests that the ability to forward the diagnostic channel (if it exists) of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_NOHUP "pmix.nohup" (bool)

Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.

PMIX LAUNCHER DAEMON "pmix.lnch.dmn" (char*)

Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

PMIX FORKEXEC AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

PMIX EXEC AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

17.2.4 Tool rendezvous-related events

The following constants refer to events relating to rendezvous of a tool and launcher during spawn of the IL.

PMIX_LAUNCHER_READY An application launcher (e.g., mpiexec) shall generate this event to signal a tool that started it that the launcher is ready to receive directives/commands (e.g., PMIx_Spawn). This is only used when the initiator is able to parse the command line itself, or the launcher is started as a persistent Distributed Virtual Machine (DVM).

17.3 IO Forwarding

Underlying the operation of many tools is a common need to forward **stdin** from the tool to targeted processes, and to return **stdout/stderr** from those processes to the tool (e.g., for display on the user's console). Historically, each tool developer was responsible for creating their own IO forwarding subsystem. However, the introduction of PMIx as a standard mechanism for interacting between applications and the host environment has made it possible to relieve tool developers of this burden.

This section defines functions by which tools can request forwarding of input/output to/from other processes and serves as a design guide to:

- provide tool developers with an overview of the expected behavior of the PMIx IO forwarding support;
- guide RM vendors regarding roles and responsibilities expected of the RM to support IO forwarding; and
- provide insight into the thinking of the PMIx community behind the definition of the PMIx IO forwarding APIs.

Note that the forwarding of IO via PMIx requires that both the host environment and the tool support PMIx, but does not impose any similar requirements on the application itself.

The responsibility of the host environment in forwarding of IO falls into the following areas:

- Capturing output from specified processes.
- Forwarding that output to the host of the PMIx server library that requested it.
- Delivering that payload to the PMIx server library via the PMIx_server_IOF_deliver API for final dispatch to the requesting tool.

It is the responsibility of the PMIx library to buffer, format, and deliver the payload to the requesting client. This may require eaching of output until a forwarding registration is received, as governed by the corresponding IO forwarding attributes of Section 17.3.5 that are supported by the implementation.

27 17.3.1 Forwarding stdout/stderr

At an appropriate point in its operation (usually during startup), a tool will utilize the **PMIx_tool_init** function to connect to a PMIx server. The PMIx server can be hosted by an RM daemon or could be embedded in a library-provided starter program such as *mpiexec* - in terms of IO forwarding, the operations remain the same either way. For purposes of this discussion, we will assume the server is in an RM daemon and that the application processes are directly launched by the RM, as shown in Fig 17.4.

Once the tool has connected to the target server, it can request that processes be spawned on its behalf or that output from a specified set of existing processes in a given executing application be




Figure 17.4.: Forwarding stdout/stderr

forwarded to it. Requests to spawn processes should include the **PMIX_FWD_STDIN**, **PMIX_FWD_STDOUT**, and/or **PMIX_FWD_STDERR** attributes if the tool intends to request that the corresponding streams be forwarded at some point during execution.

Note that requests to capture output from existing processes via the **PMIx_IOF_pull** API, and/or to forward input to specified processes via the **PMIx_IOF_push** API, can only succeed if the required attributes to retain that ability were passed when the corresponding job was spawned. The host is required to return an error for all such requests in cases where this condition is not met.

Two modes are supported when requesting that the host forward standard output/error via the **PMIx_IOF_pull** API - these can be controlled by including one of the following attributes in the *info* array passed to that function:

• PMIX_IOF_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

• PMIX_IOF_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool. This is the default mode of operation.

When requesting to forward **stdout/stderr**, the tool can specify several formatting options to

be used on the resulting output stream. These include:

- PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool)
 Requests that output be prefixed with the nspace,rank of the source and a string identifying the channel (stdout, stderr, etc.).
- PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)
 Requests that output be marked with the time at which the data was received by the tool note that this will differ from the time at which the data was collected from the source.
- PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)
 Requests that output be formatted in XML.

The PMIx client in the tool is responsible for formatting the output stream. Note that output from multiple processes will often be interleaved due to variations in arrival time - ordering of output is not guaranteed across processes and/or nodes.

3 17.3.2 Forwarding stdin

A tool is not necessarily a child of the RM as it may have been started directly from the command line. Thus, provision must be made for the tool to collect its **stdin** and pass it to the host RM (via the PMIx server) for forwarding. Two methods of support for forwarding of **stdin** are defined:




Figure 17.5.: Forwarding stdin

• internal collection by the PMIx tool library itself. This is requested via the PMIX_IOF_PUSH_STDIN attribute in the PMIX_IOF_push call. When this mode is

selected, the tool library begins collecting all **stdin** data and internally passing it to the local server for distribution to the specified target processes. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx_IOF_push** is made that includes the **PMIX_IOF_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

external collection directly by the tool. It is assumed that the tool will provide its own code/mechanism for collecting its stdin as the tool developers may choose to insert some filtering and/or editing of the stream prior to forwarding it. In addition, the tool can directly control the targets for the data on a per-call basis – i.e., each call to PMIx_IOF_push can specify its own set of target recipients for that particular blob of data. Thus, this method provides maximum flexibility, but requires that the tool developer provide their own code to capture stdin.

Note that it is the responsibility of the RM to forward data to the host where the target process(es) are executing, and for the host daemon on that node to deliver the data to the **stdin** of target process(es). The PMIx server on the remote node is not involved in this process. Systems that do not support forwarding of **stdin** shall return **PMIX_ERR_NOT_SUPPORTED** in response to a forwarding request.

Advice to users

Scalable forwarding of **stdin** represents a significant challenge. Most environments will at least handle a *send-to-1* model whereby **stdin** is forwarded to a single identified process, and occasionally an additional *send-to-all* model where **stdin** is forwarded to all processes in the application. Users are advised to check their host environment for available support as the distribution method lies outside the scope of PMIx.

Stdin buffering by the RM and/or PMIx library can be problematic. If any targeted recipient is slow reading data (or decides never to read data), then the data must be buffered in some intermediate daemon or the PMIx tool library itself. Thus, piping a large amount of data into **stdin** can result in a very large memory footprint in the system management stack or the tool. Best practices, therefore, typically focus on reading of input files by application processes as opposed to forwarding of **stdin**.

Forward all available channels.

17.3.3 IO Forwarding Channels

PMIX FWD ALL CHANNELS

The pmix_iof_channel_t structure is a uint16_t type that defines a set of bit-mask flags for specifying IO forwarding channels. These can be bitwise OR'd together to reference multiple channels.

PMIX_FWD_NO_CHANNELS Forward no channels.

PMIX_FWD_STDIN_CHANNEL Forward stdin.

PMIX_FWD_STDOUT_CHANNEL Forward stdout.

PMIX_FWD_STDDIAG_CHANNEL Forward stderr.

PMIX_FWD_STDDIAG_CHANNEL Forward stddiag, if available.

38

1	17.3.4	IO Forwarding constants
2		PMIX_ERR_IOF_FAILURE An IO forwarding operation failed - the affected channel will be included in the notification.
4 5		PMIX_ERR_IOF_COMPLETE IO forwarding of the standard input for this process has completed - i.e., the stdin file descriptor has closed.
6	17.3.5	IO Forwarding attributes
7 8 9		The following attributes are used to control IO forwarding behavior at the request of tools. Use of the attributes is optional - any option not provided will revert to some implementation-specific value.
10 11 12 13		PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size. PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the
15		cache.
16 17 18		PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
19 20 21 22 23		PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
25 26		PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) May time in accorde to buffer IO before delivering it. Used in conjugation with buffering
20 27		Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.
28		PMIX_IOF_COMPLETE "pmix.iof.cmp" (bool)
29 30 31 32		Indicates that the specified IO channel has been closed by the source. PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool) Requests that output be prefixed with the nspace,rank of the source and a string identifying the channel (stdout, stderr, etc.).
33 34		PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool) Requests that output be marked with the time at which the data was received by the tool -
35 36		note that this will differ from the time at which the data was collected from the source. PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool)
37		Requests that output be formatted in XML.

PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)

1

6 7 8

10 11 12

9

14 15

13

16

20 21 22

17

18 19

23 24

25 26 27

28 29 30

31

32 33

34 35

36

37

38

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the PMIx IOF push call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx IOF push** is made that includes the PMIX IOF COMPLETE attribute indicating that forwarding of stdin is to be terminated.

PMIX_IOF_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

PMIX_IOF_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

17.4 **Debugger Support**

Debuggers are a class of tool that merits special consideration due to their particular requirements for access to job-related information and control over process execution. The primary advantage of using PMIx for these purposes lies in the resulting portability of the debugger as it can be used with any system and/or programming model that supports PMIx. In addition to the general tool support described above, debugger support includes:

- Co-location, co-spawn, and communication wireup of debugger daemons for scalable launch. This includes providing debugger daemons with endpoint connection information across the daemons themselves.
- Identification of the job that is to be debugged. This includes automatically providing debugger daemons with the job-level information for their target job.

Debuggers can also utilize the options in the PMIx Spawn API to exercise a degree of control over spawned jobs for debugging purposes. For example, a debugger can utilize the environmental parameter attributes of Section 11.2.4 to request LD_PRELOAD of a memory interceptor library prior to spawning an application process, or interject a custom fork/exec agent to shepherd the application process.

A key element of the debugging process is the ability of the debugger to require that processes pause at some well-defined point, thereby providing the debugger with an opportunity to attach and control execution. The actual implementation of the pause lies outside the scope of PMIx - it typically requires either the launcher or the application itself to implement the necessary operations. However, PMIx does provide several standard attributes by which the debugger can specify the desired attach point:

• PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point. Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

• PMIX DEBUG STOP IN INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have reached the pause point. <code>PMIx</code> implementations that do not support this operation shall return an error from <code>PMIx_Init</code> if this behavior is requested. Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

• PMIX_DEBUG_WAIT_FOR_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have indicated they are at the pause point. Launchers that cannot support this operation shall return an error from the <code>PMIx_Spawn</code> API if this behavior is requested.

Note that there is no mechanism by which the PMIx library or the launcher can verify that an application will recognize and support the PMIX_DEBUG_WAIT_FOR_NOTIFY request. Debuggers utilizing this attachment method must, therefore, be prepared to deal with the case where the application fails to recognize and/or honor the request.

If the PMIx implementation and/or the host environment support it, debuggers can utilize the PMIx_Query_info API to determine which features are available via the PMIX QUERY ATTRIBUTE SUPPORT attribute.

• PMIX_DEBUG_STOP_IN_INIT by checking PMIX_CLIENT_ATTRIBUTES for the

PMIx Init API.

• PMIX_DEBUG_STOP_ON_EXEC by checking PMIX_HOST_ATTRIBUTES for the PMIX_Spawn API.

The target namespace or process (as given by the debugger in the spawn request) shall be provided to each daemon in its job-level information via the PMIX_DEBUG_TARGET attribute. Debugger daemons are responsible for self-determining their specific target process(es), and can then utilize the PMIx_Query_info API to obtain information about them (see Fig 17.6) - e.g., to obtain the PIDs of the local processes to which they need to attach. PMIx provides the pmix_proc_info_t structure for organizing information about a process' PID, location, and state. Debuggers may request information on a given job at two levels:

- PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)
 Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.
- PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)
 Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

Note that the information provided in the returned proctable represents a snapshot in time. Any process, regardless of role (tool, client, debugger, etc.) can obtain the proctable of a given namespace so long as it has the system-determined authorizations to do so. The list of namespaces available via a given server can be obtained using the **PMIx_Query_info** API with the **PMIX_QUERY_NAMESPACES** key.

Debugger daemons can be started in two ways - either at the same time the application is spawned, or separately at a later time.

17.4.1 Co-Location of Debugger Daemons

Debugging operations typically require the use of daemons that are located on the same node as the processes they are attempting to debug. The debugger can, of course, specify its own mapping method when issuing its spawn request or utilize its own internal launcher to place the daemons. However, when attaching to a running job, PMIx provides debuggers with a simplified method for requesting that the launcher associated with the job *co-locate* the required daemons. Debuggers can request *co-location* of their daemons by adding the following attributes to the **PMIx_Spawn** used to spawn them:




Figure 17.6.: Obtaining proctables

 PMIX_DEBUGGER_DAEMONS - indicating that the launcher is being asked to spawn debugger daemons.

- PMIX_DEBUG_TARGET indicating the job or process that is to be debugged. This allows the launcher to identify the processes to be debugged and their location. Note that the debugger job shall be assigned its own namespace (different from that of the job it is being spawned to debug) and each daemon will be assigned a unique rank within that namespace.
- PMIX_DEBUG_DAEMONS_PER_PROC specifies the number of debugger daemons to be co-located per target process.
- PMIX_DEBUG_DAEMONS_PER_NODE specifies the number of debugger daemons to be co-located per node where at least one target process is executing.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the PMIX_DEBUG_TARGET attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on the node. Note that the debugger will be attaching to the application processes at some arbitrary point in the application's execution unless some method for pausing the application (e.g., by providing a PMIx directive at time of launch, or via a tool using the PMIx_Job_control API to direct that the process be paused) has been employed.

Advice to users

Note that the tool calling **PMIx_Spawn** to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool.

17.4.2 Co-Spawn of Debugger Daemons

In the case where a job is being spawned under the control of a debugger, PMIx provides a shortcut method for spawning the debugger's daemons in parallel with the job. This requires that the debugger be specified as one of the <code>pmix_app_t</code> in the same spawn command used to start the job. The debugger application must include at least the <code>PMIX_DEBUGGER_DAEMONS</code> attribute identifying itself as a debugger, and may utilize either a mapping option to direct daemon placement, or one of the <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> or <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> or <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> or

The launcher must not include information regarding the debugger daemons in the job-level info provided to the rest of the <code>pmix_app_ts</code>, nor in any calculated rank values (e.g., <code>PMIX_NODE_RANK</code> or <code>PMIX_LOCAL_RANK</code>) in those applications. The debugger job is to be assigned its own namespace and each debugger daemon shall receive a unique rank - i.e., the debugger application is to be treated as a completely separate PMIx job that is simply being started in parallel with the user's applications. The launcher is free to implement the launch as a single operation for both the applications and debugger daemons (preferred), or may stage the launches as required. The launcher shall not return from the <code>PMIx_Spawn</code> command until all included applications and the debugger daemons have been started.

Attributes that apply to both the debugger daemons and the application processes can be specified in the *job_info* array passed into the **PMIx_Spawn** API. Attributes that either (a) apply solely to the debugger daemons or to one of the applications included in the spawn request, or (b) have values that differ from those provided in the *job_info* array, should be specified in the *info* array in the corresponding **pmix_app_t**. Note that PMIx job *pause* attributes (e.g., **PMIX_DEBUG_STOP_IN_INIT**) do not apply to applications (defined in **pmix_app_t**) where the **PMIX_DEBUGGER_DAEMONS** attribute is set to **true**.

Debugger daemons spawned in this manner shall be provided with the typical PMIx information for their own job plus the target they are to debug via the **PMIX_DEBUG_TARGET** attribute. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own **PMIX_LOCAL_RANK** in the daemon debugger job versus the corresponding **PMIX_LOCAL_RANK** of the target processes on the node.

Advice to users

Note that the tool calling **PMIx_Spawn** to request the launch of the debugger daemons is *not* included in the resulting job - i.e., the debugger daemons do not inherit the namespace of the tool. Thus, collective operations and notifications that target the debugger daemon job will not include the tool unless the namespace/rank of the tool is explicitly included.

The PMIx_Spawn API only supports the return of a single namespace resulting from the spawn request. In the case where the debugger job is co-spawned with the application, the spawn function shall return the namespace of the application and not the debugger job. Tools requiring access to the namespace of the debugger job must query the launcher for the spawned namespaces to find the one belonging to the debugger job.

17.4.3 Debugger Agents

Individual debuggers may, depending upon implementation, require varying degrees of control over each application process when it is started beyond those available via directives to **PMIx_Spawn**. PMIx offers two mechanisms to help provide a means of meeting these needs.

The PMIX_FORKEXEC_AGENT attribute allows the debugger to specify an intermediate process (the Fork/Exec Agent (FEA)) for spawning the actual application process (see Fig. 17.7a), thereby interposing the debugger daemon between the application process and the launcher's daemon. Instead of spawning the application process, the launcher will spawn the FEA, which will connect back to the PMIx server as a tool to obtain the spawn description of the application process it is to spawn. The PMIx server in the launcher's daemon shall not register the fork/exec agent as a local client process, nor shall the launcher include the agent in any of the job-level values (e.g., PMIX_RANK within the job or PMIX_LOCAL_RANK on the node) provided to the application process. The launcher shall treat the collection of FEAs as a debugger job equivalent to the co-spawn use-case described in Section 17.4.2.

In contrast, the **PMIX_EXEC_AGENT** attribute (Fig. 17.7b) allows the debugger to specify an agent that will perform some preparatory actions and then exec the eventual application process to replace itself. In this scenario, the exec agent is provided with the application process' command line as arguments on its command line (e.g., "./agent appargv[0] appargv[1]") and does not connect back to the host's PMIx server. It is the responsibility of the exec agent to properly separate its own command line arguments (if any) from the application description.




Figure 17.7.: Intermediate agents

17.4.4 Tracking the job lifecycle

There are a wide range of events a debugger can register to receive, but three are specifically defined for tracking a job's progress:

- PMIX_EVENT_JOB_START indicates when the first process in the job has been spawned.
- PMIX LAUNCH COMPLETE indicates when the last process in the job has been spawned.
- PMIX EVENT JOB END indicates that all processes have terminated.

Each event is required to contain at least the namespace of the corresponding job and a
PMIX_EVENT_TIMESTAMP indicating the time the event occurred. In addition, the
PMIX_EVENT_JOB_END event shall contain the returned status code
(PMIX_JOB_TERM_STATUS) for the corresponding job, plus the identity (PMIX_PROCID) and
exit status (PMIX_EXIT_CODE) of the first failed process, if applicable. Generation of these
events by the launcher can be requested by including the PMIX_NOTIFY_JOB_EVENTS
attributes in the spawn request. Note that these events can be logged via the PMIX_Log_API by
including the PMIX_LOG_JOB_EVENTS attribute - this can be done either in conjunction with
generated events, or in place of them.

Alternatively, if the debugger or tool solely wants to be alerted to job termination, then including the PMIX_NOTIFY_COMPLETION attribute in the spawn request would suffice. This attribute directs the launcher to provide just the PMIX_EVENT_JOB_END event. Note that this event can be logged via the PMIX_LOG_COMPLETION attribute - this can be done either in conjunction with the generated event, or in place of it.

Advice to users

The PMIx server is required to cache events in order to avoid race conditions - e.g., when a tool is trying to register for the **PMIX_EVENT_JOB_END** event from a very short-lived job. Accordingly, registering for job-related events can result in receiving events relating to jobs other than the one of interest.

Users are therefore advised to specify the job whose events are of interest by including the **PMIX_EVENT_AFFECTED_PROC** or **PMIX_EVENT_AFFECTED_PROCS** attribute in the *info* array passed to the **PMIX_Register_event_handler** API.

17.4.4.1 Job lifecycle events

 PMIX_EVENT_JOB_START The first process in the job has been spawned - includes
PMIX_EVENT_TIMESTAMP as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_LAUNCH_COMPLETE All processes in the job have been spawned - includes
PMIX_EVENT_TIMESTAMP as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_EVENT_JOB_END All processes in the job have terminated - includes
PMIX_EVENT_TIMESTAMP when the last process terminated as well as the PMIX_JOBID and/or PMIX_NSPACE of the job.

PMIX_EVENT_SESSION_START The allocation has been instantiated and is ready for use -

includes PMIX_EVENT_TIMESTAMP as well as the PMIX_SESSION_ID of the allocation. This event is issued after any system-controlled prologue has completed, but before any user-specified actions are taken.

PMIX_EVENT_SESSION_END The allocation has terminated - includes
PMIX_EVENT_TIMESTAMP as well as the PMIX_SESSION_ID of the allocation. This event is issued after any user-specified actions have completed, but before any system-controlled epilogue is performed.

The following events relate to processes within a job:

PMIX_EVENT_PROC_TERMINATED The specified process(es) terminated - normal or abnormal termination will be indicated by the **PMIX_PROC_TERM_STATUS** in the *info* array of the notification. Note that a request for individual process events can generate a significant event volume from large-scale jobs.

The following constants may be included via the **PMIX_JOB_TERM_STATUS** attributed in the *info* array in the **PMIX_EVENT_JOB_END** event notification to provide more detailed information regarding the reason for job abnormal termination:

PMIX_ERR_JOB_CANCELED
 PMIX_ERR_JOB_ABORTED
 be terminated.
 The job was canceled by the host environment.
 One or more processes in the job called abort, causing the job to

PMIX_ERR_JOB_KILLED_BY_CMD The job was killed by user command.

PMIX_ERR_JOB_ABORTED_BY_SIG The job was aborted due to receipt of an error signal (e.g., SIGKILL).

PMIX_ERR_JOB_TERM_WO_SYNC The job was terminated due to at least one process 1 2 terminating without calling PMIx Finalize, or was a member of an assemblage formed 3 via PMIx Connect and terminated or called PMIx Finalize without first calling 4 **PMIx Disconnect** (or its non-blocking form) from that assemblage. 5 PMIX ERR JOB SENSOR BOUND EXCEEDED The job was terminated due to one or more 6 processes exceeding a specified sensor limit. 7 PMIX ERR JOB NON ZERO TERM The job was terminated due to one or more processes 8 exiting with a non-zero status. 9 PMIX_ERR_JOB_ABORTED_BY_SYS_EVENT The job was aborted due to receipt of a 10 system event. 17.4.4.2 Job lifecycle attributes 11 12 PMIX JOB TERM STATUS "pmix.job.term.status" (pmix status t) 13 Status returned by job upon its termination. The status will be communicated as part of a 14 PMIx event payload provided by the host environment upon termination of a job. Note that generation of the PMIX EVENT JOB END event is optional and host environments may 15 16 choose to provide it only upon request. PMIX_PROC_STATE_STATUS "pmix.proc.state" (pmix_proc_state_t) 17 State of the specified process as of the last report - may not be the actual current state based 18 on update rate. 19 PMIX_PROC_TERM_STATUS "pmix.proc.term.status" (pmix_status_t) 20 21 Status returned by a process upon its termination. The status will be communicated as part of a PMIx event payload provided by the host environment upon termination of a process. 22 Note that generation of the PMIX EVENT PROC TERMINATED event is optional and host 23 environments may choose to provide it only upon request. 24 **Debugger-related constants** 17.4.5 25 26 The following constants are used in events used to coordinate applications and the debuggers 27 attaching to them. PMIX DEBUG_WAITING_FOR_NOTIFY 28 All processes in the job to be debugged are paused 29 waiting for a release at some point within the application. The application shall remain in a 30 paused state awaiting release until receipt of the PMIX DEBUGGER RELEASE. 31 PMIX DEBUGGER RELEASE Release processes that are paused at the 32 PMIX_DEBUG_WAIT_FOR_NOTIFY point in the target application. 17.4.6 Debugger attributes 33 34 Attributes used to assist debuggers - these are values that can either be passed to the PMIx_Spawn APIs or accessed by a debugger itself using the PMIx_Get API with the 35 PMIX RANK WILDCARD rank. 36 37 PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the

PMIX LAUNCH COMPLETE event when all processes are stopped at the exec point.

PMIX DEBUG STOP IN INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have reached the pause point.

PMIX_DEBUG_WAIT_FOR_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have indicated they are at the pause point.

PMIX_DEBUG_TARGET "pmix.dbg.tgt" (pmix_proc_t*)

Identifier of process(es) to be debugged - a rank of **PMIX_RANK_WILDCARD** indicates that all processes in the specified namespace are to be included.

PMIX DEBUGGER DAEMONS "pmix.debugger" (bool)

Included in the <code>pmix_info_t</code> array of a <code>pmix_app_t</code>, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole <code>pmix_app_t</code> in a <code>PMIx_Spawn</code> request, then the <code>PMIX_DEBUG_TARGET</code> attribute must also be provided (in either the <code>job_info</code> or in the <code>info</code> array of the <code>pmix_app_t</code>) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> nor <code>PMIX_DEBUG_DAEMONS_PER_NODE</code> is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

PMIX_COSPAWN_APP "pmix.cospawn" (bool)

Designated application is to be spawned as a disconnected job - i.e., the launcher shall not include the application in any of the job-level values (e.g., **PMIX_RANK** within the job)

provided to any other application process generated by the same spawn request. Typically used to cospawn debugger daemons alongside an application.

PMIX DEBUG DAEMONS PER PROC "pmix.dbg.dpproc" (uint16 t)

Number of debugger daemons to be spawned per application process. The launcher is to pass the identifier of the namespace to be debugged by including the PMIX_DEBUG_TARGET attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on the node.

PMIX_DEBUG_DAEMONS_PER_NODE "pmix.dbg.dpnd" (uint16_t)

Number of debugger daemons to be spawned on each node where the target job is executing. The launcher is to pass the identifier of the namespace to be debugged by including the **PMIX_DEBUG_TARGET** attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own **PMIX_LOCAL_RANK** in the daemon debugger job versus the corresponding **PMIX_LOCAL_RANK** of the target processes on the node.

PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.

PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

28 17.5 Tool-Specific APIs

PMIx-based tools automatically have access to all PMIx client functions. Tools designated as a *launcher* or a *server* will also have access to all PMIx server functions. There are, however, an additional set of functions (described in this section) that are specific to a PMIx tool. Access to those functions require use of the tool initialization routine.

17.5.1 PMIx tool init

Summary

Initialize the PMIx library for operating as a tool, optionally connecting to a specified PMIx server.

```
Format
1
   PMIx v2.0
2
              pmix status t
              PMIx_tool_init(pmix_proc_t *proc,
 3
                                 pmix info t info[], size t ninfo);
 4
              INOUT proc
5
6
                   pmix proc t structure (handle)
7
                   Array of pmix info t structures (array of handles)
8
9
              IN ninfo
                   Number of elements in the info array (size t)
10
11
              Returns PMIX SUCCESS or a negative value corresponding to a PMIx error constant.
                                             Required Attributes
              The following attributes are required to be supported by all PMIx libraries:
12
              PMIX_TOOL_NSPACE "pmix.tool.nspace" (char*)
13
                    Name of the namespace to use for this tool.
14
              PMIX TOOL RANK "pmix.tool.rank" (uint32 t)
15
                    Rank of this tool.
16
              PMIX TOOL DO NOT CONNECT "pmix.tool.nocon" (bool)
17
                    The tool wants to use internal PMIx support, but does not want to connect to a PMIx server.
18
              PMIX TOOL ATTACHMENT FILE "pmix.tool.attach" (char*)
19
                    Pathname of file containing connection information to be used for attaching to a specific
20
21
                    server.
22
              PMIX SERVER URI "pmix.srvr.uri" (char*)
23
                    URI of the PMIx server to be contacted.
              PMIX_TCP_URI "pmix.tcp.uri" (char*)
24
25
                    The URI of the PMIx server to connect to, or a file name containing it in the form of
                    file: <name of file containing it>.
26
              PMIX SERVER_PIDINFO "pmix.srvr.pidinfo" (pid_t)
27
                    PID of the target PMIx server for a tool.
28
29
              PMIX SERVER NSPACE "pmix.srv.nspace" (char*)
                    Name of the namespace to use for this PMIx server.
30
31
              PMIX_CONNECT_TO_SYSTEM "pmix.cnct.sys" (bool)
                    The requester requires that a connection be made only to a local, system-level PMIx server.
32
33
              PMIX CONNECT SYSTEM FIRST "pmix.cnct.sys.first" (bool)
```

1	Preferentially, look for a system-level PMIx server first.
	▼ Optional Attributes
2	The following attributes are optional for implementers of PMIx libraries:
3 4 5	PMIX_CONNECT_RETRY_DELAY "pmix.tool.retry" (uint32_t) Time in seconds between connection attempts to a PMIx server - the default value is implementation specific.
6 7 8	<pre>PMIX_CONNECT_MAX_RETRIES "pmix.tool.mretries" (uint32_t) Maximum number of times to try to connect to PMIx server - the default value is implementation specific.</pre>
9 10 11	PMIX_SOCKET_MODE "pmix.sockmode" (uint32_t) POSIX mode_t (9 bits valid). If the library supports socket connections, this attribute may be supported for setting the socket mode.
12 13 14 15	<pre>PMIX_TCP_REPORT_URI "pmix.tcp.repuri" (char*) If provided, directs that the TCP URI be reported and indicates the desired method of reporting: '-' for stdout, '+' for stderr, or filename. If the library supports TCP socket connections, this attribute may be supported for reporting the URI.</pre>
16 17 18 19	<pre>PMIX_TCP_IF_INCLUDE "pmix.tcp.ifinclude" (char*) Comma-delimited list of devices and/or CIDR notation to include when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces to be used.</pre>
20 21 22 23	<pre>PMIX_TCP_IF_EXCLUDE "pmix.tcp.ifexclude" (char*) Comma-delimited list of devices and/or CIDR notation to exclude when establishing the TCP connection. If the library supports TCP socket connections, this attribute may be supported for specifying the interfaces that are not to be used.</pre>
24 25 26	<pre>PMIX_TCP_IPV4_PORT "pmix.tcp.ipv4" (int) The IPv4 port to be used If the library supports IPV4 connections, this attribute may be supported for specifying the port to be used.</pre>
27 28 29	<pre>PMIX_TCP_IPV6_PORT "pmix.tcp.ipv6" (int) The IPv6 port to be used. If the library supports IPV6 connections, this attribute may be supported for specifying the port to be used.</pre>
30 31 32	PMIX_TCP_DISABLE_IPV4 "pmix.tcp.disipv4" (bool) Set to true to disable IPv4 family of addresses. If the library supports IPV4 connections, this attribute may be supported for disabling it.
33 34 35	PMIX_TCP_DISABLE_IPV6 "pmix.tcp.disipv6" (bool) Set to true to disable IPv6 family of addresses. If the library supports IPV6 connections, this attribute may be supported for disabling it.

PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool)

The host shall progress the PMIx library via calls to PMIx Progress

PMIX_EVENT_BASE "pmix.evbase" (void*)

Pointer to an **event_base** to use in place of the internal progress thread. All PMIx library events are to be assigned to the provided event base. The event base *must* be compatible with the event library used by the PMIx implementation - e.g., either both the host and PMIx library must use libevent, or both must use libev. Cross-matches are unlikely to work and should be avoided - it is the responsibility of the host to ensure that the PMIx implementation supports (and was built with) the appropriate event library.

Description

 Initialize the PMIx tool, returning the process identifier assigned to this tool in the provided **pmix_proc_t** struct. The *info* array is used to pass user requests pertaining to the initialization and subsequent operations. Passing a **NULL** value for the array pointer is supported if no directives are desired.

If called with the PMIX_TOOL_DO_NOT_CONNECT attribute, the PMIx tool library will fully initialize but not attempt to connect to a PMIx server. The tool can connect to a server at a later point in time, if desired, by calling the PMIx_tool_attach_to_server function. If provided, the proc structure will be set to a zero-length namespace and a rank of PMIX_RANK_UNDEF unless the PMIX_TOOL_NSPACE and PMIX_TOOL_RANK attributes are included in the info array.

In all other cases, the PMIx tool library will automatically attempt to connect to a PMIx server according to the precedence chain described in Section 17.1. If successful, the function will return PMIX_SUCCESS and will fill the process structure (if provided) with the assigned namespace and rank of the tool. The server to which the tool connects will be designated its *primary* server. Note that each connection attempt in the above precedence chain will retry (with delay between each retry) a number of times according to the values of the corresponding attributes.

Note that the PMIx tool library is referenced counted, and so multiple calls to PMIx_tool_init are allowed. If the tool is not connected to any server when this API is called, then the tool will attempt to connect to a server unless the PMIX_TOOL_DO_NOT_CONNECT is included in the call to API.

17.5.2 PMIx tool finalize

Summary

Finalize the PMIx tool library.

Format 1 PMIx v2.0 2 pmix status t PMIx tool finalize(void); 3 4 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. **Description** 5 Finalize the PMIx tool library, closing all existing connections to servers. An error code will be 6 7 returned if, for some reason, a connection cannot be cleanly terminated — in such cases, the 8 connection is dropped. Upon detecting loss of the connection, the PMIx server shall cleanup all associated records of the tool. 9 17.5.3 PMIx tool disconnect Summary 11 12 Disconnect the PMIx tool from the specified server connection while leaving the tool library 13 initialized. **Format** 14 PMIx v4.0 15 pmix status t PMIx_tool_disconnect(const pmix_proc_t *server); 16 IN 17 server pmix_proc_t structure (handle) 18 19 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. 20 Description Close the current connection to the specified server, if one has been made, while leaving the PMIx 21 22 library initialized. An error code will be returned if, for some reason, the connection cannot be 23 cleanly terminated - in this case, the connection is dropped. In either case, the library will remain 24 initialized. Upon detecting loss of the connection, the PMIx server shall cleanup all associated 25 records of the tool. 26 Note that if the server being disconnected is the current *primary* server, then all operations 27 requiring support from a server will return the PMIX_ERR_UNREACH error until the tool either 28 designates an existing connection to be the *primary* server or, if no other connections exist, the tool

29

establishes a connection to a PMIx server.

17.5.4 PMIx_tool_attach_to_server Summary Establish a connection to a PMIx server. 3 **Format** PMIx v4.0 5 pmix status t 6 PMIx tool attach to server(pmix proc t *proc, 7 pmix_proc_t *server, pmix_info_t info[], 8 9 size t ninfo); 10 INOUT proc Pointer to pmix_proc_t structure (handle) 11 INOUT server 12 Pointer to pmix_proc_t structure (handle) 13 14 IN info Array of pmix_info_t structures (array of handles) 15 IN ninfo 16 Number of elements in the *info* array (size_t) 17 18 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. Required Attributes The following attributes are required to be supported by all PMIx libraries: 19 PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*) 20 21 Pathname of file containing connection information to be used for attaching to a specific 22 server. PMIX SERVER URI "pmix.srvr.uri" (char*) 23 24 URI of the PMIx server to be contacted. 25 PMIX_TCP_URI "pmix.tcp.uri" (char*) The URI of the PMIx server to connect to, or a file name containing it in the form of 26 file: <name of file containing it>. 27 28 PMIX SERVER PIDINFO "pmix.srvr.pidinfo" (pid t) PID of the target PMIx server for a tool. 29 PMIX SERVER NSPACE "pmix.srv.nspace" (char*) 30 Name of the namespace to use for this PMIx server. 31 PMIX CONNECT TO SYSTEM "pmix.cnct.sys" (bool) 32 33 The requester requires that a connection be made only to a local, system-level PMIx server.

PMIX_CONNECT_SYSTEM_FIRST "pmix.cnct.sys.first" (bool) 1 Preferentially, look for a system-level PMIx server first. 2 PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool) 3 The server to which the tool is connecting shall be designated the *primary* server once 4 connection has been accomplished. 5 Description 6 7 Establish a connection to a server. This function can be called at any time by a PMIx tool to create a new connection to a server. If a specific server is given and the tool is already attached to it, then 8 the API shall return PMIX SUCCESS without taking any further action. In all other cases, the tool 9 10 will attempt to discover a server using the method described in Section 17.1, ignoring all candidates to which it is already connected. The PMIX ERR UNREACH error shall be returned if no new 11 connection is made. 12 The process identifier assigned to this tool is returned in the provided proc structure. Passing a 13 value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a PMIx 14 server and does not require return of the identifier at that time. 15 The process identifier of the server to which the tool attached is returned in the *server* structure. 16 Passing a value of **NULL** for the *proc* parameter is allowed if the user wishes solely to connect to a 17 PMIx server and does not require return of the identifier at that time. 18 19 Note that the **PMIX PRIMARY SERVER** attribute must be included in the *info* array if the server 20 being connected to is to become the primary server, or a call to PMIx tool set server must be provided immediately after the call to this function. 21 Advice to PMIx library implementers -22 When a tool connects to a server that is under a different namespace manager (e.g., host RM) from the prior server, the namespace in the identifier of the tool must remain unique in the new universe. 23 If the namespace of the tool fails to meet this criteria in the new universe, then the new namespace 24 manager is required to return an error and the connection attempt must fail. 25 Advice to users

Some PMIx implementations may not support connecting to a server that is not under the same namespace manager (e.g., host RM) as the server to which the tool is currently connected.

26

17.5.5 PMIx_tool_get_servers Summary 2 Get an array containing the pmix_proc_t process identifiers of all servers to which the tool is 3 currently connected. 4 **Format** 5 PMIx v4.0 pmix status t 6 7 PMIx_tool_get_servers(pmix_proc_t *servers[], size_t *nservers); **OUT** servers 8 9 Address where the pointer to an array of **pmix_proc_t** structures shall be returned (handle) 10 **INOUT** nservers Address where the number of elements in *servers* shall be returned (handle) 11 12 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant. Description 13 Return an array containing the pmix proc t process identifiers of all servers to which the tool is 14 15 currently connected. The process identifier of the current primary server shall be the first entry in 16 the array, with the remaining entries in order of attachment from earliest to most recent. 17.5.6 PMIx tool set server 17 Summary 18 Designate a server as the tool's *primary* server. 19 **Format** 20 PMIx v4.021 pmix status t 22 PMIx_tool_set_server(const pmix_proc_t *server pmix inf 23 info[], size t ninfo); JN: 24 server 25 pmix_proc_t structure (handle) 26 27 Array of pmix_info_t structures (array of handles) 28 29 Number of elements in the *info* array (**size** t) 30 Returns **PMIX_SUCCESS** or a negative value corresponding to a PMIx error constant.

```
Required Attributes
               The following attributes are required to be supported by all PMIx libraries:
 1
 2
               PMIX WAIT FOR CONNECTION "pmix.wait.conn" (bool)
 3
                     Wait until the specified process has connected to the requesting tool or server, or the
                     operation times out (if the PMIX_TIMEOUT directive is included in the request).
 5
               PMIX TIMEOUT "pmix.timeout" (int)
6
                     Time in seconds before the specified operation should time out (zero indicating infinite) and
 7
                     return the PMIX ERR TIMEOUT error. Care should be taken to avoid race conditions
                     caused by multiple layers (client, server, and host) simultaneously timing the operation.
8
               Description
9
10
               Designate the specified server to be the tool's primary server for all subsequent API calls.
    17.5.7
               PMIx_IOF_pull
               Summary
12
               Register to receive output forwarded from a set of remote processes.
13
               Format
14
   PMIx v3.0
15
               pmix status t
               PMIx_IOF_pull(const pmix_proc_t procs[], size_t nprocs,
16
                                  const pmix info t directives[], size t ndirs,
17
                                 pmix_iof_channel_t channel,
18
                                 pmix_iof_cbfunc_t cbfunc,
19
20
                                 pmix_hdlr_reg_cbfunc_t regcbfunc,
21
                                 void *regcbdata);
               IN
22
                    procs
                    Array of proc structures identifying desired source processes (array of handles)
23
24
               IN
                    nprocs
                    Number of elements in the procs array (integer)
25
26
               IN
                    directives
                    Array of pmix info t structures (array of handles)
27
               IN
                    ndirs
28
29
                    Number of elements in the directives array (integer)
               IN
30
31
                    Bitmask of IO channels included in the request (pmix iof channel t)
```

1 2	IN cbfunc Callback function for delivering relevant output (pmix_iof_cbfunc_t function reference)
3	IN regcbfunc
4 5	Function to be called when registration is completed (pmix_hdlr_reg_cbfunc_t function reference)
6	IN regcbdata
7	Data to be passed to the <i>regcbfunc</i> callback function (memory reference)
8 9	Returns PMIX_SUCCESS or a negative value corresponding to a PMIx error constant. In the event the function returns an error, the <i>regcbfunc</i> will <i>not</i> be called.
	▼
0	The following attributes are required for PMIx libraries that support IO forwarding:
1 2 3	<pre>PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.</pre>
4 5 6	<pre>PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.</pre>
7 8 9	PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
	▼Optional Attributes
20	The following attributes are optional for PMIx libraries that support IO forwarding:
21 22 23 24 25	PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be <i>flushed</i> to the callback upon a call to deregister the respective channel.
27 28 29	PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.
31 32 33	<pre>PMIX_IOF_TAG_OUTPUT "pmix.iof.tag" (bool) Requests that output be prefixed with the nspace,rank of the source and a string identifying the channel (stdout, stderr, etc.).</pre>
84	<pre>PMIX_IOF_TIMESTAMP_OUTPUT "pmix.iof.ts" (bool)</pre>

Requests that output be marked with the time at which the data was received by the tool -1 note that this will differ from the time at which the data was collected from the source. 2 3 PMIX_IOF_XML_OUTPUT "pmix.iof.xml" (bool) Requests that output be formatted in XML. 4 **Description** 5 6 Register to receive output forwarded from a set of remote processes. Advice to users 7 Providing a NULL function pointer for the cbfunc parameter will cause output for the indicated 8 channels to be written to their corresponding **stdout/stderr** file descriptors. Use of 9 PMIX RANK WILDCARD to specify all processes in a given namespace is supported but should be used carefully due to bandwidth and memory footprint considerations. 10 17.5.8 PMIx_IOF_deregister Summary 12 Deregister from output forwarded from a set of remote processes. 13 Format 14 PMIx v3.015 pmix status t 16 PMIx IOF deregister(size t iofhdlr, const pmix_info_t directives[], size_t ndirs, 17 pmix_op_cbfunc_t cbfunc, void *cbdata); 18 IN 19 iofhdlr 20 Registration number returned from the pmix hdlr reg cbfunc t callback from the call to PMIx_IOF_pull (size_t) 21 IN directives 22 Array of pmix info t structures (array of handles) 23 24 ndirs 25 Number of elements in the *directives* array (integer) cbfunc 26 27 Callback function to be called when deregistration has been completed. (function reference) 28 IN cbdata Data to be passed to the *cbfunc* callback function (memory reference) 29 30 Returns one of the following:

• PMIX_SUCCESS, indicating that the request is being processed by the host environment - result 1 2 will be returned in the provided *cbfunc*. Note that the library *must not* invoke the callback function prior to returning from the API. 3 • PMIX OPERATION SUCCEEDED, indicating that the request was immediately processed and 4 returned success - the cbfunc will not be called 5 • a PMIx error constant indicating either an error in the input or that the request was immediately 6 7 processed and failed - the cbfunc will not be called **Description** 8 9 Deregister from output forwarded from a set of remote processes. Advice to PMIx library implementers. Any currently buffered IO should be flushed upon receipt of a deregistration request. All received 10 11 IO after receipt of the request shall be discarded. 17.5.9 PMIx_IOF_push Summary 13 14 Push data collected locally (typically from **stdin** or a file) to **stdin** of the target recipients. **Format** 15 PMIx v3.016 pmix_status_t PMIx_IOF_push(const pmix_proc_t targets[], size_t ntargets, 17 18 pmix byte object t *bo, const pmix_info_t directives[], size_t ndirs, 19 20 pmix op cbfunc t cbfunc, void *cbdata); IN 21 targets Array of proc structures identifying desired target processes (array of handles) 22 23 IN ntargets 24 Number of elements in the *targets* array (integer) IN 25 26 Pointer to pmix byte object t containing the payload to be delivered (handle) 27 IN directives Array of pmix info t structures (array of handles) 28 29 ndirs

Number of elements in the *directives* array (integer)

Array of **pmix** info t structures (array of handles)

30

31

32

IN

directives

1 2 3 4 5	 IN cbfunc Callback function to be called when operation has been completed. (pmix_op_cbfunc_t function reference) IN cbdata Data to be passed to the cbfunc callback function (memory reference)
6	Returns one of the following:
7 8 9	• PMIX_SUCCESS , indicating that the request is being processed by the host environment - result will be returned in the provided <i>cbfunc</i> . Note that the library <i>must not</i> invoke the callback function prior to returning from the API.
10 11	• PMIX_OPERATION_SUCCEEDED , indicating that the request was immediately processed and returned <i>success</i> - the <i>cbfunc</i> will <i>not</i> be called.
12 13	• a PMIx error constant indicating either an error in the input or that the request was immediately processed and failed - the <i>cbfunc</i> will <i>not</i> be called.
	▼
14	The following attributes are required for PMIx libraries that support IO forwarding:
15 16 17	PMIX_IOF_CACHE_SIZE "pmix.iof.csize" (uint32_t) The requested size of the PMIx server cache in bytes for each specified channel. By default, the server is allowed (but not required) to drop all bytes received beyond the max size.
18 19 20	<pre>PMIX_IOF_DROP_OLDEST "pmix.iof.old" (bool) In an overflow situation, the PMIx server is to drop the oldest bytes to make room in the cache.</pre>
21 22 23	PMIX_IOF_DROP_NEWEST "pmix.iof.new" (bool) In an overflow situation, the PMIx server is to drop any new bytes received until room becomes available in the cache (default).
	▼Optional Attributes
24	The following attributes are optional for PMIx libraries that support IO forwarding:
25 26 27 28 29 30	PMIX_IOF_BUFFERING_SIZE "pmix.iof.bsize" (uint32_t) Requests that IO on the specified channel(s) be aggregated in the PMIx tool library until the specified number of bytes is collected to avoid being called every time a block of IO arrives. The PMIx tool library will execute the callback and reset the collection counter whenever the specified number of bytes becomes available. Any remaining buffered data will be flushed to the callback upon a call to deregister the respective channel.
31 32 33 34	PMIX_IOF_BUFFERING_TIME "pmix.iof.btime" (uint32_t) Max time in seconds to buffer IO before delivering it. Used in conjunction with buffering size, this prevents IO from being held indefinitely while waiting for another payload to arrive.

	<pre>PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)</pre>
2	Requests that the PMIx library collect the stdin of the requester and forward it to the
3	processes specified in the PMIx_IOF_push call. All collected data is sent to the same
ļ	targets until stdin is closed, or a subsequent call to PMIx_IOF_push is made that
5	includes the PMIX_IOF_COMPLETE attribute indicating that forwarding of stdin is to be
3	terminated.
	lacklacklack

Description

7

9

10

11 12

13

14

15

16 17 Called either to:

- push data collected by the caller themselves (typically from **stdin** or a file) to **stdin** of the target recipients;
- request that the PMIx library automatically collect and push the **stdin** of the caller to the target recipients; or
- indicate that automatic collection and transmittal of **stdin** is to stop

Advice to users

Execution of the *cbfunc* callback function serves as notice that the PMIx library no longer requires the caller to maintain the *bo* data object - it does *not* indicate delivery of the payload to the targets. Use of PMIX_RANK_WILDCARD to specify all processes in a given namespace is supported but should be used carefully due to bandwidth and memory footprint considerations.

APPENDIX A

Python Bindings

While the PMIx Standard is defined in terms of C-based APIs, there is no intent to limit the use of PMIx to that specific language. Support for other languages is captured in the Standard by describing their equivalent syntax for the PMIx APIs and native forms for the PMIx datatypes. This Appendix specifically deals with Python interfaces, beginning with a review of the PMIx datatypes. Support is restricted to Python 3 and above - i.e., the Python bindings do not support Python 2.

Note: the PMIx APIs have been loosely collected into three Python classes based on their PMIx "class" (i.e., client, server, and tool). All processes have access to a basic set of the APIs, and therefore those have been included in the "client" class. Servers can utilize any of those functions plus a set focused on operations not commonly executed by an application process. Finally, tools can also act as servers but have their own initialization function.

A.1 Design Considerations

Several issues arose during design of the Python bindings:

A.1.1 Error Codes vs Python Exceptions

The C programming language reports errors through the return of the corresponding integer status codes. PMIx has defined a range of negative values for this purpose. However, Python has the option of raising *exceptions* that effectively operate as interrupts that can be trapped if the program appropriately tests for them. The PMIx Python bindings opted to follow the C-based standard and return PMIx status codes in lieu of raising exceptions as this method was considered more consistent for those working in both domains.

20 A.1.2 Representation of Structured Data

PMIx utilizes a number of C-language structures to efficiently bundle related information. For example, the PMIx process identifier is represented as a struct containing a character array for the namespace and a 32-bit unsigned integer for the process rank. There are several options for translating such objects to Python – e.g., the PMIx process identifier could be represented as a two-element tuple (nspace, rank) or as a dictionary 'nspace': name, 'rank': 0. Exploration found no discernible benefit to either representation, nor was any clearly identifiable rationale developed that would lead a user to expect one versus the other for a given PMIx data type. Consistency in the translation (i.e., exclusively using tuple or dictionary) appeared to be the most important criterion. Hence, the decision was made to express all complex datatypes as Python dictionaries.

A.2 Datatype Definitions

PMIx defines a number of datatypes comprised of fixed-size character arrays, restricted range integers (e.g., uint32_t), and structures. Each datatype is represented by a named unsigned 16-bit integer (uint16_t) constant. Users are advised to use the named PMIx constants for indicating datatypes instead of integer values to ensure compatibility with future PMIx versions.

With only a few exceptions, the C-based PMIx datatypes defined in Chapter 3 on page 12 directly translate to Python. However, Python lacks the size-specific value definitions of C (e.g., uint8_t) and thus some care must be taken to protect against overflow/underflow situations when moving between the languages. Python bindings that accept values including PMIx datatypes shall therefore have the datatype and associated value checked for compatibility with their PMIx-defined equivalents, returning an error if:

- datatypes not defined by PMIx are encountered
- provided values fall outside the range of the C-equivalent definition e.g., if a value identified as **PMIX UINT8** lies outside the **uint8** trange

Note that explicit labeling of PMIx data type, even when Python itself doesn't care, is often required for the Python bindings to know how to properly interpret and label the provided value when passing it to the PMIx library.

Table A.1 lists the correspondence between data types in the two languages.



Table A.1.: C-to-Python Datatype Correspondence

	Table A.T., C-to-1 yulon 1	71 1	
C-Definition	PMIx Name	Python Definition	Notes
bool	PMIX_BOOL	boolean	
byte	PMIX_BYTE	A single element byte	
		array (i.e., a byte array	
		of length one)	
char*	PMIX_STRING	string	
size_t	PMIX_SIZE	integer	
pid_t	PMIX_PID	integer	value shall be limited to the uint32_t
			range
int, int8_t, int16_t,	PMIX_INT, PMIX_INT8,	integer	value shall be limited to its corresponding
int32_t, int64_t	PMIX_INT16,		range
	PMIX_INT32, PMIX_INT64		
uint, uint8_t,	PMIX_UINT, PMIX_UINT8,	integer	value shall be limited to its corresponding
uint16_t, uint32_t,	PMIX_UINT16,		range
uint64_t	PMIX_UINT32,		
	PMIX_UINT64		
float, double	PMIX_FLOAT,	float	value shall be limited to its corresponding
	PMIX_DOUBLE		range
struct timeval	PMIX_TIMEVAL	{'sec': sec, 'usec':	each field is an integer value
		microsec}	
time_t	PMIX_TIME	integer	limited to positive values
pmix_data_type_t	PMIX_DATA_TYPE	integer	value shall be limited to the uint16_t
			range
pmix_status_t	PMIX_STATUS	integer	
pmix_key_t	N/A	string	The string's length shall be limited to one
			less than the size of the pmix_key_t
			array (to reserve space for the terminating
			NULL)
pmix_nspace_t	N/A	string	The string's length shall be limited to one
		_	less than the size of the pmix_nspace_t
			array (to reserve space for the terminating
			NULL)

C-Definition

value shall be limited to the uint32_t pmix rank t PMIX PROC RANK integer range excepting the reserved values near UINT32 MAX PMIX_PROC {'nspace': nspace, nspace is a Python string and rank is an pmix_proc_t 'rank': rank} integer value. The *nspace* string's length shall be limited to one less than the size of the **pmix_nspace_t** array (to reserve space for the terminating **NULL**), and the rank value shall conform to the constraints associated with pmix rank t {'bytes': bytes, 'size': pmix byte object t bytes is a Python byte array and size is the PMIX BYTE OBJECT integer number of bytes in that array. size } value shall be limited to the uint8 t PMIX PERSISTENCE pmix persistence t integer value shall be limited to the uint8_t PMIX SCOPE pmix_scope_t integer value shall be limited to the uint8_t pmix_data_range_t PMIX RANGE integer value shall be limited to the uint8 t pmix proc state t PMIX PROC STATE integer range {'proc': {'nspace': *proc* is a Python **proc** dictionary; pmix proc info t PMIX PROC INFO nspace, 'rank': hostname and executable are Python rank}, 'hostname': strings; and pid, exitcode, and state are hostname, 'executable': Python integers executable, 'pid': pid, 'exitcode': exitcode, 'state': state}

PMIx Name

Python Definition

Notes

Table A.1.: C-to-Python Datatype Correspondence

C-Definition	PMIx Name	Python Definition	Notes
pmix_data_array_t	PMIX_DATA_ARRAY	{'type': type, 'array':	type is the PMIx type of object in the array
		array}	and <i>array</i> is a Python <i>list</i> containing the
			individual array elements. Note that array
			can consist of any PMIx types, including
			(for example) a Python info object that
			itself contains an array value
pmix_info_directives_t	PMIX_INFO_DIRECTIVES	list	list of integer values (defined in Section
			3.2.10)
pmix_alloc_directive_t	PMIX_ALLOC_DIRECTIVE	integer	value shall be limited to the uint8_t
			range
pmix_iof_channel_t	PMIX_IOF_CHANNEL	list	list of integer values (defined in Section
	, , ,		17.3.3)
pmix_envar_t	PMIX_ENVAR	{'envar': envar,	envar and value are Python strings, and
		'value': value,	separator a single-character Python string
		'separator': separator}	
pmix_value_t	PMIX_VALUE	{'value': value,	type is the PMIx datatype of value, and
		'val_type': type}	value is the associated value expressed
			in the appropriate Python form for the
			specified datatype
pmix_info_t	PMIX_INFO	{'key': key, 'flags':	key is a Python string key , flags is an
		flags, value': value,	info directives value, type is
		'val_type': type}	the PMIx datatype of value, and value
			is the associated value expressed in the
			appropriate Python form for the specified
			datatype
pmix_pdata_t	PMIX_PDATA	{'proc': {'nspace':	proc is a Python proc dictionary;
		nspace, 'rank': rank},	key is a Python string key ; type is the
		'key': key, 'value':	PMIx datatype of <i>value</i> ; and <i>value</i> is
		value, 'val_type': type}	the associated value expressed in the
			appropriate Python form for the specified
			datatype

C-Definition	PMIx Name	Python Definition	Notes
pmix_app_t	PMIX_APP	{'cmd': cmd, 'argv':	cmd is a Python string; argv and env are
		[argv], 'env': [env],	Python <i>lists</i> containing Python strings;
		'maxprocs': maxprocs,	maxprocs is an integer; and info is a
		'info': [info]}	Python <i>list</i> of info values
pmix_query_t	PMIX_QUERY	{'keys': [keys],	keys is a Python list of Python strings, and
		'qualifiers': [info]}	qualifiers is a Python list of info values
pmix_regattr_t	PMIX_REGATTR	{'name': name, 'key':	name and string are Python strings; type
		key, 'type': type, 'info':	is the PMIx datatype for the attribute's
		[info], 'description':	value; <i>info</i> is a Python <i>list</i> of info values;
		[desc]}	and description is a list of Python strings
			describing the attribute
pmix_job_state_t	PMIX_JOB_STATE	integer	value shall be limited to the uint8_t
			range
pmix_link_state_t	PMIX_LINK_STATE	integer	value shall be limited to the uint8_t
			range
pmix_cpuset_t	PMIX_PROC_CPUSET	{'source': source,	source is a string name of the library that
		'cpus': bitmap}	created the cpuset; and cpus is a list of
			string ranges identifying the PUs to which
			the process is bound (e.g., [1, 3-5, 7])
pmix_locality_t	PMIX_LOCTYPE	list	list of integer values (defined in Section
			11.4.2.3) describing the relative locality of
			the specified local process
pmix_fabric_t	N/A	{'name': name,	name is the string name assigned to the
		'index': idx, 'info':	fabric; <i>index</i> is the integer ID assigned to
		[info]}	the fabric; <i>info</i> is a list of info describing
			the fabric
pmix_endpoint_t	PMIX_ENDPOINT	{'uuid': uuid,	<i>uuid</i> is the string system-unique identifier
		'osname': osname,	assigned to the device; osname is the
		endpt': endpt}	operating system name assigned to
			the device; endpt is a byteobject
			containing the endpoint information

Table A.1.: C-to-Python Datatype Correspondence

Table A.1.: C-to-Python Datatype Correspondence

		outdrype correspondence	
C-Definition	PMIx Name	Python Definition	Notes
pmix_device_distance_t	PMIX_DEVICE_DIST	{'uuid': uuid,	<i>uuid</i> is the string system-unique identifier
		'osname': osname,	assigned to the device; osname is the
		mindist': mindist,	operating system name assigned to the
		'maxdist': maxdist}	device; and <i>mindist</i> and <i>maxdist</i> are
			Python integers
pmix_coord_t	PMIX_COORD	{'view': view, 'coord':	view is the pmix_coord_view_t of the
		[coords]}	coordinate; and <i>coord</i> is a list of integer
			coordinates, one for each dimension of the
			fabric
pmix_geometry_t	PMIX_GEOMETRY	{'fabric': idx, 'uuid':	fabric is the Python integer index of the
		uuid, 'osname':	fabric; <i>uuid</i> is the string system-unique
	, , ,	osname, coordinates':	identifier assigned to the device; osname is
		[coords]}	the operating system name assigned to the
			device; and <i>coordinates</i> is a list of coord
			containing the coordinates for the device
	` `		across all views
pmix_device_type_t	PMIX_DEVTYPE	list	list of integer values (defined in Section
			11.4.8)
pmix_bind_envelope_t	N/A	integer	one of the values defined in Section
			11.4.4.1

A.2.1 Example

Converting a C-based program to its Python equivalent requires translation of the relevant datatypes as well as use of the appropriate API form. An example small program may help illustrate the changes. Consider the following C-based program snippet:

```
#include <pmix.h>
...

pmix_info_t info[2];

PMIX_INFO_LOAD(&info[0], PMIX_PROGRAMMING_MODEL, "TEST", PMIX_STRING)

PMIX_INFO_LOAD(&info[1], PMIX_MODEL_LIBRARY_NAME, "PMIX", PMIX_STRING)

rc = PMIx_Init(&myproc, info, 2);

PMIX_INFO_DESTRUCT(&info[0]); // free the copied string

PMIX_INFO_DESTRUCT(&info[1]); // free the copied string

C
```

Moving to the Python version requires that the **pmix_info_t** be translated to the Python **info** equivalent, and that the returned information be captured in the return parameters as opposed to a pointer parameter in the function call, as shown below:

Note the use of the **PMIX_STRING** identifier to ensure the Python bindings interpret the provided string value as a PMIx "string" and not an array of bytes.

Python

(rc, myproc) = myclient.init(info)

1 A.3 Callback Function Definitions

2 A.3.1 IOF Delivery Function

3 4		Summary Callback function for delivering forwarded IO to a process
5	PMIx v4.0	Format Python
6 7		<pre>def iofcbfunc(iofhdlr:integer, channel:bitarray,</pre>
8 9		IN iofhdlr Registration number of the handler being invoked (integer)
10 11		N channel Python channel 16-bit bitarray identifying the channel the data arrived on (bitarray)
12 13		IN source Python proc identifying the namespace/rank of the process that generated the data (dict)
14 15		IN payload Python byteobject containing the data (dict)
16 17 18		IN info List of Python info provided by the source containing metadata about the payload. This could include PMIX_IOF_COMPLETE (list)
19		Returns: nothing
20		See pmix_iof_cbfunc_t for details
21	A.3.2	Event Handler
22 23		Summary Callback function for event handlers
24		Format

PMIx v4.0

		Python —
1 2		<pre>def evhandler(evhdlr:integer, status:integer,</pre>
3		IN iofhdlr Registration number of the handler being invoked (integer)
5		IN status Status associated with the operation (integer)
7 8		N source Python proc identifying the namespace/rank of the process that generated the event (dict)
9 10		 IN info List of Python info provided by the source containing metadata about the event (list) IN results
11 12		List of Python info containing the aggregated results of all prior evhandlers (list)
13		Returns:
14		• rc - Status returned by the event handler's operation (integer)
15 16		• <i>results</i> - List of Python info containing results from this event handler's operation on the event (list)
17		See pmix_notification_fn_t for details
18	A.3.3	Server Module Functions
19 20 21		The following definitions represent functions that may be provided to the PMIx server library at time of initialization for servicing of client requests. Module functions that are not provided default to returning "not supported" to the caller.
22	A.3.3.1	Client Connected
23 24		Summary Notify the host server that a client connected to this server.
25		Format

PMIx v4.0

	Python —
1	def clientconnected2(proc:dict is not None, info:list) Python
2 3 4 5	 IN proc Python proc identifying the namespace/rank of the process that connected (dict) IN info list of Python info containing information about the process (list)
6	Returns:
7	• rc - PMIX_SUCCESS or a PMIx error code indicating the connection should be rejected (integer)
8	See pmix_server_client_connected2_fn_t for details
9 A.3.3.2	Summary
l1	Notify the host environment that a client called PMIx_Finalize .
12 <i>PMIx v4.0</i>	Format Python
13	<pre>def clientfinalized(proc:dict is not None):</pre> Python
14 15	IN proc Python proc identifying the namespace/rank of the process that finalized (dict)
16	Returns: nothing
17	See pmix_server_client_finalized_fn_t for details
8 A.3.3.3	Client Aborted
19 20	Summary Notify the host environment that a local client called PMIx_Abort.

1		Format
_	PMIx v4.0	Python —
2		def clientaborted(args:dict is not None) Python
0		
3 4		IN args Python dictionary containing:
5		• 'caller': Python proc identifying the namespace/rank of the process calling abort (dict)
6		• 'status': PMIx status to be returned on exit (integer)
7		• 'msg': Optional string message to be printed (string)
8 9		• 'targets': Optional list of Python proc identifying the namespace/rank of the processes to be aborted (list)
10		Returns:
11		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
12		See pmix_server_abort_fn_t for details
13	A.3.3.4	Fence
14		Summary
15		At least one client called either PMIx_Fence or PMIx_Fence_nb
16	DMI 40	Format
17	PMIx v4.0	def fence(args:dict is not None)
1,		Python
18		IN args
19		Python dictionary containing:
20 21		• 'procs': List of Python proc identifying the namespace/rank of the participating processes (list)
22 23		• 'directives': Optional list of Python info containing directives controlling the operation (list)
24		• 'data': Optional Python bytearray of data to be circulated during fence operation (bytearray)
25		Returns:
26		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
27		• data - Python bytearray containing the aggregated data from all participants (bytearray)
28		See pmix_server_fencenb_fn_t for details

2 Summary 3 Used by the PMIx server to request its local host contact the PMIx server on the remote node that 4 hosts the specified proc to obtain and return a direct modex blob for that proc. 5 Format **Pvthon** PMIx v4.06 def dmodex(args:dict is not None) **Python** IN 7 args Python dictionary containing: • 'proc': Python **proc** of process whose data is being requested (dict) 9 10 • 'directives': Optional list of Python **info** containing directives controlling the operation 11 (list) 12 Returns: 13 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 14 • data - Python bytearray containing the data for the specified process (bytearray) 15 See pmix server dmodex reg fn t for details A.3.3.6 **Publish** 16 17 Summary Publish data per the PMIx API specification. 18 **Format** 19 **Python** PMIx v4.0 def publish(args:dict is not None) 20 **Python** IN 21 args 22 Python dictionary containing: 23 • 'proc': Python proc dictionary of process publishing the data (dict) 24 • 'directives': List of Python **info** containing data and directives (list) 25 Returns: 26 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 27 See pmix server publish fn t for details

A.3.3.5 Direct Modex

1	A.3.3.7	Lookup
2 3		Summary Lookup published data.
4		Format Python
5	PMIx v4.0	def lookup(args:dict is not None) Python
6 7		IN args Python dictionary containing:
8		• 'proc': Python proc of process seeking the data (dict)
9		• 'keys': List of Python strings (list)
10		• 'directives': Optional list of Python info containing directives (list)
11		Returns:
12		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
13		• pdata - List of pdata containing the returned results (list)
14		See pmix_server_lookup_fn_t for details
15	A.3.3.8	Unpublish
16 17		Summary Delete data from the data store.
18	PMIx v4.0	Format Python
19		def unpublish(args:dict is not None) Python
20 21		IN args Python dictionary containing:
22		• 'proc': Python proc of process unpublishing data (dict)
23		• 'keys': List of Python strings (list)
24		• 'directives': Optional list of Python info containing directives (list)
25		Returns:
26		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
27		See pmix server unpublish fn t for details

1	A.3.3.9	Spawn
2		Summary Summary
3		Spawn a set of applications/processes as per the PMIx_Spawn API.
4	PMIx v4.0	Format Python
5	1 11111 14.0	def spawn(args:dict is not None)
		Python —
6 7		IN args Python dictionary containing:
8		• 'proc': Python proc of process making the request (dict)
9		• 'jobinfo': Optional list of Python info job-level directives and information (list)
0		• 'apps': List of Python app describing applications to be spawned (list)
11		Returns:
12		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
13		• nspace - Python string containing namespace of the spawned job (str)
14		See pmix_server_spawn_fn_t for details
15	A.3.3.10	Connect
16 17		Summary Record the specified processes as <i>connected</i> .
8	PMIx v4.0	Format Python
19		def connect(args:dict is not None) Python
20 21		IN args Python dictionary containing:
22		• 'procs': List of Python proc identifying the namespace/rank of the participating processes (list)
24 25		• 'directives': Optional list of Python info containing directives controlling the operation (list)
26		Returns:
27		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
28		See pmix_server_connect_fn_t for details

A.3.3.11 Disconnect 2 Summary 3 Disconnect a previously connected set of processes. **Format Python** PMIx v4.0 5 def disconnect (args:dict is not None) **Python** IN 6 args 7 Python dictionary containing: • 'procs': List of Python proc identifying the namespace/rank of the participating processes 8 9 (list) • 'directives': Optional list of Python **info** containing directives controlling the operation 10 11 (list) 12 Returns: 13 • rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer) 14 See pmix server disconnect fn t for details A.3.3.12 Register Events 15 Summary 16 Register to receive notifications for the specified events. 17 18 Format **Python** PMIx v4.0 def register_events(args:dict is not None) 19 Python IN 20 args Python dictionary containing: 21 • 'codes': List of Python integers (list) 22 23 • 'directives': Optional list of Python **info** containing directives controlling the operation 24 (list) 25 Returns: 26 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 27 See pmix server register events fn t for details

A.3.3.13 Deregister Events 1 2 Summary 3 Deregister to receive notifications for the specified events. **Format** 4 Python PMIx v4.05 def deregister_events(args:dict is not None) Python 6 IN args 7 Python dictionary containing: 8 • 'codes': List of Python integers (list) Returns: 9 • rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer) 10 See pmix_server_deregister_events_fn_t for details 11 A.3.3.14 Notify Event 12 Summary 13 14 Notify the specified range of processes of an event. **Format** 15 **Python** PMIx v4.016 def notify_event(args:dict is not None) Python 17 IN args Python dictionary containing: 18 • 'code': Python integer pmix_status_t (integer) 19 20 • 'source': Python **proc** of process that generated the event (dict) • 'range': Python **range** in which the event is to be reported (integer) 21 22 • 'directives': Optional list of Python info directives (list) 23 Returns: 24 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 25 See pmix_server_notify_event_fn_t for details A.3.3.15 Query 26 Summary 27 28 Query information from the resource manager.

1	PMIx v4.0	Format Python
2	T WILL V V.O	def query(args:dict is not None) Python
3 4		IN args Python dictionary containing:
5		• 'source': Python proc of requesting process (dict)
6		• 'queries': List of Python query directives (list)
7		Returns:
8		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
9		• <i>info</i> - List of Python info containing the returned results (list)
10		See pmix_server_query_fn_t for details
11	A.3.3.16	Tool Connected
12 13		Summary Register that a tool has connected to the server.
14	PMIx v4.0	Format Python
15		<pre>def tool_connected(args:dict is not None)</pre>
16 17		IN args Python dictionary containing:
18		• 'directives': Optional list of Python info info on the connecting tool (list)
19		Returns:
20		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
21		• proc - Python proc containing the assigned namespace:rank for the tool (dict)
22		See pmix_server_tool_connection_fn_t for details
23	A.3.3.17	Log
24 25		Summary Log data on behalf of a client.

1		Format Python
_	PMIx v4.0	
2		def log(args:dict is not None) Python
3		IN args Python dictionary containing:
5		• 'source': Python proc of requesting process (dict)
6		• 'data': Optional list of Python info containing data to be logged (list)
7		• 'directives': Optional list of Python info containing directives (list)
8		Returns:
9		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10		See pmix_server_log_fn_t for details.
11	A.3.3.18	Allocate Resources
12 13		Summary Request allocation operations on behalf of a client.
14	PMIx v4.0	Format Python
15		def allocate(args:dict is not None) Python
16 17		IN args Python dictionary containing:
18		• 'source': Python proc of requesting process (dict)
19		• 'action': Python allocdir specifying requested action (integer)
20		• 'directives': Optional list of Python info containing directives (list)
21		Returns:
22		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
23		• refarginfo - List of Python info containing results of requested operation (list)
24		See pmix_server_alloc_fn_t for details.
25	A.3.3.19	Job Control
26 27		Summary Execute a job control action on behalf of a client.

1		Format
	PMIx v4.0	Python —
2		<pre>def job_control(args:dict is not None)</pre>
3 4		IN args Python dictionary containing:
5		• 'source': Python proc of requesting process (dict)
6		• 'targets': List of Python proc specifying target processes (list)
7		• 'directives': Optional list of Python info containing directives (list)
8		Returns:
9		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
10		See pmix_server_job_control_fn_t for details.
11	A.3.3.20	Monitor
12 13		Summary Request that a client be monitored for activity.
14	PMIx v4.0	Format Python
15		def monitor(args:dict is not None)
		Python
16 17		IN args Python dictionary containing:
18		• 'source': Python proc of requesting process (dict)
19		• 'monitor': Python info attribute indicating the type of monitor being requested (dict)
20 21		• 'error': Status code to be used when generating an event notification (integer) alerting that the monitor has been triggered.
22		• 'directives': Optional list of Python info containing directives (list)
23		Returns:
24		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
25		See pmix_server_monitor_fn_t for details.
26	A.3.3.21	Get Credential
27 28		Summary Request a credential from the host environment.

1		Format Python
_	PMIx v4.0	
2		def get_credential(args:dict is not None) Python
3		IN args Python dictionary containing:
5		• 'source': Python proc of requesting process (dict)
6		• 'directives': Optional list of Python info containing directives (list)
7		Returns:
8		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
9		• cred - Python byteobject containing returned credential (dict)
10		• info - List of Python info containing any additional info about the credential (list)
11		See pmix_server_get_cred_fn_t for details.
12	A.3.3.22	Validate Credential
13 14		Summary Request validation of a credential
15	PMIx v4.0	Format Python
16		<pre>def validate_credential(args:dict is not None)</pre>
17 18		IN args Python dictionary containing:
19		• 'source': Python proc of requesting process (dict)
20		• 'credential': Python byteobject containing credential (dict)
21		• 'directives': Optional list of Python info containing directives (list)
22		Returns:
23		• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer)
24		• info - List of Python info containing any additional info from the credential (list)
25		See pmix_server_validate_cred_fn_t for details.

1 2 Summary 3 Request the specified IO channels be forwarded from the given array of processes. **Format Python** PMIx v4.05 def iof pull(args:dict is not None) **Python** IN 6 args 7 Python dictionary containing: • 'sources': List of Python proc of processes whose IO is being requested (list) 8 9 • 'channels': Bitmask of Python **channel** identifying IO channels to be forwarded (integer) 10 • 'directives': Optional list of Python **info** containing directives (list) Returns: 11 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 12 See pmix server iof fn t for details. 13 A.3.3.24 IO Push Summary 15 Pass standard input data to the host environment for transmission to specified recipients. 16 **Format** 17 **Pvthon** PMIx v4.0 def iof_push(args:dict is not None) 18 **Python** 19 IN args Python dictionary containing: 20 21 • 'source': Python **proc** of process whose input is being forwarded (dict) 22 • 'payload': Python byteobject containing input bytes (dict) 23 • 'targets': List of **proc** of processes that are to receive the payload (list) • 'directives': Optional list of Python **info** containing directives (list) 24 25 Returns: 26 • rc - PMIX SUCCESS or a PMIx error code indicating the operation failed (integer) 27 See pmix server stdin fn t for details.

A.3.3.23 IO Forward

A.3.3.25 Group Operations 1 2 Summary 3 Request group operations (construct, destruct, etc.) on behalf of a set of processes. **Format Python** PMIx v4.0 5 def group (args:dict is not None) **Python** IN 6 args 7 Python dictionary containing: • 'op': Operation host is to perform on the specified group (integer) 8 9 • 'group': String identifier of target group (str) 10 • 'procs': List of Python **proc** of participating processes (dict) • 'directives': Optional list of Python **info** containing directives (list) 11 Returns: 12 • rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer) 13 14 • refarginfo - List of Python **info** containing results of requested operation (list) See pmix server grp fn t for details. 15 A.3.3.26 **Fabric Operations** 16 Summary 17 Request fabric-related operations (e.g., information on a fabric) on behalf of a tool or other process. 18 19 Format **Python** PMIx v4.0 20 def fabric (args: dict is not None) **Python** IN 21 args 22 Python dictionary containing: 23 • 'source': Python proc of requesting process (dict) 24 • 'index': Identifier of the fabric being operated upon (integer) 25 'op': Operation host is to perform on the specified fabric (integer) 26 • 'directives': Optional list of Python **info** containing directives (list) 27 Returns:

• rc - PMIX_SUCCESS or a PMIx error code indicating the operation failed (integer) 1 2 • refarginfo - List of Python **info** containing results of requested operation (list) 3 See pmix server fabric fn t for details. A.4 PMIxClient The client Python class is by far the richest in terms of APIs as it houses all the APIs that an 5 6 application might utilize. Due to the datatype translation requirements of the C-Python interface, 7 only the blocking form of each API is supported – providing a Python callback function directly to 8 the C interface underlying the bindings was not a supportable option. Client.init A.4.1 Summary 10 11 Initialize the PMIx client library after obtaining a new PMIxClient object. 12 **Format** Python PMIx v4.0 13 rc, proc = myclient.init(info:list) Python IN 14 info List of Python info dictionaries (list) 15 Returns: 16 17 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) • proc - a Python proc dictionary (dict) 18 19 See PMIx_Init for description of all relevant attributes and behaviors. Client.initialized A.4.2 Format 21 **Python** PMIx v4.0 22 rc = myclient.initialized() **Python** Returns: 23 24 \bullet rc - a value of 1 (true) will be returned if the PMIx library has been initialized, and 0 (false) 25 otherwise (integer)

See PMIx Initialized for description of all relevant attributes and behaviors.

1 A.4.3 Client.get_version

2	PMIx v4.0	Format Python —
3	111111111111	<pre>vers = myclient.get_version()</pre>
4		Returns:
5		• <i>vers</i> - Python string containing the version of the PMIx library (e.g., "3.1.4") (integer)
6		See PMIx_Get_version for description of all relevant attributes and behaviors.
7	A.4.4	Client.finalize
8 9		Summary Finalize the PMIx client library.
10	PMIx v4.0	Format
11	1 1/11/1 1/4.0	rc = myclient.finalize(info:list) Python
12 13		IN info List of Python info dictionaries (list)
14		Returns:
15		• <i>rc</i> - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
16		See PMIx_Finalize for description of all relevant attributes and behaviors.
17	A.4.5	Client.abort
18 19		Summary Request that the provided list of processes be aborted.

```
Format
1
                                                       Python
   PMIx v4.0
2
               rc = myclient.abort(status:integer, msg:str, targets:list)
                                                       Python
               IN
3
                    status
 4
                    PMIx status to be returned on exit (integer)
5
               IN
                    String message to be printed (string)
6
               IN
                    targets
 7
                    List of Python proc dictionaries (list)
8
9
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
10
               See PMIx_Abort for description of all relevant attributes and behaviors.
11
              Client.store_internal
    A.4.6
               Summary
13
14
               Store some data locally for retrieval by other areas of the process
               Format
15
                                                       Python
   PMIx v4.0
               rc = myclient.store_internal(proc:dict, key:str, value:dict)
16
                                                       Python
17
               IN
                    proc
                    Python proc dictionary of the process being referenced (dict)
18
19
               IN
                    String key of the data (string)
20
               IN
                    value
21
22
                    Python value dictionary (dict)
23
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24
               See PMIx _Store_internal for details.
25
              Client.put
    A.4.7
               Summary
27
28
               Push a key/value pair into the client's namespace.
```

Format 1 **Python** PMIx v4.0 2 rc = myclient.put(scope:integer, key:str, value:dict) **Python** IN 3 scope 4 Scope of the data being posted (integer) 5 IN String key of the data (string) 6 IN value 7 Python **value** dictionary (dict) 8 9 Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 10 See PMIx_Put for description of all relevant attributes and behaviors. 11 Client.commit A.4.8 Summary 13 14 Push all previously **PMIxClient.put** values to the local PMIx server. **Format** 15 **Python** PMIx v4.0 16 rc = myclient.commit() **Python** 17 Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 18 See PMIx_Commit for description of all relevant attributes and behaviors. 19 A.4.9 Client.fence 21 Summary 22 Execute a blocking barrier across the processes identified in the specified list.

```
Format
 1
                                                       Python
   PMIx v4.0
 2
               rc = myclient.fence(peers:list, directives:list)
                                                       Python
               IN
 3
                    peers
 4
                    List of Python proc dictionaries (list)
                    directives
 5
               IN
                    List of Python info dictionaries (list)
 6
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 9
               See PMIx Fence for description of all relevant attributes and behaviors.
    A.4.10
                Client.get
               Summary
11
               Retrieve a key/value pair.
12
13
               Format
                                                       Python
   PMIx v4.0
               rc, val = myclient.get(proc:dict, key:str, directives:list)
14
                                                       Python
               IN
15
                    proc
                    Python proc whose data is being requested (dict)
16
17
               IN
                    Python string key of the data to be returned (str)
18
19
               IN
                    directives
                    List of Python info dictionaries (list)
20
               Returns:
21
22
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • val - Python value containing the returned data (dict)
23
24
               See PMIx_Get for description of all relevant attributes and behaviors.
    A.4.11
               Client.publish
               Summary
26
27
               Publish data for later access via PMIx Lookup.
```

```
Format
 1
                                                       Python
   PMIx v4.0
 2
               rc = myclient.publish(directives:list)
                                                       Python
               IN
 3
                    directives
                    List of Python info dictionaries containing data to be published and directives (list)
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
               See PMIx_Publish for description of all relevant attributes and behaviors.
    A.4.12
                Client.lookup
               Summary
 9
               Lookup information published by this or another process with PMIx_Publish.
10
               Format
11
                                                       Python
   PMIx v4.0
12
               rc, info = myclient.lookup(pdata:list,
                                                                 directives: list)
                                                       Python
13
               IN
                    pdata
                    List of Python pdata dictionaries identifying data to be retrieved (list)
14
               IN
                    directives
15
                    List of Python info dictionaries (list)
16
17
               Returns:
18
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • info - Python list of info containing the returned data (list)
19
20
               See PMIx_Lookup for description of all relevant attributes and behaviors.
    A.4.13 Client.unpublish
22
               Summary
```

Delete data published by this process with **PMIx Publish**.

```
Format
1
                                                      Python
   PMIx v4.0
2
               rc = myclient.unpublish(keys:list, directives:list)
                                                       Python
               IN
3
                    keys
 4
                    List of Python string keys identifying data to be deleted (list)
 5
               IN
                    directives
                    List of Python info dictionaries (list)
 6
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               See PMIx Unpublish for description of all relevant attributes and behaviors.
    A.4.14
                Client.spawn
               Summary
11
               Spawn a new job.
12
13
               Format
                                                      Python
   PMIx v4.0
               rc,nspace = myclient.spawn(jobinfo:list, apps:list)
14
                                                       Python
               IN
                    jobinfo
15
                    List of Python info dictionaries (list)
16
17
               IN
                    apps
                    List of Python app dictionaries (list)
18
19
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20
21
               • nspace - Python nspace of the new job (dict)
22
               See PMIx_Spawn for description of all relevant attributes and behaviors.
    A.4.15
                Client.connect
               Summary
24
25
               Connect namespaces.
```

```
Format
1
                                                      Python
   PMIx v4.0
2
               rc = myclient.connect(peers:list, directives:list)
                                                      Python
               IN
3
                    peers
 4
                   List of Python proc dictionaries (list)
                    directives
 5
               IN
                   List of Python info dictionaries (list)
 6
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               See PMIx Connect for description of all relevant attributes and behaviors.
    A.4.16
                Client.disconnect
               Summary
11
               Disconnect namespaces.
12
13
               Format
                                                      Python
   PMIx v4.0
               rc = myclient.disconnect(peers:list, directives:list)
14
                                                      Python
               IN
15
                    peers
                   List of Python proc dictionaries (list)
16
17
               IN
                    directives
                   List of Python info dictionaries (list)
18
               Returns:
19
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20
21
               See PMIx_Disconnect for description of all relevant attributes and behaviors.
    A.4.17 Client.resolve_peers
               Summary
23
24
               Return list of processes within the specified nspace on the given node.
```

1		Format
	PMIx v4.0	Python —
2		rc,procs = myclient.resolve_peers(node:str, nspace:str)
3 4 5 6		IN node Name of node whose processes are being requested (str) IN nspace Python nspace whose processes are to be returned (str)
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		• procs - List of Python proc dictionaries (list)
10		See PMIx_Resolve_peers for description of all relevant attributes and behaviors.
11	A.4.18	Client.resolve_nodes
12 13		Summary Return list of nodes hosting processes within the specified nspace .
14	PMIx v4.0	Format Python
15		<pre>rc, nodes = myclient.resolve_nodes(nspace:str)</pre>
16 17		IN nspace Python nspace (str)
18		Returns:
19		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20		• nodes - List of Python string node names (list)
21		See PMIx_Resolve_nodes for description of all relevant attributes and behaviors.
22	A.4.19	Client.query
23 24		Summary Query information about the system in general.

```
Format
 1
                                                       Python
   PMIx v4.0
 2
               rc,info = myclient.query(queries:list)
                                                       Python
               IN
 3
                    queries
                    List of Python query dictionaries (list)
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
               • info - List of Python info containing results of the query (list)
               See PMIx Query info for description of all relevant attributes and behaviors.
 8
    A.4.20
                Client.log
               Summary
10
               Log data to a central data service/store.
11
12
               Format
                                                       Python
   PMIx v4.0
13
               rc = myclient.log(data:list, directives:list)
                                                       Python
14
               IN
                    data
                    List of Python info (list)
15
               IN
                    directives
16
                    Optional list of Python info (list)
17
18
               Returns:
19
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20
               See PMIx_Log for description of all relevant attributes and behaviors.
    A.4.21
                Client.allocation_request
22
               Summary
23
               Request an allocation operation from the host resource manager.
```

```
Format
1
                                                       Python
   PMIx v4.0
2
               rc, info = myclient.allocation_request(request:integer, directives:list)
                                                       Python
               IN
3
                    request
 4
                    Python allocdir specifying requested operation (integer)
 5
               IN
                    directives
                    List of Python info describing request (list)
6
               Returns:
8
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               • info - List of Python info containing results of the request (list)
10
               See PMIx_Allocation_request for description of all relevant attributes and behaviors.
    A.4.22
                Client.job ctrl
               Summary
12
               Request a job control action.
13
               Format
14
                                                       Python
   PMIx v4.0
               rc,info = myclient.job_ctrl(targets:list, directives:list)
15
                                                       Python
               IN
16
                    targets
                    List of Python proc specifying targets of requested operation (integer)
17
                    directives
18
               IN
                    List of Python info describing operation to be performed (list)
19
               Returns:
20
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
21
               • info - List of Python info containing results of the request (list)
22
23
               See PMIx_Job_control for description of all relevant attributes and behaviors.
                Client.monitor
               Summary
25
26
               Request that something be monitored.
```

```
Format
1
                                                       Python
   PMIx v4.0
2
               rc, info = myclient.monitor(monitor:dict, error_code:integer, directives:list
                                                       Python
               IN
3
                    monitor
 4
                    Python info specifying specifying the type of monitor being requested (dict)
5
               IN
                    error code
                    Status code to be used when generating an event notification alerting that the monitor has
6
 7
                    been triggered (integer)
               IN
                   directives
8
9
                    List of Python info describing request (list)
               Returns:
10
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
11
               • info - List of Python info containing results of the request (list)
12
13
               See PMIx Process monitor for description of all relevant attributes and behaviors.
                Client.get credential
    A.4.24
               Summary
15
               Request a credential from the PMIx server/SMS.
16
               Format
17
                                                       Python
   PMIx v4.0
               rc,cred = myclient.get_credential(directives:list)
18
                                                       Python
               IN
19
                    directives
20
                    Optional list of Python info describing request (list)
21
               Returns:
22
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • cred - Python byteobject containing returned credential (dict)
23
               See PMIx_Get_credential for description of all relevant attributes and behaviors.
24
    A.4.25
                Client.validate_credential
26
               Summary
27
               Request validation of a credential by the PMIx server/SMS.
```

1		Format
	PMIx v4.0	Python —
2		rc,info = myclient.validate_credential(cred:dict, directives:list) Python
3		IN cred Python byteobject containing credential (dict)
5 6		IN directives Optional list of Python info describing request (list)
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		• <i>info</i> - List of Python info containing additional results of the request (list)
10		See PMIx_Validate_credential for description of all relevant attributes and behaviors.
11	A.4.26	Client.group_construct
12 13 14		Summary Construct a new group composed of the specified processes and identified with the provided group identifier.
15		Format Python
	PMIx v4.0	
16 17		<pre>rc,info = myclient.construct_group(grp:string,</pre>
18		IN grp
19 20		Python string identifier for the group (str) IN members
21		List of Python proc dictionaries identifying group members (list)
22 23		IN directives Optional list of Python info describing request (list)
24		Returns:
25		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
26		• <i>info</i> - List of Python info containing results of the request (list)
27		See PMIx_Group_construct for description of all relevant attributes and behaviors.

A.4.27 Client.group_invite

```
Summary
 2
 3
               Explicitly invite specified processes to join a group.
               Format
                                                       Pvthon
   PMIx v4.0
 5
               rc, info = myclient.group invite(grp:string,
 6
                                               members:list, directives:list)
                                                       Python
 7
               IN
                    grp
                    Python string identifier for the group (str)
 8
 9
               IN
                    members
                    List of Python proc dictionaries identifying processes to be invited (list)
10
11
               IN
                    directives
12
                    Optional list of Python info describing request (list)
               Returns:
13
14
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • info - List of Python info containing results of the request (list)
15
               See PMIx_Group_invite for description of all relevant attributes and behaviors.
16
    A.4.28
                Client.group join
               Summary
18
               Respond to an invitation to join a group that is being asynchronously constructed.
19
               Format
20
                                                       Python
   PMIx v4.0
21
               rc, info = myclient.group_join(grp:string,
22
                                               leader:dict, opt:integer,
                                               directives:list)
23
                                                       Python
24
               IN
                     grp
                    Python string identifier for the group (str)
25
26
               IN
27
                    Python proc dictionary identifying process leading the group (dict)
               IN
28
                    One of the pmix_group_opt_t values indicating decline/accept (integer)
29
               IN
                     directives
30
31
                    Optional list of Python info describing request (list)
```

```
Returns:
 1
 2
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 3
               • info - List of Python info containing results of the request (list)
 4
               See PMIx_Group_join for description of all relevant attributes and behaviors.
    A.4.29
                Client.group_leave
               Summarv
 6
 7
               Leave a PMIx Group.
               Format
 8
                                                       Python
   PMIx v4.0
 9
               rc = myclient.group leave(grp:string, directives:list)
                                                       Python
               IN
10
                    grp
11
                    Python string identifier for the group (str)
12
               IN
                    directives
                    Optional list of Python info describing request (list)
13
14
               Returns:
15
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               See PMIx_Group_leave for description of all relevant attributes and behaviors.
16
    A.4.30
                Client.group destruct
17
               Summary
18
               Destruct a PMIx Group.
19
               Format
20
                                                       Python
   PMIx v4.0
21
               rc = myclient.group_destruct(grp:string, directives:list)
                                                       Python
               IN
22
                    Python string identifier for the group (str)
23
               IN
                    directives
24
                    Optional list of Python info describing request (list)
25
26
               Returns:
27
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
28
               See PMIx Group destruct for description of all relevant attributes and behaviors.
```

A.4.31 Client.register event handler Summary 3 Register an event handler to report events. **Format Python** PMIx v4.0 5 rc,id = myclient.register_event_handler(codes:list, directives: list, cbfunc) 6 Python IN codes 7 List of Python integer status codes that should be reported to this handler (llist) 8 9 IN directives 10 Optional list of Python **info** describing request (list) IN 11 Python **evhandler** to be called when event is received (func) 12 13 Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 14 • *id* - PMIx reference identifier for handler (integer) 15 See PMIx_Register_event_handler for description of all relevant attributes and behaviors. 16 A.4.32 Client.deregister_event_handler Summary 18 19 Deregister an event handler. **Format** 20 **Python** PMIx v4.0 myclient.deregister_event_handler(id:integer) 21 Python

See PMIx_Deregister_event_handler for description of all relevant attributes and

PMIx reference identifier for handler (integer)

IN

id

Returns: None

behaviors.

22

23

24

25

1 A.4.33 Client.notify_event

2		Summary Report an event for notification via any registered handler.
4	PMIx v4.0	Format Python
5 6 7		<pre>rc = myclient.notify_event(status:integer, source:dict,</pre>
8 9 10 11 12		PMIx status code indicating the event being reported (integer) IN source Python proc of the process that generated the event (dict) IN range Python range in which the event is to be reported (integer)
13 14		Optional list of Python info dictionaries describing the event (list)
15 16		Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
17		See PMIx_Notify_event for description of all relevant attributes and behaviors.
18	A.4.34	Client.fabric_register
19 20		Summary Register for access to fabric-related information, including communication cost matrix.
21	PMIx v4.0	Format Python
22		rc,idx,fabricinfo = myclient.fabric_register(directives:list) Python
23 24		IN directives Optional list of Python info containing directives (list)
25		Returns:
26		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27 28		 idx - Index of the registered fabric (integer) fabricinfo - List of Python info containing fabric info (list)
29		See PMIx_Fabric_register for details.

A.4.35 Client.fabric update Summary 3 Update fabric-related information, including communication cost matrix. **Format** Python PMIx v4.0 5 rc,fabricinfo = myclient.fabric_update(idx:integer) **Python** IN idx 6 7 Index of the registered fabric (list) 8 Returns: 9 • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) • fabricinfo - List of Python info containing updated fabric info (list) 10 See PMIx_Fabric_update for details. 11 A.4.36 Client.fabric_deregister 13 Summary 14 Deregister fabric. **Format** 15 PMIx v4.0 rc = myclient.fabric_deregister(idx:integer) 16 **Python** IN idx 17 Index of the registered fabric (list) 18 Returns: 19 20 • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) 21 See PMIx Fabric deregister for details.

A.4.37 Client.load topology

Summary

Load the local hardware topology into the PMIx library.

```
Format
 1
                                                       Python
   PMIx v4.0
 2
               rc = myclient.load_topology()
                                                       Python
 3
               Returns:
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 5
               See PMIx Load topology for details - note that the topology loaded into the PMIx library may
 6
               be utilized by PMIx and other libraries, but is not directly accessible by Python.
    A.4.38
                Client.get_relative_locality
               Summary
 8
               Get the relative locality of two local processes.
 9
               Format
10
                                                       Python
   PMIx v4.0
               rc, locality = myclient.get_relative_locality(loc1:str, loc2:str)
11
                                                       Python
               IN
                    loc1
12
                    Locality string of a process (str)
13
               IN
                    loc2
14
15
                    Locality string of a process (str)
               Returns:
16
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
17
18
               • locality - locality list containing the relative locality of the two processes (list)
19
               See PMIx_Get_relative_locality for details.
    A.4.39
                Client.get_cpuset
               Summary
21
```

Get the PU binding bitmap of the current process.

```
Format
1
                                                     Python
   PMIx v4.0
2
              rc,cpuset = myclient.get_cpuset(ref:integer)
                                                     Python
              IN
3
                   ref
                   bindenv binding envelope to be used (integer)
 5
              Returns:
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
              • cpuset - cpuset containing the source and bitmap of the cpuset (dict)
              See PMIx Get cpuset for details.
8
               Client.parse cpuset string
    A.4.40
              Summary
10
              Parse the PU binding bitmap from its string representation.
11
12
              Format
                                                     Python
   PMIx v4.0
13
              rc,cpuset = myclient.parse cpuset string(cpuset:string)
                                                     Pvthon
14
              IN
                   cpuset
                   String returned by PMIxServer.generate_cpuset_string (string)
15
16
              Returns:
17
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
              • cpuset - cpuset containing the source and bitmap of the cpuset (dict)
18
              See PMIx_Parse_cpuset_string for details.
19
               Client.compute_distances
    A.4.41
20
              Summary
21
              Compute distances from specified process location to local devices.
22
```

1		Format Python —
_	PMIx v4.0	
2		rc, distances = myclient.compute_distances(cpuset:dict, info:list) Python
3 4 5		IN cpuset cpuset describing the location of the process (dict) IN info
6 7		List of info dictionaries describing the devices whose distance is to be computed (list) Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9 10		• <i>distances</i> - List of devdist structures containing the distances from the caller to the specified devices (list)
11 12		See PMIx_Compute_distances for details. Note that distances can only be computed against the local topology.
13	A.4.42	Client.error_string
14 15		Summary Pretty-print string representation of pmix_status_t.
16	PMIx v4.0	Format Python
17	1 W11 V4.0	<pre>rep = myclient.error_string(status:integer)</pre>
18 19		IN status PMIx status code (integer)
20		Returns:
21		• rep - String representation of the provided status code (str)
22		See PMIx_Error_string for further details.
23	A.4.43	Client.proc_state_string
24 25		Summary Pretty-print string representation of pmix_proc_state_t.

```
Format
1
                                                    Python
   PMIx v4.0
2
              rep = myclient.proc_state_string(state:integer)
                                                    Python
 3
              IN
                   state
                   PMIx process state code (integer)
 4
              Returns:
              • rep - String representation of the provided process state (str)
 6
 7
              See PMIx_Proc_state_string for further details.
    A.4.44
               Client.scope string
              Summary
9
              Pretty-print string representation of pmix scope t.
10
              Format
11
                                                    Python
   PMIx v4.0
12
              rep = myclient.scope_string(scope:integer)
                                                    Python
13
              IN
                   scope
14
                   PMIx scope value (integer)
15
              Returns:
              • rep - String representation of the provided scope (str)
16
17
              See PMIx Scope string for further details
    A.4.45
               Client.persistence_string
18
              Summary
19
              Pretty-print string representation of pmix_persistence_t.
20
              Format
21
                                                    Python
   PMIx v4.0
22
              rep = myclient.persistence_string(persistence:integer)
                                                    Python
              IN
23
                 persistence
                   PMIx persistence value (integer)
24
25
              Returns:
26
              • rep - String representation of the provided persistence (str)
27
              See PMIx Persistence string for further details.
```

A.4.46 Client.data range string Summary 3 Pretty-print string representation of pmix_data_range_t. **Format Python** PMIx v4.0 5 rep = myclient.data_range_string(range:integer) Python IN 6 range PMIx data range value (integer) 7 Returns: 9 • rep - String representation of the provided data range (str) See PMIx_Data_range_string for further details. 10 A.4.47 Client.info directives string Summary 12 13 Pretty-print string representation of **pmix_info_directives_t**. **Format** 14 **Python** PMIx v4.0 15 rep = myclient.info_directives_string(directives:bitarray) **Python** IN 16 directives PMIx info directives value (bitarray) 17 Returns: 18 • rep - String representation of the provided info directives (str) 19 20 See PMIx Info directives string for further details. A.4.48 Client.data type string

21 A.4.40 Chefft.data_type_String

22 Summary

23

Pretty-print string representation of pmix_data_type_t.

```
Format
1
                                                    Python
   PMIx v4.0
2
              rep = myclient.data_type_string(dtype:integer)
                                                    Python
 3
              IN
                   dtype
                   PMIx datatype value (integer)
 4
              Returns:
              • rep - String representation of the provided datatype (str)
 6
 7
              See PMIx_Data_type_string for further details.
    A.4.49
               Client.alloc directive string
8
              Summary
9
              Pretty-print string representation of pmix alloc directive t.
10
              Format
11
                                                    Python
   PMIx v4.0
12
              rep = myclient.alloc_directive_string(adir:integer)
                                                    Python
13
              IN
                   adir
14
                   PMIx allocation directive value (integer)
15
              Returns:
              • rep - String representation of the provided allocation directive (str)
16
17
              See PMIx Alloc directive string for further details.
    A.4.50
               Client.iof channel string
18
              Summary
19
20
              Pretty-print string representation of pmix iof channel t.
              Format
21
                                                    Python
   PMIx v4.0
22
              rep = myclient.iof channel string(channel:bitarray)
                                                    Python
              IN
23
                   channel
                   PMIx IOF channel value (bitarray)
24
25
              Returns:
26
              • rep - String representation of the provided IOF channel (str)
27
              See PMIx IOF channel string for further details.
```

A.4.51 Client.job state string Summary 3 Pretty-print string representation of pmix_job_state_t. **Format Python** PMIx v4.0 rep = myclient.job_state_string(state:integer) 5 **Python** IN state 6 7 PMIx job state value (integer) Returns: 9 • rep - String representation of the provided job state (str) See PMIx_Job_state_string for further details. 10 A.4.52 Client.get attribute string Summary 12 13 Pretty-print string representation of a PMIx attribute. **Format** 14 **Python** PMIx v4.0 rep = myclient.get_attribute_string(attribute:str) 15 **Python** IN 16 attribute PMIx attribute name (string) 17 Returns: 18 • rep - String representation of the provided attribute (str) 19 20 See PMIx Get attribute string for further details.

21 A.4.53 Client.get attribute name

Summary

22 23

Pretty-print name of a PMIx attribute corresponding to the provided string.

```
Format
1
                                                    Python
   PMIx v4.0
2
              rep = myclient.get_attribute_name(attribute:str)
                                                    Python
 3
              IN
                   attributestring
                   Attribute string (string)
 4
              Returns:
              • rep - Attribute name corresponding to the provided string (str)
 6
 7
              See PMIx Get attribute name for further details.
    A.4.54
               Client.link state string
8
              Summary
9
              Pretty-print string representation of pmix link state t.
10
              Format
11
                                                    Python
   PMIx v4.0
12
              rep = myclient.link_state_string(state:integer)
                                                    Python
13
                   state
14
                   PMIx link state value (integer)
15
              Returns:
              • rep - String representation of the provided link state (str)
16
17
              See PMIx_Link_state_string for further details.
    A.4.55
               Client.device type string
18
              Summary
19
20
              Pretty-print string representation of pmix_device_type_t.
              Format
21
                                                    Python
   PMIx v4.0
22
              rep = myclient.device_type_string(type:bitarray)
                                                    Python
              IN
23
                   type
                   PMIx device type value (bitarray)
24
25
              Returns:
26
              • rep - String representation of the provided device type (str)
27
              See PMIx_Device_type_string for further details.
```

A.4.56 Client.progress

2 Summary

Progress the PMIx library.

4 Format

PMIx v4.0

3

5

6

myclient.progress()

Python

lyclienc.progress()

Python

See **PMIx_Progress** for further details.

7 A.5 PMIxServer

8 The server Python class inherits the Python "client" class as its parent. Thus, it includes all client functions in addition to the ones defined in this section.

o A.5.1 Server.init

11 Summary

12 Initialize the PMIx server library after obtaining a new PMIxServer object.

13 Format

PMIx v4.0

15 16

17

18

19

21

22

25

rc = myserver.init(directives:list, map:dict)

Python

IN directives

List of Python **info** dictionaries (list)

IN map

Python dictionary key-function pairs that map **server module** callback functions to provided implementations (see **pmix_server_module_t**) (dict)

Python

20 Returns:

• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)

See PMIx_server_init for description of all relevant attributes and behaviors.

23 A.5.2 Server.finalize

24 Summary

Finalize the PMIx server library.

```
Format
1
                                                     Python
   PMIx v4.0
2
               rc = myserver.finalize()
                                                      Python
               Returns:
3
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 5
               See PMIx server finalize for details.
    A.5.3
              Server.generate_regex
               Summary
 7
               Generate a regular expression representation of the input strings.
9
               Format
                                                      Python
   PMIx v4.0
10
               rc,regex = myserver.generate_regex(input:list)
                                                      Python
               IN
                    input
11
                   List of Python strings (e.g., node names) (list)
12
13
               Returns:
14
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
               • regex - Python bytearray containing regular expression representation of the input list
15
16
                 (bytearray)
17
               See PMIx_generate_regex for details.
    A.5.4
              Server.generate ppn
19
               Summary
               Generate a regular expression representation of the input strings.
20
```

1	PMIx v4.0	Format Python —
2		rc,regex = myserver.generate_ppn(input:list) Python
3 4 5		IN input List of Python strings, each string consisting of a comma-delimited list of ranks on each node, with the strings being in the same order as the node names provided to "generate_regex" (list)
6		Returns:
7		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
8 9		• regex - Python bytearray containing regular expression representation of the input list (bytearray)
10		See PMIx_generate_ppn for details.
11	A.5.5	Server.generate_locality_string
12 13		Summary Generate a PMIx locality string from a given cpuset.
14	PMIx v4.0	Format Python
15		rc,locality = myserver.generate_locality_string(cpuset:dict) Python
16 17		IN cset cpuset containing the bitmap of assigned PUs (dict)
18		Returns:
19		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
20		• <i>locality</i> - String representation of the PMIx locality corresponding to the input bitmap (string)
21		See PMIx_server_generate_locality_string for details.
22	A.5.6	Server.generate_cpuset_string
23 24		Summary Generate a PMIx string representation of the provided cpuset.

```
Format
1
                                                     Python
   PMIx v4.0
2
              rc,cpustr = myserver.generate_cpuset_string(cpuset:dict)
                                                     Python
              IN
3
                   cset
                   cpuset containing the bitmap of assigned PUs (dict)
              Returns:
 5
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
              • cpustr - String representation of the input bitmap (string)
 7
              See PMIx server generate cpuset string for details.
 8
    A.5.7
              Server.register nspace
              Summary
10
              Setup the data about a particular namespace.
11
12
              Format
                                                    Python
   PMIx v4.0
              rc = myserver.register_nspace(nspace:str,
13
14
                                                    nlocalprocs:integer,
15
                                                     directives: list)
                                                     Python
              IN
16
                   nspace
17
                   Python string containing the namespace (str)
              IN
                   nlocalprocs
18
19
                   Number of local processes (integer)
20
              IN
                   directives
                   List of Python info dictionaries (list)
21
22
              Returns:
23
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
24
               See PMIx_server_register_nspace for description of all relevant attributes and behaviors.
    A.5.8
              Server.deregister nspace
26
              Summary
27
              Deregister a namespace.
```

1		Format
	<i>PMIx v4.0</i>	Python —
2		myserver.deregister_nspace(nspace:str) Python
3 4		IN nspace Python string containing the namespace (str)
5		Returns: None
6		See PMIx_server_deregister_nspace for details.
7	A.5.9	Server.register_resources
8		Summary
9		Register non-namespace related information with the local PMIx library
10		Format
	PMIx v4.0	Python
11		myserver.register_resources(directives:list)
		Python
12		IN directives
13		List of Python info dictionaries (list)
14		Returns: None
15		See PMIx_server_register_resources for details.
16	A.5.10	Server.deregister_resources
17		Summary
18		Remove non-namespace related information from the local PMIx library
19		Format
	PMIx v4.0	Python —
20		myserver.deregister_resources(directives:list) Python
21		IN directives
22		List of Python info dictionaries (list)
23		Returns: None
24		See PMIx_server_deregister_resources for details.

A.5.11 Server.register client Summary Register a client process with the PMIx server library. 3 **Format Python** PMIx v4.0 5 rc = myserver.register_client(proc:dict, uid:integer, gid:integer) Python IN 6 proc 7 Python **proc** dictionary identifying the client process (dict) 8 IN 9 Linux uid value for user executing client process (integer) 10 IN Linux gid value for user executing client process (integer) 11 12 Returns: • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer) 13 See PMIx_server_register_client for details. 14 A.5.12 Server.deregister_client 16 Summary Deregister a client process and purge all data relating to it. 17 Format 18 **Python** PMIx v4.0 myserver.deregister_client(proc:dict) 19 **Python** IN proc 20 Python **proc** dictionary identifying the client process (dict) 21 Returns: None 22 23 See PMIx_server_deregister_client for details. A.5.13 Server.setup fork

Summary

Setup the environment of a child process that is to be forked by the host.

1	PMIx v4.0	Format Python
2		<pre>rc = myserver.setup_fork(proc:dict, envin:dict)</pre>
3 4 5 6		IN proc Python proc dictionary identifying the client process (dict) INOUT envin Python dictionary containing the environment to be passed to the client (dict)
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		See PMIx_server_setup_fork for details.
10	A.5.14	Server.dmodex_request
11 12		Summary Function by which the host server can request modex data from the local PMIx server.
13	PMIx v4.0	Format Python
14		rc,data = myserver.dmodex_request(proc:dict) Python
15 16		IN proc Python proc dictionary identifying the process whose data is requested (dict)
17		Returns:
18		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19		• data - Python byteobject containing the returned data (dict)
20		See PMIx_server_dmodex_request for details.
21	A.5.15	Server.setup_application
22 23 24		Summary Function by which the resource manager can request application-specific setup data prior to launch of a <i>job</i> .

1		Format
	PMIx v4.0	Python —
2		rc,info = myserver.setup_application(nspace:str, directives:list)
		Python —
3 4		Namespace whose setup information is being requested (str)
5		IN directives
6		Python list of info directives
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		• <i>info</i> - Python list of info dictionaries containing the returned data (list)
10		See PMIx_server_setup_application for details.
11	A.5.16	Server.register_attributes
12		Summary
13		Register host environment attribute support for a function.
14		Format
14	PMIx v4.0	Python
14 15	PMIx v4.0	<pre>Python rc = myserver.register_attributes(function:str, attrs:list)</pre>
	PMIx v4.0	<pre>Python rc = myserver.register_attributes(function:str, attrs:list)</pre>
15 16	PMIx v4.0	<pre>Python rc = myserver.register_attributes(function:str, attrs:list)</pre>
15 16 17	PMIx v4.0	<pre>Python rc = myserver.register_attributes(function:str, attrs:list)</pre>
15 16	PMIx v4.0	<pre>Python rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs</pre>
15 16 17 18	PMIx v4.0	rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes
15 16 17 18	PMIx v4.0	rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns:
15 16 17 18 19 20 21	PMIx v4.0	Python rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15 16 17 18 19 20	PMIx v4.0	rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns:
15 16 17 18 19 20 21	PMIx v4.0 A.5.17	Python rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15 16 17 18 19 20 21 22		Python rc = myserver.register_attributes (function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns: rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) See PMIx_Register_attributes for details. Server.setup_local_support
15 16 17 18 19 20 21 22		Python rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) See PMIx_Register_attributes for details.
15 16 17 18 19 20 21 22 23 24		rc = myserver.register_attributes(function:str, attrs:list) Python IN function Name of the function (str) IN attrs Python list of regattr describing the supported attributes Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) See PMIx_Register_attributes for details. Server.setup_local_support Summary

```
Format
1
                                                      Python
   PMIx v4.0
2
               rc = myserver.setup_local_support(nspace:str, info:list)
                                                      Python
3
               IN
                    nspace
 4
                   Namespace whose setup information is being requested (str)
 5
               IN
                    info
 6
                   Python list of info containing the setup data (list)
 7
               Returns:
8
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
               See PMIx_server_setup_local_support for details.
    A.5.18
               Server.iof deliver
               Summary
11
               Function by which the host environment can pass forwarded IO to the PMIx server library for
12
13
               distribution to its clients.
               Format
14
                                                      Python
   PMIx v4.0
               rc = myserver.iof_deliver(source:dict, channel:integer,
15
                                                data:dict, directives:list)
16
                                                      Python
               IN
17
                    source
18
                   Python proc dictionary identifying the process who generated the data (dict)
               IN
                    channel
19
                   Python channel bitmask identifying IO channel of the provided data (integer)
20
               IN
21
22
                   Python byteobject containing the data (dict)
23
                    directives
                   Python list of info containing directives (list)
24
               Returns:
25
26
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27
               See PMIx_server_IOF_deliver for details.
    A.5.19
                Server.collect inventory
29
               Summary
30
               Collect inventory of resources on a node.
```

```
Format
1
                                                     Python
   PMIx v4.0
2
              rc,info = myserver.collect_inventory(directives:list)
                                                     Python
              IN
3
                    directives
                   Optional Python list of info containing directives (list)
              Returns:
              • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
              • info - Python list of info containing the returned data (list)
              See PMIx server collect inventory for details.
 8
    A.5.20
               Server.deliver inventory
              Summary
10
              Pass collected inventory to the PMIx server library for storage.
11
              Format
12
                                                     Python
   PMIx v4.0
13
              rc = myserver.deliver inventory(info:list, directives:list)
                                                     Pvthon
                   info
14
              IN
                   - Python list of info dictionaries containing the inventory data (list)
15
              IN
                   directives
16
                   Python list of info dictionaries containing directives (list)
17
18
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19
              See PMIx_server_deliver_inventory for details.
20
    A.5.21
               Server.define_process_set
22
              Summary
23
              Add members to a PMIx process set.
```

```
Format
1
                                                    Python
   PMIx v4.0
2
              rc = myserver.define_process_set(members:list, name:str)
                                                    Python
              IN
3
                   members
 4
                   - List of Python proc dictionaries identifying the processes to be added to the process set
 5
              IN
6
                   name
 7
                   - Name of the process set (str)
8
              Returns:
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9
10
              See PMIx server define process set for details.
    A.5.22
               Server.delete process set
              Summary
12
              Delete a PMIx process set.
13
              Format
14
                                                    Python
   PMIx v4.0
15
              rc = myserver.delete_process_set(name:str)
                                                     Python
              IN
                   name
16
17
                   - Name of the process set (str)
              Returns:
18
              • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
19
20
              See PMIx_server_delete_process_set for details.
               Server.register_resources
    A.5.23
              Summary
22
              Register non-namespace related information with the local PMIx server library.
23
```

```
Format
1
                                                      Python
   PMIx v4.0
2
               rc = myserver.register_resources(info:list)
                                                      Python
               IN
3
                    info
                    - List of Python info dictionaries list)
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
               See PMIx_server_register_resources for details.
    A.5.24
                Server.deregister resources
               Summary
9
               Deregister non-namespace related information with the local PMIx server library.
10
               Format
11
                                                      Python
   PMIx v4.0
12
               rc = myserver.deregister_resources(info:list)
                                                      Python
13
               IN
                    info
14
                    - List of Python info dictionaries list)
               Returns:
15
16
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
17
               See PMIx_server_deregister_resources for details.
    A.6
             PMIxTool
19
               The tool Python class inherits the Python "server" class as its parent. Thus, it includes all client and
               server functions in addition to the ones defined in this section.
20
              Tool.init
    A.6.1
               Summary
22
23
               Initialize the PMIx tool library after obtaining a new PMIxTool object.
```

```
Format
 1
                                                       Python
   PMIx v4.0
 2
               rc,proc = mytool.init(info:list)
                                                       Python
               IN
                    info
 3
                    List of Python info directives (list)
 4
               Returns:
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
 6
               • proc - a Python proc (dict)
 7
               See PMIx_tool_init for description of all relevant attributes and behaviors.
 8
              Tool.finalize
    A.6.2
10
               Summary
               Finalize the PMIx tool library, closing the connection to the server.
11
               Format
12
                                                       Python
   PMIx v4.0
13
               rc = mytool.finalize()
                                                       Python
               Returns:
14
               • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
15
               See PMIx_tool_finalize for description of all relevant attributes and behaviors.
16
    A.6.3
              Tool.disconnect
17
               Summary
18
               Disconnect the PMIx tool from the specified server connection while leaving the tool library
19
20
               initialized.
               Format
21
                                                       Python
   PMIx v4.0
22
               rc = mytool.disconnect(server:dict)
                                                       Python
               IN
23
                     server
                    Process identifier of server from which the tool is to be disconnected (proc)
24
25
               Returns:
26
               • rc - PMIX SUCCESS or a negative value corresponding to a PMIx error constant (integer)
27
               See PMIx tool disconnect for details.
```

A.6.4 Tool.attach to server Summary 2 3 Establish a connection to a PMIx server. **Format Python** PMIx v4.0 5 rc,proc,server = mytool.connect_to_server(info:list) **Python** 6 IN info 7 List of Python **info** dictionaries (list) Returns: 8 9 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) • proc - a Python proc containing the tool's identifier (dict) 10 • server - a Python proc containing the identifier of the server to which the tool attached (dict) 11 12 See PMIx tool attach to server for details. A.6.5 **Tool.get servers** 14 Summary Get a list containing the **proc** process identifiers of all servers to which the tool is currently 15 connected. 16 Format 17 **Python** PMIx v4.0 18 rc, servers = mytool.get_servers() **Python** 19 Returns: • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 20 21 • servers - a list of Python proc containing the identifiers of the servers to which the tool is currently attached (dict) 22 See PMIx_tool_get_servers for details. 23 A.6.6 Tool.set server 25 Summary 26 Designate a server as the tool's *primary* server.

1		Format
	<i>PMIx v4.0</i>	Python —
2		<pre>rc = mytool.set_server(proc:dict, info:list)</pre>
		Python —
3		IN proc
4		Python proc containing the identifier of the servers to which the tool is to attach (list)
5		IN info
6		List of Python info dictionaries (list)
7		Returns:
8		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
9		See PMIx_tool_set_server for details.
10	A.6.7	Tool.iof_pull
11		Summary
12		Register to receive output forwarded from a remote process.
13		Format
	<i>PMIx v4.0</i>	Python
14		<pre>rc,id = mytool.iof_pull(sources:list, channel:integer,</pre>
15		directives:list, cbfunc)
		Python —
16		IN sources
17		List of Python proc dictionaries of processes whose IO is being requested (list)
18		IN channel
19		Python channel bitmask identifying IO channels to be forwarded (integer)
20		IN directives List of Duthon in So distinguises describing request (list)
21 22		List of Python info dictionaries describing request (list) IN cbfunc
23		Python iofcbfunc to receive IO payloads (func)
24		Returns:
25		• rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer)
26		• <i>id</i> - PMIx reference identifier for request (integer)
27		See PMIx_IOF_pull for description of all relevant attributes and behaviors.

Summarv 2 3 Deregister from output forwarded from a remote process. **Format Python** PMIx v4.0 5 rc = mytool.iof_deregister(id:integer, directives:list) **Python** IN id 6 PMIx reference identifier returned by pull request (list) 7 8 IN directives 9 List of Python **info** dictionaries describing request (list) 10 Returns: 11 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 12 See **PMIx IOF deregister** for description of all relevant attributes and behaviors. Tool.iof push A.6.9 13 Summary 14 Push data collected locally (typically from stdin) to stdin of target recipients. 15 **Format** 16 Python PMIx v4.0 rc = mytool.iof_push(targets:list, data:dict, directives:list) 17 Python 18 IN sources List of Python **proc** of target processes (list) 19 IN 20 Python byteobject containing data to be delivered (dict) 21 directives 22 IN 23 Optional list of Python **info** describing request (list) Returns: 24 • rc - PMIX_SUCCESS or a negative value corresponding to a PMIx error constant (integer) 25 See **PMIx_IOF_push** for description of all relevant attributes and behaviors. 26 **Example Usage**

A.6.8

28

Tool.iof deregister

The following examples are provided to illustrate the use of the Python bindings.

1 A.7.1 Python Client

2

3

4

5

The following example contains a client program that illustrates a fairly common usage pattern. The program instantiates and initializes the PMIxClient class, posts some data that is to be shared across all processes in the job, executes a "fence" that circulates the data, and then retrieves a value posted by one of its peers. Note that the example has been formatted to fit the document layout.

Python

```
from pmix import *
6
7
8
            def main():
9
                # Instantiate a client object
                myclient = PMIxClient()
10
                print("Testing PMIx ", myclient.get version())
11
12
                # Initialize the PMIx client library, declaring the programming model
13
14
                # as "TEST" and the library name as "PMIX", just for the example
                info = ['key':PMIX_PROGRAMMING_MODEL,
15
16
                          'value': 'TEST', 'val type': PMIX STRING,
                         'key':PMIX_MODEL_LIBRARY_NAME,
17
18
                          'value':'PMIX', 'val_type':PMIX_STRING]
19
                rc, myname = myclient.init(info)
20
                if PMIX SUCCESS != rc:
21
                    print("FAILED TO INIT WITH ERROR", myclient.error_string(rc))
22
                    exit(1)
23
                # try posting a value
24
                rc = myclient.put(PMIX_GLOBAL, "mykey",
25
                                   'value':1, 'val_type':PMIX_INT32)
26
27
                if PMIX SUCCESS != rc:
28
                    print("PMIx Put FAILED WITH ERROR", myclient.error string(rc))
29
                    # cleanly finalize
                    myclient.finalize()
30
31
                    exit(1)
32
                # commit it
33
                rc = myclient.commit()
34
35
                if PMIX_SUCCESS != rc:
                    print("PMIx_Commit FAILED WITH ERROR",
36
37
                           myclient.error_string(rc))
38
                    # cleanly finalize
39
                    myclient.finalize()
40
                     exit(1)
```

```
1
                # execute fence across all processes in my job
2
                procs = []
                info = []
3
4
                rc = myclient.fence(procs, info)
5
                if PMIX SUCCESS != rc:
                    print("PMIx_Fence FAILED WITH ERROR", myclient.error_string(rc))
6
7
                    # cleanly finalize
8
                    myclient.finalize()
9
                    exit(1)
10
11
                # Get a value from a peer
                if 0 != myname['rank']:
12
13
                    info = []
14
                    rc, get_val = myclient.get('nspace':"testnspace", 'rank': 0,
15
                                                 "mykey", info)
                    if PMIX_SUCCESS != rc:
16
17
                        print ("PMIx_Commit FAILED WITH ERROR",
18
                               myclient.error_string(rc))
19
                        # cleanly finalize
20
                        myclient.finalize()
21
                        exit(1)
                    print("Get value returned: ", get val)
22
23
24
                # test a fence that should return not supported because
25
                # we pass a required attribute that the server is known
26
                # not to support
27
                procs = []
28
                info = ['key': 'ARBIT', 'flags': PMIX_INFO_REQD,
29
                          'value':10, 'val_type':PMIX_INT]
                rc = myclient.fence(procs, info)
30
                if PMIX_SUCCESS == rc:
31
32
                    print("PMIx_Fence SUCCEEDED BUT SHOULD HAVE FAILED")
33
                    # cleanly finalize
                    myclient.finalize()
34
35
                    exit(1)
36
                # Publish something
37
                info = ['key': 'ARBITRARY', 'value':10, 'val_type':PMIX_INT]
38
39
                rc = myclient.publish(info)
                if PMIX SUCCESS != rc:
40
41
                    print ("PMIx Publish FAILED WITH ERROR",
42
                          myclient.error string(rc))
43
                    # cleanly finalize
```

```
1
                     myclient.finalize()
2
                     exit(1)
3
4
                # finalize
5
                info = []
6
                myclient.finalize(info)
7
                print("Client finalize complete")
8
9
            # Python main program entry point
10
            if __name__ == '__main__':
11
                main()
                                             Python
```

12 A.7.2 Python Server

13

14

15

16 17 The following example contains a minimum-level server host program that instantiates and initializes the PMIxServer class. The program illustrates passing several server module functions to the bindings and includes code to setup and spawn a simple client application, waiting until the spawned client terminates before finalizing and exiting itself. Note that the example has been formatted to fit the document layout.

Python

```
18
            from pmix import *
19
            import signal, time
20
            import os
            import select
21
22
            import subprocess
23
24
            def clientconnected(proc:tuple is not None):
                print("CLIENT CONNECTED", proc)
25
                return PMIX_OPERATION_SUCCEEDED
26
27
28
            def clientfinalized(proc:tuple is not None):
29
                print("CLIENT FINALIZED", proc)
                return PMIX_OPERATION_SUCCEEDED
30
31
32
            def clientfence(procs:list, directives:list, data:bytearray):
33
                # check directives
34
                if directives is not None:
                    for d in directives:
35
36
                         # these are each an info dict
37
                         if "pmix" not in d['key']:
38
                             # we do not support such directives - see if
```

```
1
                             # it is required
2
                             try:
                                 if d['flags'] & PMIX INFO REQD:
3
4
                                     # return an error
5
                                     return PMIX ERR NOT SUPPORTED
6
                             except:
7
                                 #it can be ignored
8
                                 pass
9
                return PMIX OPERATION SUCCEEDED
10
11
            def main():
12
                try:
13
                    myserver = PMIxServer()
14
                except:
15
                    print("FAILED TO CREATE SERVER")
16
                    exit(1)
17
                print("Testing server version ", myserver.get_version())
18
19
                args = ['key':PMIX_SERVER_SCHEDULER,
20
                          'value':'T', 'val_type':PMIX_BOOL]
                map = 'clientconnected': clientconnected,
21
22
                        'clientfinalized': clientfinalized,
                        'fencenb': clientfence
23
24
                my result = myserver.init(args, map)
25
26
                # get our environment as a base
27
                env = os.environ.copy()
28
29
                # register an nspace for the client app
30
                (rc, regex) = myserver.generate_regex("test000,test001,test002")
                (rc, ppn) = myserver.generate_ppn("0")
31
                kvals = ['key':PMIX_NODE_MAP,
32
                           'value':regex, 'val_type':PMIX_STRING,
33
                          'key':PMIX_PROC_MAP,
34
35
                          'value':ppn, 'val_type':PMIX_STRING,
36
                          'key':PMIX_UNIV_SIZE,
37
                           'value':1, 'val type':PMIX UINT32,
38
                          'key':PMIX JOB SIZE,
39
                           'value':1, 'val type':PMIX UINT32]
40
                rc = foo.register_nspace("testnspace", 1, kvals)
41
                print("RegNspace ", rc)
42
43
                # register a client
```

```
1
                uid = os.getuid()
2
                gid = os.getgid()
3
                rc = myserver.register_client('nspace':"testnspace", 'rank':0,
4
                                                uid, gid)
5
                print("RegClient ", rc)
6
                # setup the fork
7
                rc = myserver.setup fork('nspace':"testnspace", 'rank':0, env)
8
                print("SetupFrk", rc)
9
10
                # setup the client argv
                args = ["./client.py"]
11
                # open a subprocess with stdout and stderr
12
13
                # as distinct pipes so we can capture their
14
                # output as the process runs
15
                p = subprocess.Popen(args, env=env,
16
                    stdout=subprocess.PIPE, stderr=subprocess.PIPE)
17
                # define storage to catch the output
18
                stdout = []
19
                stderr = []
20
                # loop until the pipes close
21
                while True:
22
                    reads = [p.stdout.fileno(), p.stderr.fileno()]
23
                    ret = select.select(reads, [], [])
24
25
                    stdout done = True
26
                    stderr_done = True
27
28
                    for fd in ret[0]:
29
                         # if the data
30
                        if fd == p.stdout.fileno():
31
                             read = p.stdout.readline()
32
                             if read:
33
                                 read = read.decode('utf-8').rstrip()
                                 print('stdout: ' + read)
34
35
                                 stdout done = False
                         elif fd == p.stderr.fileno():
36
37
                             read = p.stderr.readline()
38
                             if read:
39
                                 read = read.decode('utf-8').rstrip()
40
                                 print('stderr: ' + read)
41
                                 stderr done = False
42
43
                    if stdout done and stderr done:
```

```
1
                        break
               print("FINALIZING")
2
3
               myserver.finalize()
4
5
6
           if __name__ == '__main__':
7
               main()
                                           Python
```

APPENDIX B

Use-Cases

The PMIx standard provides many generic interfaces that can be composed into higher-level use cases in a variety of ways. While the specific interfaces and attributes are standardized, the use cases themselves are not (and should not) be standardized. Common use cases are included here as examples of how PMIx's generic interfaces might be composed together for a higher-level purpose. The use cases are intended for both PMIx interface users and library implementors. Wherby a better understanding of the general usage model within the community can help users picking up PMIx for the first and help implementors optimize their implementation for the common cases.

Each use case is structured to provide background information about the high-level use case as well as specific details about how the PMIx interfaces are used within the use case. Some use cases even provide code snippets. These code snippets are apart of larger code examples located within the standard's source code repository, and each complete code example is fully compilable and runnable. The related interfaces and attributes collected at the bottom of each use case are mainly for convenience and link to the full standardized definitions.

B.1 Business Card Exchange for Process-to Process Wire-up

17 B.1.1 Use Case Summary

Multi-process communication libraries, such as MPI, need to establish communication channels between a set of those processes. Each process needs to share connectivity information (a.k.a. Business Cards) with all other processes before communication channels can be established. This connectivity information may take the form of one or more unique strings that allow a different process to establish a communication channel with the originator. The runtime environment must provide a mechanism for the efficient exchange of this connectivity information. Additional information about the current state of the job (e.g., number of processes globally and locally) and of how the process was started (e.g., process binding) are also helpful. Use Case Details

Note: The Instant-On wire-up mechanism is a separate, related use case.

B.1.2 Use Case Details

Each process provides their business card to PMIx via one or more **PMIx_Put** operations to store the tuple of {**UID**, **key**, **value**}. The **UID** is the unique name for this process in the PMIx universe (i.e., **namespace** and **rank**). The **key** is a unique key that other processes can reference generically (note that since the **UID** is also associated with the **key** there is no need to make the **key** uniquely named per process). The **value** is the string representation of the connectivity information.

Some business card information is meant for remote processes (e.g., TCP or InfiniBand addresses) while others are meant only for local processes (e.g., shared memory information). As such a **scope** should be associated with the **PMIx_Put** operation to differentiate this intention.

The PMIx_Put operations may be cached local to the process. Once all PMIx_Put operations have been called each process should call PMIx_Commit to push those values to the local PMIx server. Note that in a multi-library configuration each library may PMIx_Put then PMIx_Commit values - so there may be multiple PMIx_Commit calls before a Business Card Exchange is activated.

After calling **PMIx_Commit** a process can activate the Business Card Exchange collective operation by calling **PMIx_Fence**. The **PMIx_Fence** operation is collective over the set of processes specified in the argument set. That allows for the collective to span a subset of a namespace or multiple namespaces. After the completion of the **PMIx_Fence** operation, the data **PMIx_Put** by other processes is available to the local process through a call to **PMIx_Get** which returns the key/value pairs necessary to establish the connection(s) with the other processes.

The **PMIx_Fence** operation must have a "Synchronize Only" mode that works as a barrier operation. This is helpful if the communication library requires a synchronization before leaving initialization or starting finalization, for example.

The PMIx_Fence operation should have a "Sparse" mode in addition to a "Full" mode for the data exchange. The "Full" mode will fully exchange all Business Card information to all other processes. This is helpful for tightly communicating applications. The "Sparse" mode will dynamically pull the connectivity information on-demand from inside of PMIx_Get (if it is not already available locally). This is helpful for sparsely communicating applications. Since which mode is best for an application cannot be inferred by the PMIx library the caller must specify which mode works best for their application.

The **PMIx_Fence** operation should have an option for the end user to specify which mode they desire for this operation.

Additional information about the current state of the job (e.g., number of processes globally and locally) and of how the process was started (e.g., process binding) are also helpful. This "job level" information must be available immediately after PMIx_Init without the need for any explicit synchronization.

The number of processes globally in the namespace and this process's rank within that namespace is important to know before establishing the Business Card information to best allocate resources.

```
The number of processes local to the node and this process's local rank is important to know before
 1
 2
               establishing the Business Card information to help the caller determine the scope of the put
 3
               operation. For example, to designate a leader to set up a shared memory segment of the proper size
 4
               before putting that information into the locally scoped Business Card information.
 5
               The number of processes local to a remote node is also helpful to know before establishing the
 6
               Business Card information. This information is useful to pre-establish local resources before that
 7
               remote node starts to initiate a connection or to determine the number of connections that need to
8
               be advertised in the Business Card when it is sent out.
9
               Note that some of the job level information may change over the course of the job in a dynamic
10
               application.
               Related Interfaces
11
               PMIx Put
12
   PMIx v1.0
13
               pmix status t
               PMIx_Put(pmix_scope_t scope,
14
                          const pmix_key_t key,
15
16
                          pmix value t *val);
               PMIx Get
17
   PMIx v1.0
18
               pmix_status_t
19
               PMIx Get (const pmix proc t *proc, const pmix key t key,
20
                           const pmix_info_t info[], size_t ninfo,
21
                          pmix_value_t **val);
               PMIx_Commit
22
   PMIx v1.0
23
               pmix status t PMIx Commit(void);
               PMIx Fence
24
   PMIx v1.0
25
               pmix_status_t
26
               PMIx_Fence(const pmix_proc_t procs[], size_t nprocs,
27
                             const pmix_info_t info[], size_t ninfo);
               PMIx Init
28
   PMIx v1.2
```

C

Related Keys

 The following job level information is useful to have before establishing Business Card information:

```
PMIX_NODE_LIST "pmix.nlist" (char*)
```

Comma-delimited list of nodes currently hosting processes in the specified realm. Defaults to the *job* realm.

```
PMIX NUM NODES "pmix.num.nodes" (uint32 t)
```

Number of nodes currently hosting processes in the specified realm. Defaults to the *job* realm.

```
PMIX NODEID "pmix.nodeid" (uint32 t)
```

Node identifier expressed as the node's index (beginning at zero) in an array of nodes within the active session. The value must be unique and directly correlate to the **PMIX_HOSTNAME** of the node - i.e., users can interchangeably reference the same location using either the **PMIX_HOSTNAME** or corresponding **PMIX_NODEID**.

```
PMIX_JOB_SIZE "pmix.job.size" (uint32_t)
```

Total number of processes in the specified job across all contained applications. Note that this value can be different from **PMIX_MAX_PROCS**. For example, users may choose to subdivide an allocation (running several jobs in parallel within it), and dynamic programming models may support adding and removing processes from a running *job* on-the-fly. In the latter case, PMIx events may be used to notify processes within the job that the job size has changed.

```
PMIX PROC MAP "pmix.pmap" (char*)
```

Regular expression describing processes on each node in the specified realm - see 16.2.3.2 for an explanation of its generation. Defaults to the *job* realm.

```
PMIX_LOCAL_PEERS "pmix.lpeers" (char*)
```

Comma-delimited list of ranks that are executing on the local node within the specified namespace – shortcut for **PMIx_Resolve_peers** for the local node.

```
PMIX_LOCAL_SIZE "pmix.local.size" (uint32_t)
```

Number of processes in the specified job or application realm on the caller's node. Defaults to job realm unless the **PMIX_APP_INFO** and the **PMIX_APPNUM** qualifiers are given.

For each process this information is also useful (note that any one process may want to access this list of information about any other process in the system):

```
PMIX_RANK "pmix.rank" (pmix_rank_t)
```

Process rank within the job, starting from zero.

PMIX_LOCAL_RANK "pmix.lrank" (uint16_t)

Rank of the specified process on its node - refers to the numerical location (starting from zero) of the process on its node when counting only those processes from the same job that share the node, ordered by their overall rank within that job.

PMIX GLOBAL RANK "pmix.grank" (pmix rank t)

Rank of the specified process spanning across all jobs in this session, starting with zero. Note that no ordering of the jobs is implied when computing this value. As jobs can start and end at random times, this is defined as a continually growing number - i.e., it is not dynamically adjusted as individual jobs and processes are started or terminated.

PMIX_LOCALITY_STRING "pmix.locstr" (char*)

String describing a process's bound location - referenced using the process's rank. The string is prefixed by the implementation that created it (e.g., "hwloc") followed by a colon. The remainder of the string represents the corresponding locality as expressed by the underlying implementation. The entire string must be passed to <code>PMIx_Get_relative_locality</code> for processing. Note that hosts are only required to provide locality strings for local client processes - thus, a call to <code>PMIx_Get</code> for the locality string of a process that returns <code>PMIX_ERR_NOT_FOUND</code> indicates that the process is not executing on the same node.

PMIX_HOSTNAME "pmix.hname" (char*)

Name of the host, as returned by the **gethostname** utility or its equivalent.

There are other keys that are helpful to have before a synchronization point. This is not meant to be a comprehensive list.

B.2 Debugging

 This use case distills out the features/extensions requested in the RFCs that are related to debugging. We have identified parts of PR23 (Co-located process launch for debuggers), RFC0010 (MPIR-like query), RFC0002 (event pub/sub), and RFC0022 (Environmental Parameter Directives for Applications and Launchers) under this category.

8 B.2.1 Terminology

B.2.1.1 Tools vs Debuggers

A tool is a process designed to monitor, record, analyze, or control the execution of another process. Typically used for the purposes of profiling and debugging. A first-party tool runs within the address space of the application process while a third-party tool run within its own process. A debugger is a third-party tool that inspects and controls an application process's execution using system-level debug APIs (e.g., ptrace).

B.2.1.2 Parallel Launching Methods

A starter program is a program responsible for launching a parallel runtime, such as MPI. PMIx supports two primary methods for launching parallel applications under tools and debuggers: indirect and direct. In the indirect launching method, the tool is attached to the starter. In the direct launching method, the tool takes the place of the starter. PMIx also supports attaching to already running programs via the Process Acquisition interfaces.

B.2.1.3 Process Synchronization

Process Synchronization is the technique tools use to start the processes of a parallel application such that the tools can still attach to the process early in it's lifetime. Said another away, the tool must be able to start the application processes without them "running away" from the tool. In the case of MPI, this means stopping the applications processes before they return from MPI Init.

B.2.1.4 Process Acquisition

Process Acquisition is technique tools use to locate all of the processes, local and remote, of a given parallel application. This typically boils down to collecting for every process in the parallel application: the hostname or IP of the machine running the process, the executable name, and the process ID.

B.2.2 Use Case Details

8 B.2.2.1 Direct-Launch Debugger Tool

PMIx can support the tool itself using the PMIx spawn options to control the app's startup, including directing the RM/application as to when to block and wait for tool attachment, or stipulating that an interceptor library be preloaded. However, this means that the user is restricted to whatever command line options the tool vendor has provided for operations such as process placement and binding, which places a significant burden on the tool vendor. An example might look like the following: dbgr -n 3 ./myapp.

Assuming it is supported, co-launch of debugger daemons in this use-case is supported by adding a **pmix_app_t** to the **PMIx_Spawn** command, indicating that the resulting processes are debugger daemons by setting the **PMIX_DEBUGGER_DAEMONS** attribute.

```
Related Interfaces
```

```
PMIx_tool_init

PMIx v2.0

pmix_status_t

PMIx_tool_init(pmix_proc_t *proc,

pmix_info_t info[], size_t ninfo);

PMIx_Register_event_handler
```

PMIX_RegIster_event_nandie




Figure B.1.: Direct Launch

```
1
            pmix status t
 2
            PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
 3
                                         pmix_info_t info[], size_t ninfo,
4
                                         pmix_notification_fn_t evhdlr,
5
                                         pmix_hdlr_reg_cbfunc_t cbfunc,
6
                                         void *cbdata);
            PMIx Query info
7
  PMIx v4.0
8
            pmix_status_t
9
            PMIx_Query_info(pmix_query_t queries[], size_t nqueries,
10
                             pmix_info_t *info[], size_t *ninfo);
            PMIx_Spawn
11
  PMIx v1.0
12
            pmix_status_t
            PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo,
13
14
                       const pmix_app_t apps[], size_t napps,
15
                        char nspace[])
            PMIx_Get
16
  PMIx v1.0
17
            pmix status t
18
            PMIx_Get(const pmix_proc_t *proc, const pmix_key_t key,
19
                     const pmix_info_t info[], size_t ninfo,
20
                     pmix_value_t **val);
            PMIx_Notify_event
21
  PMIx v2.0
22
            pmix status t
23
            PMIx_Notify_event(pmix_status_t status,
24
                               const pmix_proc_t *source,
25
                               pmix data range t range,
26
                               pmix_info_t info[], size_t ninfo,
27
                               pmix_op_cbfunc_t cbfunc, void *cbdata);
```

1 Related Attributes

 PMIX_QUERY_SPAWN_SUPPORT "pmix.qry.spawn" (bool)

Return a comma-delimited list of supported spawn attributes. NO QUALIFIERS.

PMIX_QUERY_DEBUG_SUPPORT "pmix.qry.debug" (bool)

Return a comma-delimited list of supported debug attributes. NO QUALIFIERS.

PMIX_DEBUG_STOP_IN_INIT "pmix.dbg.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have reached the pause point.

PMIX DEBUG STOP ON EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point.

PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)

Requests that the ability to forward the **stdout** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained. The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_NOTIFY_COMPLETION "pmix.notecomp" (bool)

Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred. Note that the requester must register for the event or capture and process it within a default event handler.

PMIX_SETUP_APP_ENVARS "pmix.setup.env" (bool)

Harvest and include relevant environmental variables.

PMIX_EVENT_AFFECTED_PROC "pmix.evproc" (pmix_proc_t) The single process that was affected.

PMIX_DEBUGGER_DAEMONS "pmix.debugger" (bool)

Included in the <code>pmix_info_t</code> array of a <code>pmix_app_t</code>, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole <code>pmix_app_t</code> in a <code>PMIx_Spawn</code> request, then the <code>PMIX_DEBUG_TARGET</code> attribute must also be provided (in either the <code>job_info</code> or in the <code>info</code> array of the <code>pmix_app_t</code>) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> nor <code>PMIX_DEBUG_DAEMONS_PER_NODE</code> is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

PMIX_DEBUG_TARGET "pmix.dbg.tgt" (pmix_proc_t*)

Identifier of process(es) to be debugged - a rank of **PMIX_RANK_WILDCARD** indicates that all processes in the specified namespace are to be included.

PMIX_DEBUG_WAIT_FOR_NOTIFY "pmix.dbg.notify" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The resulting application processes are to notify their server (by generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event) when they reach some application-determined location and pause at that point until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have indicated they are at the pause point.

PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

Related Constants

PMIX_DEBUG_WAITING_FOR_NOTIFY
PMIX DEBUGGER RELEASE

B.2.2.2 Indirect-Launch Debugger Tool

Executing a program under a tool using an intermediate launcher such as mpiexec can also be made possible. This requires some degree of coordination between the tool and the launcher. Ultimately, it is the launcher that is going to launch the application, and the tool must somehow inform it (and

```
the application) that this is being done in a debug session so that the application knows to "block"
 1
 2
             until the tool attaches to it.
 3
             In this operational mode, the user invokes a tool (typically on a non-compute, or "head", node) that
             in turn uses mpiexec to launch their application – a typical command line might look like the
 4
             following: dbgr -dbgoption mpiexec -n 32 ./myapp.
 5
             Related Interfaces
6
             PMIx tool init
 7
   PMIx v2.0
8
             pmix_status_t
9
             PMIx_tool_init(pmix_proc_t *proc,
10
                               pmix info t info[], size t ninfo);
             PMIx_Register_event_handler
11
   PMIx v2.0
12
             pmix status t
13
             PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
                                              pmix_info_t info[], size_t ninfo,
14
15
                                              pmix_notification_fn_t evhdlr,
16
                                              pmix_hdlr_reg_cbfunc_t cbfunc,
17
                                              void *cbdata);
             PMIx_Spawn
18
   PMIx v1.0
19
             pmix status t
20
             PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo,
21
                          const pmix_app_t apps[], size_t napps,
22
                          char nspace[])
             PMIx Notify event
23
   PMIx v2.0
24
             pmix_status_t
25
             PMIx_Notify_event(pmix_status_t status,
26
                                  const pmix_proc_t *source,
27
                                  pmix_data_range_t range,
                                  pmix_info_t info[], size_t ninfo,
28
                                  pmix_op_cbfunc_t cbfunc, void *cbdata);
29
```




Figure B.2.: Indirect Launch

```
PMIx_tool_attach_to_server
 1
   PMIx v4.0
2
             pmix status t
 3
              PMIx_tool_attach_to_server(pmix_proc_t *proc,
 4
                                              pmix_proc_t *server,
5
                                              pmix_info_t info[],
6
                                              size_t ninfo);
              PMIx Query info
7
   PMIx v4.0
8
              pmix_status_t
9
              PMIx_Query_info(pmix_query_t queries[], size_t nqueries,
10
                                 pmix_info_t *info[], size_t *ninfo);
              PMIx Get
11
   PMIx v1.0
12
             pmix status t
13
              PMIx Get(const pmix proc t *proc, const pmix key t key,
                        const pmix_info_t info[], size_t ninfo,
14
15
                        pmix value t **val);
16
              Related Attributes
              PMIX LAUNCH DIRECTIVES ??unknown?? (??unknown??)
17
                   ??unknown??
18
              PMIX_SPAWN_TOOL "pmix.spwn.tool" (bool)
19
                   Indicate that the job being spawned is a tool.
20
              PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)
21
22
                   Requests that the ability to forward the stdout of the spawned processes be maintained.
                   The requester will issue a call to PMIx_IOF_pull to specify the callback function and
23
                   other options for delivery of the forwarded output.
24
              PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)
25
26
                   Requests that the ability to forward the stderr of the spawned processes be maintained.
                   The requester will issue a call to PMIx_IOF_pull to specify the callback function and
27
28
                   other options for delivery of the forwarded output.
29
              PMIX SETUP APP_ENVARS "pmix.setup.env" (bool)
```

Harvest and include relevant environmental variables.

PMIX DEBUG STOP IN INIT "pmix.dbq.init" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the specified application is being spawned under a debugger. The PMIx client library in each resulting application process shall notify its PMIx server that it is pausing and then pause during <code>PMIx_Init</code> of the spawned processes until either released by debugger modification of an appropriate variable or receipt of the <code>PMIX_DEBUGGER_RELEASE</code> event. The launcher (RM or IL) is responsible for generating the <code>PMIX_DEBUG_WAITING_FOR_NOTIFY</code> event when all processes have reached the pause point.

PMIX_DEBUG_STOP_ON_EXEC "pmix.dbg.exec" (bool)

Included in either the <code>pmix_info_t</code> array in a <code>pmix_app_t</code> description (if the directive applies only to that application) or in the <code>job_info</code> array if it applies to all applications in the given spawn request. Indicates that the application is being spawned under a debugger, and that the local launch agent is to pause the resulting application processes on first instruction for debugger attach. The launcher (RM or IL) is to generate the <code>PMIX_LAUNCH_COMPLETE</code> event when all processes are stopped at the exec point.

PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose process table is being queried.

PMIX_QUERY_LOCAL_PROC_TABLE "pmix.qry.lptable" (char*)

Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each process in the specified namespace executing on the same node as the requester, ordered by process job rank. REQUIRED QUALIFIER: PMIX_NSPACE indicating the namespace whose local process table is being queried. OPTIONAL QUALIFIER: PMIX_HOSTNAME indicating the host whose local process table is being queried. By default, the query assumes that the host upon which the request was made is to be used.

PMIX DEBUGGER DAEMONS "pmix.debugger" (bool)

Included in the <code>pmix_info_t</code> array of a <code>pmix_app_t</code>, this attribute declares that the application consists of debugger daemons and shall be governed accordingly. If used as the sole <code>pmix_app_t</code> in a <code>PMIx_Spawn</code> request, then the <code>PMIX_DEBUG_TARGET</code> attribute must also be provided (in either the <code>job_info</code> or in the <code>info</code> array of the <code>pmix_app_t</code>) to identify the namespace to be debugged so that the launcher can determine where to place the spawned daemons. If neither <code>PMIX_DEBUG_DAEMONS_PER_PROC</code> nor <code>PMIX_DEBUG_DAEMONS_PER_NODE</code> is specified, then the launcher shall default to a placement policy of one daemon per process in the target job.

PMIX NOTIFY COMPLETION "pmix.notecomp" (bool)

```
1
                     Requests that the launcher generate the PMIX EVENT JOB END event for normal or
                     abnormal termination of the spawned job. The event shall include the returned status code
 2
 3
                     (PMIX JOB TERM STATUS) for the corresponding job; the identity (PMIX PROCID)
 4
                     and exit status (PMIX EXIT CODE) of the first failed process, if applicable; and a
 5
                     PMIX EVENT TIMESTAMP indicating the time the termination occurred. Note that the
                     requester must register for the event or capture and process it within a default event handler.
6
 7
               PMIX DEBUG TARGET "pmix.dbg.tgt" (pmix proc t*)
                     Identifier of process(es) to be debugged - a rank of PMIX RANK WILDCARD indicates that
8
9
                     all processes in the specified namespace are to be included.
10
               PMIX WAIT FOR CONNECTION "pmix.wait.conn" (bool)
11
                     Wait until the specified process has connected to the requesting tool or server, or the
                     operation times out (if the PMIX TIMEOUT directive is included in the request).
12
13
               Related Constants
               PMIX LAUNCHER READY
14
               PMIX LAUNCH_COMPLETE
15
16
               PMIX_DEBUG_WAITING_FOR_NOTIFY
17
               PMIX DEBUGGER RELEASE
18
               PMIX_LAUNCHER_RNDZ_URI
               Attaching to a Running Job
    B.2.2.3
19
               PMIx supports attaching to an already running parallel job in two ways. In the first way, the main
20
               process of a tool calls PMIx_Query_info with the PMIX_QUERY_PROC_TABLE attribute.
21
               This returns an array of structs containing the information required for process acquisition. This
22
23
               includes remote hostnames, executable names, and process IDs. In the second way, every tool
24
               daemon calls PMIx Query info with the PMIX QUERY LOCAL PROC TABLE attribute.
               This returns a similar array of structs but only for processes on the same node.
25
               An example of this use-case may look like the following: mpiexec -n32 ./myApp && dbgr
26
27
               attach $!.
               PMIx_tool_init
28
   PMIx v2.0
29
               pmix status t
30
               PMIx tool init(pmix proc t *proc,
31
                                  pmix_info_t info[], size_t ninfo);
               PMIx_Register_event_handler
32
   PMIx v2.0
```




Figure B.3.: Attaching to a Running Job

```
1
              pmix status t
 2
              PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
 3
                                                pmix_info_t info[], size_t ninfo,
                                                pmix_notification_fn_t evhdlr,
 4
 5
                                                pmix_hdlr_reg_cbfunc_t cbfunc,
 6
                                                void *cbdata);
              PMIx_Query_info
7
   PMIx v4.0
8
              pmix status t
9
              PMIx_Query_info(pmix_query_t queries[], size_t nqueries,
10
                                 pmix_info_t *info[], size_t *ninfo);
              PMIx_Spawn
11
   PMIx v1.0
12
              pmix_status_t
              PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo,
13
                           const pmix_app_t apps[], size_t napps,
14
15
                           char nspace[])
              PMIX_QUERY_PROC_TABLE "pmix.qry.ptable" (char*)
16
17
                   Returns a (pmix_data_array_t) array of pmix_proc_info_t, one entry for each
18
                   process in the specified namespace, ordered by process job rank. REQUIRED QUALIFIER:
19
                   PMIX NSPACE indicating the namespace whose process table is being queried.
20
              PMIX_DEBUGGER_DAEMONS "pmix.debugger" (bool)
21
                   Included in the pmix_info_t array of a pmix_app_t, this attribute declares that the
                   application consists of debugger daemons and shall be governed accordingly. If used as the
22
23
                   sole pmix app t in a PMIx Spawn request, then the PMIX DEBUG TARGET attribute
                   must also be provided (in either the job info or in the info array of the pmix app t) to
24
25
                   identify the namespace to be debugged so that the launcher can determine where to place the
                   spawned daemons. If neither PMIX_DEBUG_DAEMONS_PER_PROC nor
26
                   PMIX_DEBUG_DAEMONS_PER_NODE is specified, then the launcher shall default to a
27
28
                   placement policy of one daemon per process in the target job.
              PMIX_DEBUG_TARGET "pmix.dbg.tgt" (pmix_proc_t*)
29
                   Identifier of process(es) to be debugged - a rank of PMIX_RANK_WILDCARD indicates that
30
                   all processes in the specified namespace are to be included.
31
32
              PMIX_FWD_STDOUT "pmix.fwd.stdout" (bool)
```

Requests that the ability to forward the **stdout** of the spawned processes be maintained.

The requester will issue a call to **PMIx_IOF_pull** to specify the callback function and other options for delivery of the forwarded output.

PMIX_FWD_STDERR "pmix.fwd.stderr" (bool)

Requests that the ability to forward the **stderr** of the spawned processes be maintained.

The requester will issue a call to **PMIx IOF pull** to specify the callback function and

other options for delivery of the forwarded output. PMIX NOTIFY COMPLETION "pmix.notecomp" (bool)

Requests that the launcher generate the PMIX_EVENT_JOB_END event for normal or abnormal termination of the spawned job. The event shall include the returned status code (PMIX_JOB_TERM_STATUS) for the corresponding job; the identity (PMIX_PROCID) and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a PMIX_EVENT_TIMESTAMP indicating the time the termination occurred. Note that the requester must register for the event or capture and process it within a default event handler.

PMIX_REQUESTOR_IS_TOOL "pmix.req.tool" (bool)
The requesting process is a PMIx tool.

PMIX_QUERY_NAMESPACES "pmix.qry.ns" (char*)

Request a comma-delimited list of active namespaces. NO QUALIFIERS.

B.2.2.4 Tool Interaction with RM

Tools can benefit from a mechanism by which they may interact with a local PMIx server that has opted to accept such connections along with support for tool connections to system-level PMIx servers, and a logging feature. To add support for tool connections to a specified system-level, PMIx server environments could choose to launch a set of PMIx servers to support a given allocation - these servers will (if so instructed) provide a tool rendezvous point that is tagged with their pid and typically placed in an allocation-specific temporary directory to allow for possible multi-tenancy scenarios. Supporting such operations requires that a system-level PMIx connection be provided which is not associated with a specific user or allocation. A new key has been added to direct the PMIx server to expose a rendezvous point specifically for this purpose.

```
PMIx_Query_info_nb
```

```
PMIx v2.0

pmix_status_t

PMIx_Query_info_nb(pmix_query_t queries[], size_t nqueries,

pmix_info_cbfunc_t cbfunc, void *cbdata);

C

PMIx_Register_event_handler
```

PMIx v2.0

```
1
            pmix status t
2
            PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
3
                                         pmix_info_t info[], size_t ninfo,
4
                                         pmix_notification_fn_t evhdlr,
5
                                         pmix_hdlr_reg_cbfunc_t cbfunc,
6
                                         void *cbdata);
            PMIx_Deregister_event_handler
7
  PMIx v2.0
8
            pmix status t
9
            PMIx_Deregister_event_handler(size_t evhdlr_ref,
10
                                           pmix_op_cbfunc_t cbfunc,
11
                                           void *cbdata);
            PMIx Notify event
12
  PMIx v2.0
13
            pmix status t
14
            PMIx Notify event (pmix status t status,
15
                               const pmix proc t *source,
                               pmix_data_range_t range,
16
17
                              pmix_info_t info[], size_t ninfo,
18
                               pmix_op_cbfunc_t cbfunc, void *cbdata);
            PMIx server init
19
  PMIx v1.0
20
            pmix_status_t
21
            PMIx_server_init(pmix_server_module_t *module,
22
                             pmix_info_t info[], size_t ninfo);
            Job-specific events
23
24
            PMIX_EVENT_JOB_LEVEL /* debugger attached, process failure */
            Environment events
25
            PMIX_EVENT_ENVIRO_LEVEL /*ECC errors, temperature excursions */
26
            Errors detected by clients/peers
27
28
            Network fabric manager detects data corruption
```

B.2.2.5 Environmental Parameter Directives for Applications and Launchers 2 It is sometimes desirable or required that standard environmental variables (e.g., PATH, 3 4 LD LIBRARY PATH, LD PRELOAD) be modified prior to executing an application binary or a 5 starter such as mpiexec - this is particularly true when tools/debuggers are used to start the 6 application. This RFC proposes the definition of a new PMIx structure (pmix envar t) and 7 associated attributes for specifying such operations. **Related Interfaces** 8 PMIx Spawn 9 PMIx v1.010 pmix status t 11 PMIx_Spawn(const pmix_info_t job_info[], size_t ninfo, 12 const pmix_app_t apps[], size_t napps, char nspace[]) 13 Related Structs 14 15 pmix_envar_t Related Attributes 16 PMIX_SET_ENVAR "pmix.envar.set" (pmix_envar_t*) 17 18 Set the envar to the given value, overwriting any pre-existing one PMIX ADD ENVAR "pmix.envar.add" (pmix envar t*) 19 20 Add the environment variable, but do not overwrite any pre-existing one PMIX_UNSET_ENVAR "pmix.envar.unset" (char*) 21 22 Unset the environment variable specified in the string. PMIX_PREPEND_ENVAR "pmix.envar.prepnd" (pmix_envar_t*) 23 Prepend the given value to the specified environmental value using the given separator 24 character, creating the variable if it doesn't already exist 25 26 PMIX_APPEND_ENVAR "pmix.envar.appnd" (pmix_envar_t*) Append the given value to the specified environmental value using the given separator 27 character, creating the variable if it doesn't already exist 28 29 Resource managers and launchers must scan for relevant directives, modifying environmental 30 parameters as directed. Directives are to be processed in the order in which they were given, starting with job-level directives (applied to each app) followed by app-level directives. 31

B.3 Hybrid Programming Models

2 B.3.1 Use Case Summary

Hybrid applications (i.e., applications that utilize more than one lprogramming model, such as an MPI application that also uses OpenMP or PGAS) are growing in popularity, especially as chips with increasingly large numbers of cores and processors proliferate. Unfortunately, the various models currently operate under the assumption that they alone control execution. This leads to conflicts in hybrid applications. Deadlock of parallel applications can occur when one model prevents the other from making progress due to lack of coordination between the multiple programming models [3]. Sub-optimal performance can also occur due to uncoordinated division of hardware resources between the programming models [5, 4]. This use-case offers potential solutions to the problem by providing a pathway for programming models to coordinate their actions.

B.3.2 Use Case Details

B.3.2.1 Identifying Active Programming Models

The current state-of-the-practice for programming models to detect one another is via set environment variables. For example, OpenMP looks for environment variables to indicate that MPI is active. Unfortunately, this technique is not completely reliable as environment variables change over time and with new software versions. Also, the fact that an environment variable is present doesn't guarantee that a particular programming is in active use since Resource Managers routinely set environment variables "just in case" the application needs them. PMIx provides a reliable mechanism by which each library can determine that another library is in operation.

When initializing PMIx, programming models can register themselves, including their name, version, and threading model. This information is then cached locally and can then be read asynchronously by other programming models using PMIx's Event Notification system (see next section for more details).

This initialization mechanism also allows libraries to share knowledge of each other's resources and intended resource utilization. For example, if OpenMP knows which hardware threads that MPI is using it could potentially avoid processor and cache contention.

Code Example

```
pmix_proc_t myproc;
pmix_info_t *info;
volatile bool wearedone = false;

PMIX_INFO_CREATE(info, 4);
PMIX_INFO_LOAD(&info[0], PMIX_PROGRAMMING_MODEL, "MPI", PMIX_STRING);
PMIX_INFO_LOAD(&info[1], PMIX_MODEL_LIBRARY_NAME, "FOOMPI",

PMIX_STRING);
```

```
→ PMIX_STRING);
             9 PMIX_INFO_LOAD(&info[3], PMIX_THREADING_MODEL, "pthread", PMIX_STRING);
            pmix status t rc = PMIx Init(&myproc, info, 4);
            PMIX_INFO_FREE(info, 4);
 1
              Related Interfaces
2
              PMIx Init
 3
   PMIx v1.2
4
              pmix status t
5
              PMIx_Init(pmix_proc_t *proc,
                          pmix info t info[], size t ninfo)
6
              Related Attributes
7
8
              PMIX PROGRAMMING MODEL "pmix.pgm.model" (char*)
                   Programming model being initialized (e.g., "MPI" or "OpenMP").
9
              PMIX_MODEL_LIBRARY_NAME "pmix.mdl.name" (char*)
10
11
                   Programming model implementation ID (e.g., "OpenMPI" or "MPICH").
              PMIX MODEL LIBRARY VERSION "pmix.mld.vrs" (char*)
12
13
                   Programming model version string (e.g., "2.1.1").
              PMIX THREADING MODEL "pmix.threads" (char*)
14
15
                   Threading model used (e.g., "pthreads").
              PMIX_MODEL_NUM_THREADS "pmix.mdl.nthrds" (uint64_t)
16
17
                   Number of active threads being used by the model.
18
              PMIX MODEL NUM CPUS "pmix.mdl.ncpu" (uint64 t)
19
                   Number of cpus being used by the model.
              PMIX MODEL CPU TYPE "pmix.mdl.cputype" (char*)
20
21
                   Granularity - "hwthread", "core", etc.
22
              PMIX MODEL PHASE NAME "pmix.mdl.phase" (char*)
                   User-assigned name for a phase in the application execution (e.g., "cfd reduction").
23
24
              PMIX MODEL PHASE TYPE "pmix.mdl.ptype" (char*)
25
                   Type of phase being executed (e.g., "matrix multiply").
26
              PMIX MODEL AFFINITY POLICY "pmix.mdl.tap" (char*)
27
                   Thread affinity policy - e.g.: "master" (thread co-located with master thread), "close" (thread
                   located on cpu close to master thread), "spread" (threads load-balanced across available
28
29
                   cpus).
```

8 PMIX INFO LOAD(&info[2], PMIX MODEL LIBRARY VERSION, "1.0.0",

B.3.2.2 Coordinating at Runtime

2

3

4 5

6 7

8 9

10 11

12 13

14

15

16

17 18 The PMIx Event Notification system provides a mechanism by which the resource manager can communicate system events to applications, thus providing applications with an opportunity to generate an appropriate response. Hybrid applications can leverage these events for cross-library coordination.

Programming models can access the information provided by other programming models during their initialization using the event notification system. In this case, programming models should register a callback for the **PMIX_MODEL_DECLARED** event.

Programming models can also use the PMIx event notification system to communicate dynamic information, such as entering a new application phase (PMIX_MODEL_PHASE_NAME "pmix.mdl.phase" (char*)

User-assigned name for a phase in the application execution (e.g., "cfd reduction").

) or a change in resources used (PMIX_MODEL_RESOURCES). This dynamic information can be broadcast to other programming models using the PMIx_Notify_event function. Other programming models can register callback functions to run when these events occur (i.e., callback functions) using PMIx_Register_event_handler.

Code Example

Registering a callback to run when another programming model initializes:

```
static void model_declared_cb(size_t evhdlr_registration_id,
                                pmix_status_t status, const pmix_proc_t
2

→ *source,

                                pmix_info_t info[], size_t ninfo,
3
                                 pmix_info_t results[], size_t nresults,
                                pmix_event_notification_cbfunc_fn_t
5

    ⇔ cbfunc,

                                 void *cbdata) {
    printf("Entered %s\n", __FUNCTION__);
7
    int n;
    for (n = 0; n < ninfo; n++) {
9
      if (PMIX_CHECK_KEY(&info[n], PMIX_PROGRAMMING_MODEL) &&
10
          strcmp(info[n].value.data.string, "MPI") == 0) {
        /* ignore our own declaration */
12
       break;
13
      } else {
14
        /* actions to perform when another model registers */
15
17
    if (NULL != cbfunc) {
      /* tell the event handler that we are only a partial step */
      cbfunc(PMIX_EVENT_PARTIAL_ACTION_TAKEN, NULL, 0, NULL, NULL,
```

```
22 }
           23
           24
               pmix_status_t code = PMIX_MODEL_DECLARED;
               rc = PMIx_Register_event_handler(&code, 1, NULL, 0, model_declared_cb,
               1
2
            Notifying an event:
           PMIX_INFO_CREATE(info, 1);
           2 PMIX_INFO_LOAD(&info[0], PMIX_EVENT_NON_DEFAULT, NULL, PMIX_BOOL);
           3 rc = PMIx_Notify_event(PMIX_OPENMP_PARALLEL_ENTERED, &myproc,
               PMIX_RANGE_PROC_LOCAL, info, 1, notify_complete, (void*) & wearedone);
3
            Related Interfaces and Constants
4
            PMIx_Notify_event
5
  PMIx v2.0
6
            pmix_status_t
7
            PMIx_Notify_event(pmix_status_t status,
8
                                const pmix_proc_t *source,
9
                                pmix_data_range_t range,
10
                               pmix_info_t info[], size_t ninfo,
11
                               pmix op cbfunc t cbfunc, void *cbdata);
12
            PMIX MODEL DECLARED
13
            PMIX_MODEL_RESOURCES
14
            PMIX_OPENMP_PARALLEL_ENTERED
15
            PMIX OPENMP PARALLEL EXITED
16
            PMIx Register_event_handler
17
  PMIx v2.0
18
            pmix_status_t
19
            PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
20
                                          pmix_info_t info[], size_t ninfo,
21
                                          pmix_notification_fn_t evhdlr,
22
                                          pmix_hdlr_reg_cbfunc_t cbfunc,
23
                                          void *cbdata);
```

```
pmix event notification cbfunc fn t
1
 PMIx v2.0
2
           typedef void (*pmix event notification cbfunc fn t)
3
               (pmix_status_t status,
                pmix_info_t *results, size_t nresults,
4
5
                pmix op cbfunc t cbfunc, void *thiscbdata,
6
                void *notification cbdata);
7
```

PMIX EVENT ACTION COMPLETE

8

9

10 11

12

13

14

15

16 17

18 19

20 21

22

23

24 25

26

27 28

29

30

B.3.2.3 Coordinating at Runtime with Multiple Event Handlers

Coordinating with a threading library such as OpenMP creates the need for separate event handlers for threads of the same process. For example in an MPI+OpenMP hybrid application, the MPI thread and the main OpenMP thread may both want to be notified anytime an OpenMP worker thread enters a parallel region. This requiring support for multiple threads to potentially register different event handlers against the same status code.

Multiple event handlers registered against the same event are processed in a chain-like manner based on the order in which they were registered, as modified by directive. Registrations against specific event codes are processed first, followed by registrations against multiple event codes and then any default registrations. At each point in the chain, an event handler is called by the PMIx progress thread and given a function to call when that handler has completed its operation. The handler callback notifies PMIx that the handler is done, returning a status code to indicate the result of its work. The results are appended to the array of prior results, with the returned values combined into an array within a single pmix info t as follows:

- array [0]: the event handler name provided at registration (may be an empty field if a string name was not given) will be in the key, with the pmix status t value returned by the handler
- array [*]: the array of results returned by the handler, if any.

The current PMIx standard does not actually specify a default ordering for event handlers as they are being registered. However, it does include an inherent ordering for invocation. Specifically, PMIx stipulates that handlers be called in the following categorical order:

- single status event handlers i.e., handlers that were registered against a single specific status.
- multi status event handlers those registered against more than one specific status
- default event handlers those registered against no specific status

Code Example

1

From the OpenMP master thread:

```
static void parallel_region_OMP_cb(size_t evhdlr_registration_id,
                                     pmix_status_t status,
                                      const pmix_proc_t *source,
3
                                      pmix_info_t info[], size_t ninfo,
                                     pmix_info_t results[], size_t
5

    nresults,

                                     pmix_event_notification_cbfunc_fn_t

    ⇔ cbfunc,

                                      void *cbdata) {
7
    printf("Entered %s\n", __FUNCTION__);
    /* do what we need OpenMP to do on entering a parallel region */
   if (NULL != cbfunc) {
10
      /* tell the event handler that we are only a partial step */
      cbfunc(PMIX_EVENT_PARTIAL_ACTION_TAKEN, NULL, 0, NULL, NULL,
      13
14 }
15
    bool is_true = true;
16
    pmix_status_t code = PMIX_OPENMP_PARALLEL_ENTERED;
17
    PMIX_INFO_CREATE(info, 2);
18
    PMIX_INFO_LOAD(&info[0], PMIX_EVENT_HDLR_NAME, "OpenMP-Master",
19
    → PMIX_STRING);
    PMIX_INFO_LOAD(&info[1], PMIX_EVENT_HDLR_FIRST, &is_true, PMIX_BOOL);
20
    rc = PMIx_Register_event_handler(&code, 1, info, 2,

→ parallel_region_OMP_cb, NULL, NULL);
    if (rc < 0)
22
      fprintf(stderr, "%s: Failed to register event handler for OpenMP
      → region entrance\n", __FUNCTION__);
    PMIX_INFO_FREE(info, 2);
```

4 From the MPI thread:

```
printf("Entered %s\n", __FUNCTION__);
    /* do what we need MPI to do on entering a parallel region */
    if (NULL != cbfunc) {
10
      /* do what we need MPI to do on entering a parallel region */
11
     cbfunc(PMIX_EVENT_ACTION_COMPLETE, NULL, 0, NULL, NULL, cbdata);
12
13
14 }
15
    pmix_status_t code = PMIX_OPENMP_PARALLEL_ENTERED;
16
    PMIX_INFO_CREATE(info, 2);
17
    PMIX_INFO_LOAD(&info[0], PMIX_EVENT_HDLR_NAME, "MPI-Thread",
18
    PMIX_INFO_LOAD(&info[1], PMIX_EVENT_HDLR_AFTER, "OpenMP-Master",
    → PMIX STRING);
    rc = PMIx_Register_event_handler(&code, 1, info, 2,

→ parallel_region_MPI_cb, NULL, NULL);
    if (rc < 0)
21
      fprintf(stderr, "%s: Failed to register event handler for OpenMP
      → region entrance\n", __FUNCTION__);
    PMIX_INFO_FREE(info, 2);
```

```
Related Interfaces, Attributes, and Constants
 2
             PMIx_Register_event_handler
 3
   PMIx v2.0
4
             pmix_status_t
5
             PMIx_Register_event_handler(pmix_status_t codes[], size_t ncodes,
6
                                              pmix_info_t info[], size_t ninfo,
 7
                                              pmix_notification_fn_t evhdlr,
                                              pmix_hdlr_reg_cbfunc_t cbfunc,
8
                                              void *cbdata);
9
             PMIX_EVENT_HDLR_NAME "pmix.evname" (char*)
10
                   String name identifying this handler.
11
12
             PMIX_EVENT_HDLR_FIRST "pmix.evfirst" (bool)
                   Invoke this event handler before any other handlers.
13
             PMIX_EVENT_HDLR_LAST "pmix.evlast" (bool)
14
                   Invoke this event handler after all other handlers have been called.
15
             PMIX_EVENT_HDLR_FIRST_IN_CATEGORY "pmix.evfirstcat" (bool)
16
17
                   Invoke this event handler before any other handlers in this category.
```

```
PMIX_EVENT_HDLR_LAST_IN_CATEGORY "pmix.evlastcat" (bool)
 1
2
                   Invoke this event handler after all other handlers in this category have been called.
             PMIX_EVENT_HDLR_BEFORE "pmix.evbefore" (char*)
 3
                   Put this event handler immediately before the one specified in the (char*) value.
 4
5
             PMIX_EVENT_HDLR_AFTER "pmix.evafter" (char*)
6
                   Put this event handler immediately after the one specified in the (char*) value.
             PMIX_EVENT_HDLR_APPEND "pmix.evappend" (bool)
 7
                   Append this handler to the precedence list within its category.
8
             pmix event notification cbfunc fn t
9
   PMIx v2.0
10
             typedef void (*pmix event notification cbfunc fn t)
11
                  (pmix status t status,
                   pmix_info_t *results, size_t nresults,
12
                   pmix_op_cbfunc_t cbfunc, void *thiscbdata,
13
                   void *notification_cbdata);
14
15
             PMIX EVENT NO ACTION TAKEN
16
             PMIX EVENT PARTIAL ACTION TAKEN
17
             PMIX EVENT ACTION DEFERRED
```

APPENDIX C

2

4

5

7

8

9

10

11 12

13 14

15

16

19

20 21

22

26

Revision History

C.1 Version 1.0: June 12, 2015

The PMIx version 1.0 *ad hoc* standard was defined in a set of header files as part of the v1.0.0 release of the OpenPMIx library prior to the creation of the formal PMIx 2.0 standard. Below are a summary listing of the interfaces defined in the 1.0 headers.

- Client APIs
- 6 PMIx_Init, PMIx_Initialized, PMIx_Abort, PMIx_Finalize
 - PMIx_Put, PMIx Commit.
 - PMIx_Fence, PMIx_Fence_nb
 - PMIx Get, PMIx Get nb
 - PMIx Publish, PMIx Publish nb
 - PMIx Lookup, PMIx Lookup nb
 - PMIx_Unpublish, PMIx_Unpublish_nb
 - PMIx_Spawn, PMIx_Spawn_nb
 - PMIx Connect, PMIx Connect nb
 - PMIx Disconnect, PMIx Disconnect nb
 - PMIx_Resolve_nodes, PMIx_Resolve_peers
- Server APIs
- 18 PMIx_server_init, PMIx_server_finalize
 - PMIx generate regex, PMIx generate ppn
 - PMIx server register nspace, PMIx server deregister nspace
 - PMIx_server_register_client, PMIx_server_deregister_client
 - PMIx_server_setup_fork, PMIx_server_dmodex_request
- Common APIs
- 24 PMIx_Get_version, PMIx_Store_internal, PMIx_Error_string
- 25 PMIx_Register_errhandler, PMIx_Deregister_errhandler, PMIx_Notify_error

The **PMIx_Init** API was subsequently modified in the v1.1.0 release of that library.

C.2 Version 2.0: Sept. 2018

The following APIs were introduced in v2.0 of the PMIx Standard: 2 3 Client APIs - PMIx_Query_info_nb, PMIx_Log_nb 4 5 - PMIx Allocation request nb. PMIx Job control nb. PMIx Process monitor nb, PMIx Heartbeat 6 Server APIs 7 - PMIx server setup application, PMIx server setup local support 8 Tool APIs 9 10 - PMIx tool init, PMIx tool finalize Common APIs 11 12 - PMIx_Register_event_handler, PMIx_Deregister_event_handler 13 - PMIx Notify event 14 - PMIx Proc state string, PMIx Scope string - PMIx_Persistence_string, PMIx_Data_range_string 15 16 - PMIx_Info_directives_string, PMIx_Data_type_string - PMIx Alloc_directive_string 17 - PMIx Data pack, PMIx Data unpack, PMIx Data copy 18 - PMIx_Data_print, PMIx_Data_copy_payload 19 C.2.1 Removed/Modified APIs 21 The PMIx_Init API was modified in v2.0 of the standard from its ad hoc v1.0 signature to include passing of a pmix info t array for flexibility and "future-proofing" of the API. In

22 addition, the PMIx Notify error, PMIx Register errhandler, and 23 24 PMIx_Deregister_errhandler APIs were replaced. This pre-dated official adoption of 25 PMIx as a Standard.

C.2.2 **Deprecated constants**

The following constants were deprecated in v2.0:

28 PMIX MODEX 29 PMIX INFO_ARRAY

1 C.2.3 Deprecated attributes

2	The following attributes were deprecated in v2.0:
3	<pre>PMIX_ERROR_NAME "pmix.errname" (pmix_status_t)</pre>
4	Specific error to be notified
5	<pre>PMIX_ERROR_GROUP_COMM "pmix.errgroup.comm" (bool)</pre>
6	Set true to get comm errors notification
7	<pre>PMIX_ERROR_GROUP_ABORT "pmix.errgroup.abort" (bool)</pre>
8	Set true to get abort errors notification
9	<pre>PMIX_ERROR_GROUP_MIGRATE "pmix.errgroup.migrate" (bool)</pre>
10	Set true to get migrate errors notification
11	<pre>PMIX_ERROR_GROUP_RESOURCE "pmix.errgroup.resource" (bool</pre>
12	Set true to get resource errors notification
13	PMIX_ERROR_GROUP_SPAWN "pmix.errgroup.spawn" (bool)
14	Set true to get spawn errors notification
15	<pre>PMIX_ERROR_GROUP_NODE "pmix.errgroup.node" (bool)</pre>
16	Set true to get node status notification
17	<pre>PMIX_ERROR_GROUP_LOCAL "pmix.errgroup.local" (bool)</pre>
18	Set true to get local errors notification
19	<pre>PMIX_ERROR_GROUP_GENERAL "pmix.errgroup.gen" (bool)</pre>
20	Set true to get notified of generic errors
21	<pre>PMIX_ERROR_HANDLER_ID "pmix.errhandler.id" (int)</pre>
22	Errhandler reference id of notification being reported

3 C.3 Version 2.1: Dec. 2018

24 25

26 27

28 29

30

31

32

33

34

35 36

37

38

The v2.1 update includes clarifications and corrections from the v2.0 document, plus addition of examples:

- Clarify description of PMIx Connect and PMIx Disconnect APIs.
- Explain that values for the PMIX COLLECTIVE ALGO are environment-dependent
- Identify the namespace/rank values required for retrieving attribute-associated information using the PMIx Get API
- Provide definitions for session, job, application, and other terms used throughout the document
- Clarify definitions of PMIX_UNIV_SIZE versus PMIX_JOB_SIZE
- Clarify server module function return values
- Provide examples of the use of **PMIx_Get** for retrieval of information
- Clarify the use of PMIx_Get versus PMIx_Query_info_nb
- Clarify return values for non-blocking APIs and emphasize that callback functions must not be invoked prior to return from the API
- Provide detailed example for construction of the PMIx_server_register_nspace input information array

- 1 • Define information levels (e.g., session vs job) and associated attributes for both storing and 2 retrieving values
 - Clarify roles of PMIx server library and host environment for collective operations
 - Clarify definition of PMIX_UNIV_SIZE

C.4 Version 2.2: Jan 2019

The v2.2 update includes the following clarifications and corrections from the v2.1 document:

- Direct modex upcall function (pmix_server_dmodex_req_fn_t) cannot complete atomically as the API cannot return the requested information except via the provided callback function
- Add missing pmix_data_array_t definition and support macros
- Add a rule divider between implementer and host environment required attributes for clarity
- Add PMIX QUERY QUALIFIERS CREATE macro to simplify creation of pmix query t qualifiers
- Add PMIX_APP_INFO_CREATE macro to simplify creation of pmix_app_t directives
- Add flag and PMIX INFO IS END macro for marking and detecting the end of a pmix info t array
- Clarify the allowed hierarchical nesting of the PMIX SESSION INFO ARRAY, PMIX JOB INFO ARRAY, and associated attributes

C.5 Version 3.0: Dec. 2018

- 20 The following APIs were introduced in v3.0 of the PMIx Standard:
- Client APIs 21

3

4

6 7

8

9 10

11 12

13

14

15 16

17

18

22

23

24

26

27

- PMIx_Log, PMIx_Job_control
 - PMIx_Allocation_request, PMIx_Process_monitor
 - PMIx_Get_credential, PMIx_Validate_credential
- 25 Server APIs
 - PMIx server IOF deliver
 - PMIx server_collect_inventory, PMIx_server_deliver_inventory
- Tool APIs 28
 - PMIx_IOF_pull, PMIx_IOF_push, PMIx_IOF_deregister
- 30 - PMIx tool connect to server
- Common APIs 31
- 32 - PMIx IOF channel string

1 The document added a chapter on security credentials, a new section for IO forwarding to the 2 Process Management chapter, and a few blocking forms of previously-existing non-blocking APIs. Attributes supporting the new APIs were introduced, as well as additional attributes for a few 3 existing functions. 4 C.5.1 Removed constants 6 The following constants were removed in v3.0: 7 PMIX MODEX 8 PMIX INFO ARRAY C.5.2 Deprecated attributes 10 The following attributes were deprecated in v3.0: 11 PMIX COLLECTIVE ALGO REQD "pmix.calregd" (bool) 12 If **true**, indicates that the requested choice of algorithm is mandatory. C.5.3 Removed attributes 14 The following attributes were removed in v3.0: PMIX_ERROR_NAME "pmix.errname" (pmix_status_t) 15 Specific error to be notified 16 17 PMIX_ERROR_GROUP_COMM "pmix.errgroup.comm" (bool) Set true to get comm errors notification 18 PMIX_ERROR_GROUP_ABORT "pmix.errgroup.abort" (bool) 19 20 Set true to get abort errors notification 21 PMIX_ERROR_GROUP_MIGRATE "pmix.errgroup.migrate" (bool) 22 Set true to get migrate errors notification PMIX_ERROR_GROUP_RESOURCE "pmix.errgroup.resource" (bool) 23 24 Set true to get resource errors notification 25 PMIX_ERROR_GROUP_SPAWN "pmix.errgroup.spawn" (bool) Set true to get spawn errors notification 26 PMIX ERROR GROUP NODE "pmix.errgroup.node" (bool) 27 28 Set true to get node status notification 29 PMIX_ERROR_GROUP_LOCAL "pmix.errgroup.local" (bool) Set true to get local errors notification

PMIX ERROR_GROUP_GENERAL "pmix.errgroup.gen" (bool)

PMIX ERROR HANDLER ID "pmix.errhandler.id" (int) Errhandler reference id of notification being reported

Set true to get notified of generic errors

30

31 32

33

34

APPENDIX C. REVISION HISTORY

C.6 Version 3.1: Jan. 2019

2

4

5 6

7

8

10

11

12

13

14 15

16

17 18

19

20 21

22

23 24

25

26 27

28

29 30

32

33

34

35

36

- The v3.1 update includes clarifications and corrections from the v3.0 document:
 - Direct modex upcall function (pmix_server_dmodex_req_fn_t) cannot complete
 atomically as the API cannot return the requested information except via the provided callback
 function
 - Fix typo in name of **PMIX FWD STDDIAG** attribute
 - Correctly identify the information retrieval and storage attributes as "new" to v3 of the standard
 - Add missing pmix_data_array_t definition and support macros
 - Add a rule divider between implementer and host environment required attributes for clarity
 - Add PMIX_QUERY_QUALIFIERS_CREATE macro to simplify creation of pmix_query_t qualifiers
 - Add PMIX_APP_INFO_CREATE macro to simplify creation of pmix_app_t directives
 - Add new attributes to specify the level of information being requested where ambiguity may exist (see 6.1)
 - Add new attributes to assemble information by its level for storage where ambiguity may exist (see 16.2.3.1)
 - Add flag and PMIX_INFO_IS_END macro for marking and detecting the end of a pmix_info_t array
 - Clarify that PMIX_NUM_SLOTS is duplicative of (a) PMIX_UNIV_SIZE when used at the session level and (b) PMIX_MAX_PROCS when used at the job and application levels, but leave it in for backward compatibility.
 - Clarify difference between PMIX_JOB_SIZE and PMIX_MAX_PROCS
 - Clarify that PMIx_server_setup_application must be called per-job instead of per-application as the name implies. Unfortunately, this is a historical artifact. Note that both PMIX_NODE_MAP and PMIX_PROC_MAP must be included as input in the *info* array provided to that function. Further descriptive explanation of the "instant on" procedure will be provided in the next version of the PMIx Standard.
 - Clarify how the PMIx server expects data passed to the host by
 pmix_server_fencenb_fn_t should be aggregated across nodes, and provide a code
 snippet example

C.7 Version 3.2: Oct. 2020

- The v3.2 update includes clarifications and corrections from the v3.1 document:
- Correct an error in the **PMIx_Allocation_request** function signature, and clarify the allocation ID attributes
- Rename the **PMIX_ALLOC_ID** attribute to **PMIX_ALLOC_REQ_ID** to clarify that this is a string the user provides as a means to identify their request to query status

- Add a new PMIX_ALLOC_ID attribute that contains the identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx_Spawn
 - Update the PMIx_generate_regex and PMIx_generate_ppn descriptions to clarify
 that the output from these generator functions may not be a NULL-terminated string, but instead
 could be a byte array of arbitrary binary content.
 - Add a new PMIX_REGEX constant that represents a regular expression data type.

C.7.1 Deprecated constants

1

3

5

6

7

9

The following constants were deprecated in v3.2:

```
10
              PMIX_ERR_DATA_VALUE_NOT_FOUND
                                                     Data value not found
              PMIX_ERR_HANDSHAKE_FAILED
                                                Connection handshake failed
11
              PMIX ERR IN ERRNO
                                       Error defined in errno
12
              PMIX ERR_INVALID_ARG
13
                                          Invalid argument
                                           Invalid arguments
14
              PMIX ERR INVALID ARGS
15
              PMIX_ERR_INVALID_KEY
                                          Invalid key
16
              PMIX ERR INVALID KEY LENGTH
                                                   Invalid key length
17
              PMIX_ERR_INVALID_KEYVALP
                                               Invalid key/value pair
                                              Invalid argument length
18
              PMIX_ERR_INVALID_LENGTH
19
              PMIX ERR INVALID NAMESPACE
                                                  Invalid namespace
                                                Invalid number of arguments
20
              PMIX ERR INVALID NUM ARGS
                                                   Invalid number parsed
21
              PMIX ERR INVALID NUM PARSED
              PMIX_ERR_INVALID_SIZE
                                           Invalid size
22
23
              PMIX ERR INVALID VAL
                                          Invalid value
24
              PMIX ERR INVALID VAL LENGTH
                                                   Invalid value length
                                               Not implemented
25
              PMIX_ERR_NOT_IMPLEMENTED
              PMIX_ERR_PACK_MISMATCH
                                             Pack mismatch
26
27
              PMIX ERR PROC ENTRY NOT FOUND
                                                     Process not found
28
              PMIX ERR PROC REQUESTED ABORT
                                                     Process is already requested to abort
              PMIX ERR READY FOR HANDSHAKE
29
                                                    Ready for handshake
              PMIX_ERR_SERVER_FAILED_REQUEST
30
                                                       Failed to connect to the server
                                                Server is not available
              PMIX ERR SERVER NOT AVAIL
31
32
              PMIX ERR SILENT
                                    Silent error
              PMIX_GDS_ACTION_COMPLETE
33
                                               The Global Data Storage (GDS) action has completed
34
              PMIX NOTIFY ALLOC COMPLETE
                                                  Notify that a requested allocation operation is complete
35
                    the result of the request will be included in the info array
```

1 C.7.2 Deprecated attributes

```
2
              The following attributes were deprecated in v3.2:
 3
              PMIX_ARCH "pmix.arch" (uint32_t)
                    Architecture flag.
 4
5
              PMIX_COLLECTIVE_ALGO "pmix.calgo" (char*)
6
                    Comma-delimited list of algorithms to use for the collective operation. PMIx does not
7
                    impose any requirements on a host environment's collective algorithms. Thus, the
8
                    acceptable values for this attribute will be environment-dependent - users are encouraged to
9
                    check their host environment for supported values.
10
              PMIX DSTPATH "pmix.dstpath" (char*)
                    Path to shared memory data storage (dstore) files. Deprecated from Standard as being
11
12
                    implementation specific.
              PMIX HWLOC HOLE KIND "pmix.hwlocholek" (char*)
13
                    Kind of VM "hole" HWLOC should use for shared memory
14
15
              PMIX HWLOC SHARE TOPO "pmix.hwlocsh" (bool)
                    Share the HWLOC topology via shared memory
16
              PMIX_HWLOC_SHMEM_ADDR "pmix.hwlocaddr" (size_t)
17
                    Address of the HWLOC shared memory segment.
18
19
              PMIX HWLOC SHMEM FILE "pmix.hwlocfile" (char*)
20
                    Path to the HWLOC shared memory file.
              PMIX_HWLOC_SHMEM_SIZE "pmix.hwlocsize" (size_t)
21
22
                    Size of the HWLOC shared memory segment.
              PMIX HWLOC XML V1 "pmix.hwlocxml1" (char*)
23
                    XML representation of local topology using HWLOC's v1.x format.
24
              PMIX_HWLOC_XML_V2 "pmix.hwlocxm12" (char*)
25
26
                    XML representation of local topology using HWLOC's v2.x format.
              PMIX LOCAL TOPO "pmix.ltopo" (char*)
27
                    XML representation of local node topology.
28
              PMIX MAPPER "pmix.mapper" (char*)
29
                    Mapping mechanism to use for placing spawned processes - when accessed using
30
                    PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping
31
32
                    mechanism used for the provided namespace.
33
              PMIX MAP BLOB "pmix.mblob" (pmix byte object t)
                    Packed blob of process location.
34
              PMIX_NON_PMI "pmix.nonpmi" (bool)
35
                    Spawned processes will not call PMIx Init.
36
37
              PMIX PROC BLOB "pmix.pblob" (pmix byte object t)
                    Packed blob of process data.
38
              PMIX_PROC_URI "pmix.puri" (char*)
39
                    URI containing contact information for the specified process.
40
              PMIX_TOPOLOGY_FILE "pmix.topo.file" (char*)
41
42
                    Full path to file containing XML topology description
```

1 2 3 4		PMIX_TOPOLOGY_SIGNATURE "pmix.toposig" (char*) Topology signature string. PMIX_TOPOLOGY_XML "pmix.topo.xml" (char*) XML-based description of topology
5	C.8	Version 4.0: Dec. 2020
6 7		NOTE: The PMIx Standard document has undergone significant reorganization in an effort to become more user-friendly. Highlights include:
8 9 10 11 12 13 14 15 16		 Moving all added, deprecated, and removed items to this revision log section to make them more visible Co-locating constants and attribute definitions with the primary API that uses them - citations and hyperlinks are retained elsewhere Splitting the Key-Value Management chapter into separate chapters on the use of reserved keys, non-reserved keys, and non-process-related key-value data exchange Creating a new chapter on synchronization and data access methods Removing references to specific implementations of PMIx and to implementation-specific features and/or behaviors
17 18		In addition to the reorganization, the following changes were introduced in v4.0 of the PMIx Standard:
19 20 21 22 23 24		 Clarified that the PMIx_Fence_nb operation can immediately return PMIX_OPERATION_SUCCEEDED in lieu of passing the request to a PMIx server if only the calling process is involved in the operation Added the PMIx_Register_attributes API by which a host environment can register the attributes it supports for each server-to-host operation Added the ability to query supported attributes from the PMIx tool, client and server libraries, as

PMIX_CLIENT_ATTRIBUTES, PMIX_SERVER_ATTRIBUTES,
 PMIX_TOOL_ATTRIBUTES, and PMIX_HOST_ATTRIBUTES to identify which library supports the attribute; and

and machine-parsable output is supported. New attributes to support this operation include:

well as the host environment via the new pmix_regattr_t structure. Both human-readable

- PMIX_MAX_VALUE, PMIX_MIN_VALUE, and PMIX_ENUM_VALUE to provide machine-parsable description of accepted values
- Add PMIX APP WILDCARD to reference all applications within a given job

- Fix signature of blocking APIs PMIx_Allocation_request, PMIx_Job_control, PMIx_Process_monitor, PMIx_Get_credential, and PMIx_Validate_credential to allow return of results
- Update description to provide an option for blocking behavior of the
 PMIx_Register_event_handler, PMIx_Deregister_event_handler,
 PMIx_Notify_event, PMIx_IOF_pull, PMIx_IOF_deregister, and
 PMIx IOF push APIs. The need for blocking forms of these functions was not initially

4 5 6

7 8 9

11 12 13

14

10

15 16

17 18

19

20 21

22 23 24

25 26 27

28 29

30 31 32

33 34

35

36

37 38

39 40 anticipated but has emerged over time. For these functions, the return value is sufficient to provide the caller with information otherwise returned via callback. Thus, use of a **NULL** value as the callback function parameter was deemed a minimal disruption method for providing the desired capability

- Added a chapter on fabric support that includes new APIs, datatypes, and attributes
- Added a chapter on process sets and groups that includes new APIs and attributes
- Added APIs and a new datatypes to support generation and parsing of PMIx locality and cpuset strings
- Added a new chapter on tools that provides deeper explanation on their operation and collecting all tool-relevant definitions into one location. Also introduced two new APIs and removed restriction that limited tools to being connected to only one server at a time.
- Extended behavior of PMIx_server_init to scalably expose the topology description to the local clients. This includes creating any required shared memory backing stores and/or XML representations, plus ensuring that all necessary key-value pairs for clients to access the description are included in the job-level information provided to each client.
- Added a new API by which the host can manually progress the PMIx library in lieu of the library's own progress thread. s

The above changes included introduction of the following APIs and data types:

- Client APIs
 - PMIx_Group_construct, PMIx_Group_construct_nb
 - PMIx_Group_destruct, PMIx_Group_destruct_nb
 - PMIx_Group_invite, PMIx_Group_invite_nb
 - PMIx Group join, PMIx Group join nb
 - PMIx Group leave, PMIx Group leave nb
 - PMIx_Get_relative_locality, PMIx_Load_topology
 - PMIx_Parse_cpuset_string, PMIx_Get_cpuset
 - PMIx Link state string, PMIx Job state string
 - PMIx_Device_type_string
 - PMIx_Fabric_register, PMIx_Fabric_register_nb
 - PMIx_Fabric_update, PMIx_Fabric_update_nb
 - PMIx Fabric deregister, PMIx Fabric deregister nb
 - PMIx_Compute_distances, PMIx_Compute_distances_nb
 - PMIx Get attribute string, PMIx Get attribute name
 - PMIx Progress
- Server APIs
 - PMIx_server_generate_locality_string
 - PMIx_Register_attributes
 - PMIx_server_define_process_set, PMIx_server_delete_process_set
 - pmix server grp fn t, pmix server fabric fn t
 - pmix server client connected2 fn t

```
1
              - PMIx_server_generate_cpuset_string
2
              - PMIx server register resources, PMIx server deregister resources
            • Tool APIs
 3
              - PMIx tool disconnect
 4
5
              - PMIx_tool_set_server
6
              - PMIx_tool_attach_to_server
 7
              - PMIx_tool_get_servers
8
            • Data types
9
              - pmix regattr t
              - pmix_cpuset_t
10
11
              - pmix_topology_t
12
              - pmix_locality_t
              - pmix bind envelope t
13
              - pmix_group_opt_t
14
15
              - pmix_group_operation_t
16
              - pmix_fabric_t
17
              - pmix_device_distance_t
18
              - pmix_coord_t
19
              - pmix coord view t
20
              - pmix geometry t
21
              - pmix_link_state_t
22
              - pmix_job_state_t
              - pmix_device_type_t
23
24
            • Callback functions
              - pmix_device_dist_cbfunc_t
25
   C.8.1 Added Constants
            General error constants
27
```

PMIX ERR EXISTS OUTSIDE SCOPE

PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED

28

29

30

APPENDIX C. REVISION HISTORY

1	Data type constants
2	PMIX_COORD
3	PMIX_REGATTR
4	PMIX_REGEX
5	PMIX_JOB_STATE
6	PMIX_LINK_STATE
7	PMIX_PROC_CPUSET
8	PMIX_GEOMETRY
9	PMIX_DEVICE_DIST
10	PMIX_ENDPOINT
11	PMIX_TOPO
12	PMIX_DEVTYPE
13	PMIX_LOCTYPE
14	PMIX DATA TYPE MAX
15	PMIX_COMPRESSED_BYTE_OBJECT
16	
17	Info directives
18	PMIX_INFO_REQD_PROCESSED
19	
20	Server constants
20 21	PMIX ERR REPEAT ATTR REGISTRATION
22	FMIX_ERR_REPEAI_ATTR_REGISTRATION
23	Job-Mgmt constants
24	PMIX ERR CONFLICTING CLEANUP DIRECTIVES
25	
26	Publish constants
27	PMIX_ERR_DUPLICATE_KEY
28	
20	Tool constants
29	Tool constants
30	PMIX_LAUNCHER_READY
31 32	PMIX_ERR_IOF_FAILURE
	PMIX_ERR_IOF_COMPLETE
33	PMIX_EVENT_JOB_START
34	PMIX_LAUNCH_COMPLETE
35 36	PMIX_EVENT_JOB_END
36 27	PMIX_EVENT_SESSION_START
37 30	PMIX_EVENT_SESSION_END
38 20	PMIX_ERR_PROC_TERM_WO_SYNC
39 10	PMIX_ERR_JOB_CANCELED DMIX_ERR_JOB_ABOPTED
	FINIA BEEK OUR ARUKTEU

1	PMIX_ERR_JOB_KILLED_BY_CMD
2	PMIX_ERR_JOB_ABORTED_BY_SIG
3	PMIX ERR JOB TERM WO SYNC
4	PMIX ERR JOB SENSOR BOUND EXCEEDED
5	PMIX_ERR_JOB_NON_ZERO_TERM
6	PMIX ERR JOB ABORTED BY SYS EVENT
7	PMIX DEBUG WAITING FOR NOTIFY
8	PMIX DEBUGGER RELEASE
9	
10	Fabric constants
11	PMIX_FABRIC_UPDATE_PENDING
12	PMIX_FABRIC_UPDATED
13	PMIX_FABRIC_UPDATE_ENDPOINTS
14	PMIX_COORD_VIEW_UNDEF
15	PMIX_COORD_LOGICAL_VIEW
16	PMIX_COORD_PHYSICAL_VIEW
17	PMIX_LINK_STATE_UNKNOWN
18	PMIX_LINK_DOWN
19	PMIX_LINK_UP
20	PMIX_FABRIC_REQUEST_INFO
21	PMIX_FABRIC_UPDATE_INFO
22	
23	Sets-Groups constants
-0 24	PMIX PROCESS SET DEFINE
- · 25	PMIX PROCESS SET DELETE
-0 26	PMIX GROUP INVITED
27	PMIX GROUP LEFT
28	PMIX GROUP MEMBER FAILED
29	PMIX_GROUP_INVITE_ACCEPTED
30	PMIX GROUP INVITE DECLINED
31	PMIX GROUP INVITE FAILED
32	PMIX_GROUP_MEMBERSHIP_UPDATE
33	PMIX GROUP CONSTRUCT ABORT
34	PMIX GROUP CONSTRUCT COMPLETE
35	PMIX GROUP LEADER FAILED
36	PMIX_GROUP_LEADER_SELECTED
37	PMIX GROUP CONTEXT ID ASSIGNED
38	
39	Process-Mgmt constants
40	PMIX_ERR_JOB_ALLOC_FAILED
41	PMIX_ERR_JOB_APP_NOT_EXECUTABLE

```
1
            PMIX_ERR_JOB_NO_EXE_SPECIFIED
2
            PMIX ERR JOB FAILED TO MAP
3
            PMIX ERR JOB FAILED TO LAUNCH
4
            PMIX LOCALITY UNKNOWN
5
            PMIX LOCALITY NONLOCAL
6
            PMIX LOCALITY SHARE HWTHREAD
7
            PMIX LOCALITY SHARE CORE
8
            PMIX LOCALITY SHARE L1CACHE
9
            PMIX LOCALITY SHARE L2CACHE
10
            PMIX_LOCALITY_SHARE_L3CACHE
11
            PMIX_LOCALITY_SHARE_PACKAGE
12
            PMIX_LOCALITY_SHARE_NUMA
13
            PMIX LOCALITY SHARE NODE
14
            Events
15
16
            PMIX EVENT SYS BASE
17
            PMIX EVENT NODE DOWN
```

C.8.2 Added Attributes

Sync-Access attributes

PMIX EVENT NODE OFFLINE

PMIX EVENT SYS OTHER

PMIX_COLLECT_GENERATED_JOB_INFO "pmix.collect.gen" (bool)

Collect all job-level information (i.e., reserved keys) that was locally generated by PMIx

servers. Some job-level information (e.g., distance between processes and fabric devices) is best determined on a distributed basis as it primarily pertains to local processes. Should remote processes need to access the information, it can either be obtained collectively using the PMIx_Fence operation with this directive, or can be retrieved one peer at a time using PMIx_Get without first having performed the job-wide collection.

PMIX_ALL_CLONES_PARTICIPATE "pmix.clone.part" (bool)

All *clones* of the calling process must participate in the collective operation.

PMIX_GET_POINTER_VALUES "pmix.get.pntrs" (bool)

Request that any pointers in the returned value point directly to values in the key-value store. The user *must not* release any returned data pointers.

PMIX_GET_STATIC_VALUES "pmix.get.static" (bool)

Request that the data be returned in the provided storage location. The caller is responsible for destructing the <code>pmix_value_t</code> using the <code>PMIX_VALUE_DESTRUCT</code> macro when done.

PMIX_GET_REFRESH_CACHE "pmix.get.refresh" (bool)

18

19

20

22

23

24

25

26 27

28

29 30

31

32

33

34 35

36

37 38

1 2 3 4 5 6 7 8	When retrieving data for a remote process, refresh the existing local data cache for the process in case new values have been put and committed by the process since the last refresh Local process information is assumed to be automatically updated upon posting by the process. A NULL key will cause all values associated with the process to be refreshed - otherwise, only the indicated key will be updated. A process rank of PMIX_RANK_WILDCARD can be used to update job-related information in dynamic environments. The user is responsible for subsequently updating refreshed values they may have cached in their own local memory.
9 10 11 12 13 14 15	PMIX_QUERY_RESULTS "pmix.qry.res" (pmix_data_array_t) Contains an array of query results for a given pmix_query_t passed to the PMIX_Query_info APIs. If qualifiers were included in the query, then the first element of the array shall be the PMIX_QUERY_QUALIFIERS attribute containing those qualifiers. Each of the remaining elements of the array is a pmix_info_t containing the query key and the corresponding value returned by the query. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or other query operations.
16 17 18 19	<pre>PMIX_QUERY_QUALIFIERS "pmix.qry.quals" (pmix_data_array_t) Contains an array of qualifiers that were included in the query that produced the provided results. This attribute is solely for reporting purposes and cannot be used in PMIx_Get or other query operations.</pre>
20 21	<pre>PMIX_QUERY_SUPPORTED_KEYS "pmix.qry.keys" (char*) Returns comma-delimited list of keys supported by the query function. NO QUALIFIERS.</pre>
22 23 24	<pre>PMIX_QUERY_SUPPORTED_QUALIFIERS "pmix.qry.quals" (char*) Return comma-delimited list of qualifiers supported by a query on the provided key, instead of actually performing the query on the key. NO QUALIFIERS.</pre>
25 26 27 28 29	PMIX_QUERY_NAMESPACE_INFO "pmix.qry.nsinfo" (pmix_data_array_t*) Return an array of active namespace information - each element will itself contain an array including the namespace plus the command line of the application executing within it. OPTIONAL QUALIFIERS: PMIX_NSPACE of specific namespace whose info is being requested.
30 31 32 33	<pre>PMIX_QUERY_ATTRIBUTE_SUPPORT "pmix.qry.attrs" (bool) Query list of supported attributes for specified APIs. REQUIRED QUALIFIERS: one or more of PMIX_CLIENT_FUNCTIONS, PMIX_SERVER_FUNCTIONS, PMIX_TOOL_FUNCTIONS, and PMIX_HOST_FUNCTIONS.</pre>
34 35 36 37	PMIX_QUERY_AVAIL_SERVERS "pmix.qry.asrvrs" (pmix_data_array_t*) Return an array of pmix_info_t, each element itself containing a PMIX_SERVER_INFO_ARRAY entry holding all available data for a server on this node to which the caller might be able to connect.
38	PMIX_SERVER_INFO_ARRAY "pmix.srv.arr" (pmix_data_array_t)

1 2	Array of pmix_info_t about a given server, starting with its PMIX_NSPACE and including at least one of the rendezvous-required pieces of information.
3 4	PMIX_CLIENT_FUNCTIONS "pmix.client.fns" (bool) Request a list of functions supported by the PMIx client library.
5 6	PMIX_CLIENT_ATTRIBUTES "pmix.client.attrs" (bool) Request attributes supported by the PMIx client library.
7 8	PMIX_SERVER_FUNCTIONS "pmix.srvr.fns" (bool) Request a list of functions supported by the PMIx server library.
9 10	PMIX_SERVER_ATTRIBUTES "pmix.srvr.attrs" (bool) Request attributes supported by the PMIx server library.
11 12	PMIX_HOST_FUNCTIONS "pmix.srvr.fns" (bool) Request a list of functions supported by the host environment.
13 14	PMIX_HOST_ATTRIBUTES "pmix.host.attrs" (bool) Request attributes supported by the host environment.
15 16	PMIX_TOOL_FUNCTIONS "pmix.tool.fns" (bool) Request a list of functions supported by the PMIx tool library.
17 18	PMIX_TOOL_ATTRIBUTES "pmix.setup.env" (bool) Request attributes supported by the PMIx tool library functions.
19 20 21	Server attributes PMIX_TOPOLOGY2 "pmix.topo2" (pmix_topology_t) Provide a pointer to an implementation-specific description of the local node topology.
22 23 24	<pre>PMIX_SERVER_SHARE_TOPOLOGY "pmix.srvr.share" (bool) The PMIx server is to share its copy of the local node topology (whether given to it or self-discovered) with any clients.</pre>
25 26 27	PMIX_SERVER_SESSION_SUPPORT "pmix.srvr.sess" (bool) The host RM wants to declare itself as being the local session server for PMIx connection requests.
28 29 30	<pre>PMIX_SERVER_START_TIME "pmix.srvr.strtime" (char*) Time when the server started - i.e., when the server created it's rendezvous file (given in ctime string format).</pre>
31 32 33	PMIX_SERVER_SCHEDULER "pmix.srv.sched" (bool) Server is supporting system scheduler and desires access to appropriate WLM-supporting features. Indicates that the library is to be initialized for scheduler support.
34	<pre>PMIX_JOB_INFO_ARRAY "pmix.job.arr" (pmix_data_array_t)</pre>

Provide an array of <code>pmix_info_t</code> containing job-realm information. The <code>PMIX_SESSION_ID</code> attribute of the <code>session</code> containing the <code>job</code> is required to be included in the array whenever the PMIx server library may host multiple sessions (e.g., when executing with a host RM daemon). As information is registered one job (aka namespace) at a time via the <code>PMIx_server_register_nspace</code> API, there is no requirement that the array contain either the <code>PMIX_NSPACE</code> or <code>PMIX_JOBID</code> attributes when used in that context (though either or both of them may be included). At least one of the job identifiers must be provided in all other contexts where the job being referenced is ambiguous.

PMIX_APP_INFO_ARRAY "pmix.app.arr" (pmix_data_array_t)

Provide an array of **pmix_info_t** containing application-realm information. The **PMIX_NSPACE** or **PMIX_JOBID** attributes of the *job* containing the application, plus its **PMIX_APPNUM** attribute, must to be included in the array when the array is *not* included as part of a call to **PMIx_server_register_nspace** - i.e., when the job containing the application is ambiguous. The job identification is otherwise optional.

PMIX_PROC_INFO_ARRAY "pmix.pdata" (pmix_data_array_t)

Provide an array of pmix_info_t containing process-realm information. The PMIX_RANK and PMIX_NSPACE attributes, or the PMIX_PROCID attribute, are required to be included in the array when the array is not included as part of a call to PMIX_server_register_nspace - i.e., when the job containing the process is ambiguous. All three may be included if desired. When the array is included in some broader structure that identifies the job, then only the PMIX_RANK or the PMIX_PROCID attribute must be included (the others are optional).

PMIX_NODE_INFO_ARRAY "pmix.node.arr" (pmix_data_array_t)

Provide an array of **pmix_info_t** containing node-realm information. At a minimum, either the **PMIX_NODEID** or **PMIX_HOSTNAME** attribute is required to be included in the array, though both may be included.

PMIX_MAX_VALUE "pmix.descr.maxval" (varies)

Used in **pmix_regattr_t** to describe the maximum valid value for the associated attribute.

PMIX_MIN_VALUE "pmix.descr.minval" (varies)

Used in **pmix_regattr_t** to describe the minimum valid value for the associated attribute.

PMIX_ENUM_VALUE "pmix.descr.enum" (char*)

Used in <code>pmix_regattr_t</code> to describe accepted values for the associated attribute. Numerical values shall be presented in a form convertible to the attribute's declared data type. Named values (i.e., values defined by constant names via a typical C-language enum declaration) must be provided as their numerical equivalent.

PMIX_HOMOGENEOUS_SYSTEM "pmix.homo" (bool)

The nodes comprising the session are homogeneous - i.e., they each contain the same number of identical packages, fabric interfaces, GPUs, and other devices.

1 PMIX_REQUIRED_KEY "pmix.req.key" (char*) Identifies a key that must be included in the requested information. If the specified key is not 2 3 already available, then the PMIx servers are required to delay response to the dmodex 4 request until either the key becomes available or the request times out. **Job-Mgmt attributes** 5 6 PMIX_ALLOC_ID "pmix.alloc.id" (char*) 7 A string identifier (provided by the host environment) for the resulting allocation which can later be used to reference the allocated resources in, for example, a call to PMIx Spawn. 8 9 PMIX ALLOC QUEUE "pmix.alloc.queue" (char*) Name of the WLM queue to which the allocation request is to be directed, or the queue being 10 referenced in a query. 11 **Publish attributes** 12 13 PMIX_ACCESS_PERMISSIONS "pmix.aperms" (pmix_data_array_t) Define access permissions for the published data. The value shall contain an array of 14 pmix_info_t structs containing the specified permissions. 15 PMIX_ACCESS_USERIDS "pmix.auids" (pmix_data_array_t) 16 Array of effective UIDs that are allowed to access the published data. 17 PMIX_ACCESS_GRPIDS "pmix.agids" (pmix_data_array_t) 18 Array of effective GIDs that are allowed to access the published data. 19 Reserved keys 20 21 PMIX NUM ALLOCATED NODES "pmix.num.anodes" (uint32 t) Number of nodes in the specified realm regardless of whether or not they currently host 22 23 processes. Defaults to the *job* realm. PMIX_NUM_NODES "pmix.num.nodes" (uint32_t) 24 Number of nodes currently hosting processes in the specified realm. Defaults to the *job* 25 26 realm. PMIX_CMD_LINE "pmix.cmd.line" (char*) 27 Command line used to execute the specified job (e.g., "mpirun -n 2 -map-by foo ./myapp: -n 28 29 4 ./myapp2"). 30 PMIX_APP_ARGV "pmix.app.argv" (char*) Consolidated argy passed to the spawn command for the given application (e.g., "./myapp 31 arg1 arg2 arg3"). 32 33 PMIX PACKAGE RANK "pmix.pkgrank" (uint16 t) Rank of the specified process on the *package* where this process resides - refers to the 34 numerical location (starting from zero) of the process on its package when counting only 35 those processes from the same job that share the package, ordered by their overall rank 36 37 within that job. Note that processes that are not bound to PUs within a single specific 38 package cannot have a package rank.

1 2 3	PMIX_REINCARNATION "pmix.reinc" (uint32_t) Number of times this process has been re-instantiated - i.e, a value of zero indicates that the process has never been restarted. 5
4 5	PMIX_HOSTNAME_ALIASES "pmix.alias" (char*) Comma-delimited list of names by which the target node is known.
6 7	PMIX_HOSTNAME_KEEP_FQDN "pmix.fqdn" (bool) FQDNs are being retained by the PMIx library.
8 9	PMIX_CPUSET_BITMAP "pmix.bitmap" (pmix_cpuset_t*) Bitmap applied to the process upon launch.
10 11	PMIX_EXTERNAL_PROGRESS "pmix.evext" (bool) The host shall progress the PMIx library via calls to PMIx_Progress
12 13 14	PMIX_NODE_MAP_RAW "pmix.nmap.raw" (char*) Comma-delimited list of nodes containing procs within the specified realm. Defaults to the <i>job</i> realm.
15 16 17	PMIX_PROC_MAP_RAW "pmix.pmap.raw" (char*) Semi-colon delimited list of strings, each string containing a comma-delimited list of ranks on the corresponding node within the specified realm. Defaults to the <i>job</i> realm.
18 19 20 21	Tool attributes PMIX_TOOL_CONNECT_OPTIONAL "pmix.tool.conopt" (bool) The tool shall connect to a server if available, but otherwise continue to operate unconnected.
22 23 24	<pre>PMIX_TOOL_ATTACHMENT_FILE "pmix.tool.attach" (char*) Pathname of file containing connection information to be used for attaching to a specific server.</pre>
25 26 27	PMIX_LAUNCHER_RENDEZVOUS_FILE "pmix.tool.lncrnd" (char*) Pathname of file where the launcher is to store its connection information so that the spawning tool can connect to it.
28 29 30	PMIX_PRIMARY_SERVER "pmix.pri.srvr" (bool) The server to which the tool is connecting shall be designated the <i>primary</i> server once connection has been accomplished.
31 32 33 34	PMIX_NOHUP "pmix.nohup" (bool) Any processes started on behalf of the calling tool (or the specified namespace, if such specification is included in the list of attributes) should continue after the tool disconnects from its server.
35	PMIX_LAUNCHER_DAEMON "pmix.lnch.dmn" (char*)

 Path to executable that is to be used as the backend daemon for the launcher. This replaces the launcher's own daemon with the specified executable. Note that the user is therefore responsible for ensuring compatibility of the specified executable and the host launcher.

PMIX FORKEXEC AGENT "pmix.frkex.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The fork/exec agent shall connect back (as a PMIx tool) to the launcher's daemon to receive its spawn instructions, and is responsible for starting the actual application process it replaced. See Section 17.4.3 for details.

PMIX_EXEC_AGENT "pmix.exec.agnt" (char*)

Path to executable that the launcher's backend daemons are to fork/exec in place of the actual application processes. The launcher's daemon shall pass the full command line of the application on the command line of the exec agent, which shall not connect back to the launcher's daemon. The exec agent is responsible for exec'ing the specified application process in its own place. See Section 17.4.3 for details.

PMIX_IOF_PUSH_STDIN "pmix.iof.stdin" (bool)

Requests that the PMIx library collect the **stdin** of the requester and forward it to the processes specified in the **PMIx_IOF_push** call. All collected data is sent to the same targets until **stdin** is closed, or a subsequent call to **PMIx_IOF_push** is made that includes the **PMIX_IOF_COMPLETE** attribute indicating that forwarding of **stdin** is to be terminated.

PMIX_IOF_COPY "pmix.iof.cpy" (bool)

Requests that the host environment deliver a copy of the specified output stream(s) to the tool, letting the stream(s) continue to also be delivered to the default location. This allows the tool to tap into the output stream(s) without redirecting it from its current final destination.

PMIX_IOF_REDIRECT "pmix.iof.redir" (bool)

Requests that the host environment intercept the specified output stream(s) and deliver it to the requesting tool instead of its current final destination. This might be used, for example, during a debugging procedure to avoid injection of debugger-related output into the application's results file. The original output stream(s) destination is restored upon termination of the tool.

PMIX_DEBUG_TARGET "pmix.dbg.tgt" (pmix_proc_t*)

Identifier of process(es) to be debugged - a rank of **PMIX_RANK_WILDCARD** indicates that all processes in the specified namespace are to be included.

PMIX_DEBUG_DAEMONS_PER_PROC "pmix.dbg.dpproc" (uint16_t)

Number of debugger daemons to be spawned per application process. The launcher is to pass the identifier of the namespace to be debugged by including the PMIX_DEBUG_TARGET attribute in the daemon's job-level information. The debugger daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX_LOCAL_RANK in the daemon debugger job versus the corresponding PMIX_LOCAL_RANK of the target processes on the node.

1 PMIX_DEBUG_DAEMONS_PER_NODE "pmix.dbg.dpnd" (uint16_t) Number of debugger daemons to be spawned on each node where the target job is executing. 2 3 The launcher is to pass the identifier of the namespace to be debugged by including the 4 PMIX DEBUG TARGET attribute in the daemon's job-level information. The debugger 5 daemons spawned on a given node are responsible for self-determining their specific target process(es) - e.g., by referencing their own PMIX LOCAL RANK in the daemon debugger 6 7 job versus the corresponding **PMIX LOCAL RANK** of the target processes on the node. 8 PMIX WAIT FOR CONNECTION "pmix.wait.conn" (bool) Wait until the specified process has connected to the requesting tool or server, or the 9 operation times out (if the **PMIX TIMEOUT** directive is included in the request). 10 Fabric attributes 11 PMIX SERVER SCHEDULER "pmix.srv.sched" (bool) 12 Server is supporting system scheduler and desires access to appropriate WLM-supporting 13 14 features. Indicates that the library is to be initialized for scheduler support. 15 PMIX FABRIC COST MATRIX "pmix.fab.cm" (pointer) 16 Pointer to a two-dimensional square array of point-to-point relative communication costs 17 expressed as uint16 t values. 18 PMIX FABRIC GROUPS "pmix.fab.grps" (string) 19 A string delineating the group membership of nodes in the overall system, where each fabric group consists of the group number followed by a colon and a comma-delimited list of nodes 20 21 in that group, with the groups delimited by semi-colons (e.g., 22 0:node000, node002, node004, node006; 1:node001, node003, node005, node007) 23 PMIX_FABRIC_VENDOR "pmix.fab.vndr" (string) 24 Name of the vendor (e.g., Amazon, Mellanox, HPE, Intel) for the specified fabric. 25 PMIX FABRIC IDENTIFIER "pmix.fab.id" (string) 26 27 An identifier for the specified fabric (e.g., MgmtEthernet, Slingshot-11, OmniPath-1). 28 PMIX FABRIC INDEX "pmix.fab.idx" (size t) 29 The index of the fabric as returned in **pmix fabric t**. 30 PMIX FABRIC NUM DEVICES "pmix.fab.nverts" (size t) 31 Total number of fabric devices in the overall system - corresponds to the number of rows or 32 columns in the cost matrix. 33 PMIX FABRIC COORDINATES "pmix.fab.coords" (pmix data array t) Array of pmix_geometry_t fabric coordinates for devices on the specified node. The 34 array will contain the coordinates of all devices on the node, including values for all 35 supported coordinate views. The information for devices on the local node shall be provided 36 37 if the node is not specified in the request. PMIX FABRIC DIMS "pmix.fab.dims" (uint32 t) 38

4 5

7 8 9

6

12 13 14

10

11

16 17 18

15

27 28 29

31 32 33

30

34 35

36 37 38

39

40

Number of dimensions in the specified fabric plane/view. If no plane is specified in a request, then the dimensions of all planes in the overall system will be returned as a pmix_data_array_t containing an array of uint32_t values. Default is to provide dimensions in *logical* view.

PMIX_FABRIC_ENDPT "pmix.fab.endpt" (pmix_data_array_t)

Fabric endpoints for a specified process. As multiple endpoints may be assigned to a given process (e.g., in the case where multiple devices are associated with a package to which the process is bound), the returned values will be provided in a pmix data array t of pmix endpoint t elements.

PMIX FABRIC SHAPE "pmix.fab.shape" (pmix data array t*)

The size of each dimension in the specified fabric plane/view, returned in a pmix data array t containing an array of uint32 t values. The size is defined as the number of elements present in that dimension - e.g., the number of devices in one dimension of a physical view of a fabric plane. If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix data array t array where each element is itself a two-element array containing the PMIX_FABRIC_PLANE followed by that plane's fabric shape. Default is to provide the shape in *logical* view.

PMIX_FABRIC_SHAPE_STRING "pmix.fab.shapestr" (string)

Network shape expressed as a string (e.g., "10x12x2"). If no plane is specified, then the shape of each plane in the overall system will be returned in a pmix_data_array_t array where each element is itself a two-element array containing the PMIX_FABRIC PLANE followed by that plane's fabric shape string. Default is to provide the shape in *logical* view.

PMIX_SWITCH_PEERS "pmix.speers" (pmix_data_array_t)

Peer ranks that share the same switch as the process specified in the call to PMIx_Get. Returns a pmix_data_array_t array of pmix_info_t results, each element containing the PMIX_SWITCH_PEERS key with a three-element pmix_data_array_t array of pmix info t containing the PMIX_DEVICE_ID of the local fabric device, the PMIX_FABRIC_SWITCH identifying the switch to which it is connected, and a comma-delimited string of peer ranks sharing the switch to which that device is connected.

PMIX FABRIC PLANE "pmix.fab.plane" (string)

ID string of a fabric plane (e.g., CIDR for Ethernet). When used as a modifier in a request for information, specifies the plane whose information is to be returned. When used directly as a key in a request, returns a pmix data array t of string identifiers for all fabric planes in the overall system.

PMIX FABRIC SWITCH "pmix.fab.switch" (string)

ID string of a fabric switch. When used as a modifier in a request for information, specifies the switch whose information is to be returned. When used directly as a key in a request, returns a pmix data array t of string identifiers for all fabric switches in the overall system.

PMIX_FABRIC_DEVICE "pmix.fabdev" (pmix_data_array_t)

1 2 3	An array of pmix_info_t describing a particular fabric device using one or more of the attributes defined below. The first element in the array shall be the PMIX_DEVICE_ID of the device.
4 5	PMIX_FABRIC_DEVICE_INDEX "pmix.fabdev.idx" (uint32_t) Index of the device within an associated communication cost matrix.
6 7 8	<pre>PMIX_FABRIC_DEVICE_NAME "pmix.fabdev.nm" (string) The operating system name associated with the device. This may be a logical fabric interface name (e.g. "eth0" or "eno1") or an absolute filename.</pre>
9 0	PMIX_FABRIC_DEVICE_VENDOR "pmix.fabdev.vndr" (string) Indicates the name of the vendor that distributes the device.
1 2	<pre>PMIX_FABRIC_DEVICE_BUS_TYPE "pmix.fabdev.btyp" (string) The type of bus to which the device is attached (e.g., "PCI", "GEN-Z").</pre>
3 4	<pre>PMIX_FABRIC_DEVICE_VENDORID "pmix.fabdev.vendid" (string) This is a vendor-provided identifier for the device or product.</pre>
5 6	<pre>PMIX_FABRIC_DEVICE_DRIVER "pmix.fabdev.driver" (string) The name of the driver associated with the device.</pre>
7 8	<pre>PMIX_FABRIC_DEVICE_FIRMWARE "pmix.fabdev.fmwr" (string) The device's firmware version.</pre>
9 20 21	<pre>PMIX_FABRIC_DEVICE_ADDRESS "pmix.fabdev.addr" (string) The primary link-level address associated with the device, such as a MAC address. If multiple addresses are available, only one will be reported.</pre>
22 23 24	<pre>PMIX_FABRIC_DEVICE_COORDINATES "pmix.fab.coord" (pmix_geometry_t) The pmix_geometry_t fabric coordinates for the device, including values for all supported coordinate views.</pre>
?5 ?6	PMIX_FABRIC_DEVICE_MTU "pmix.fabdev.mtu" (size_t) The maximum transfer unit of link level frames or packets, in bytes.
?7 ?8	<pre>PMIX_FABRIC_DEVICE_SPEED "pmix.fabdev.speed" (size_t) The active link data rate, given in bits per second.</pre>
9 80 81 82	PMIX_FABRIC_DEVICE_STATE "pmix.fabdev.state" (pmix_link_state_t) The last available physical port state for the specified device. Possible values are PMIX_LINK_STATE_UNKNOWN, PMIX_LINK_DOWN, and PMIX_LINK_UP, to indicate if the port state is unknown or not applicable (unknown), inactive (down), or active (up).
3 34 35	<pre>PMIX_FABRIC_DEVICE_TYPE "pmix.fabdev.type" (string) Specifies the type of fabric interface currently active on the device, such as Ethernet or InfiniBand.</pre>
86	<pre>PMIX_FABRIC_DEVICE_PCI_DEVID "pmix.fabdev.pcidevid" (string)</pre>

1 2 3 4 5 6	A node-level unique identifier for a PCI device. Provided only if the device is located on a PCI bus. The identifier is constructed as a four-part tuple delimited by colons comprised of the PCI 16-bit domain, 8-bit bus, 8-bit device, and 8-bit function IDs, each expressed in zero-extended hexadecimal form. Thus, an example identifier might be "abc1:0f:23:01". The combination of node identifier (PMIX_HOSTNAME or PMIX_NODEID) and PMIX_FABRIC_DEVICE_PCI_DEVID shall be unique within the overall system.
7 8 9 10	Device attributes PMIX_DEVICE_DISTANCES "pmix.dev.dist" (pmix_data_array_t) Return an array of pmix_device_distance_t containing the minimum and maximum distances of the given process location to all devices of the specified type on the local node.
11 12 13	<pre>PMIX_DEVICE_TYPE "pmix.dev.type" (pmix_device_type_t) Bitmask specifying the type(s) of device(s) whose information is being requested. Only used as a directive/qualifier.</pre>
14 15	PMIX_DEVICE_ID "pmix.dev.id" (string) System-wide UUID or node-local OS name of a particular device.
16 17 18 19	Sets-Groups attributes PMIX_QUERY_NUM_PSETS "pmix.qry.psetnum" (size_t) Return the number of process sets defined in the specified range (defaults to PMIX_RANGE_SESSION).
20 21 22	<pre>PMIX_QUERY_PSET_NAMES "pmix.qry.psets" (pmix_data_array_t*) Return a pmix_data_array_t containing an array of strings of the process set names defined in the specified range (defaults to PMIX_RANGE_SESSION).</pre>
23 24	<pre>PMIX_QUERY_PSET_MEMBERSHIP "pmix.qry.pmems" (pmix_data_array_t*) Return an array of pmix_proc_t containing the members of the specified process set.</pre>
25 26	<pre>PMIX_PSET_NAME "pmix.pset.nm" (char*) The name of the newly defined process set.</pre>
27 28	<pre>PMIX_PSET_MEMBERS "pmix.pset.mems" (pmix_data_array_t*) An array of pmix_proc_t containing the members of the newly defined process set.</pre>
29 30 31	<pre>PMIX_PSET_NAMES "pmix.pset.nms" (pmix_data_array_t*) Returns an array of char* string names of the process sets in which the given process is a member.</pre>
32 33 34	<pre>PMIX_QUERY_NUM_GROUPS "pmix.qry.pgrpnum" (size_t) Return the number of process groups defined in the specified range (defaults to session). OPTIONAL QUALIFERS: PMIX_RANGE.</pre>
35 36 37 38	PMIX_QUERY_GROUP_NAMES "pmix.qry.pgrp" (pmix_data_array_t*) Return a pmix_data_array_t containing an array of string names of the process groups defined in the specified range (defaults to session). OPTIONAL QUALIFERS: PMIX_RANGE.

1 2 3 4	<pre>PMIX_QUERY_GROUP_MEMBERSHIP "pmix.qry.pgrpmems" (pmix_data_array_t*) Return a pmix_data_array_t of pmix_proc_t containing the members of the specified process group. REQUIRED QUALIFIERS: PMIX_GROUP_ID.</pre>
5 6 7 8 9	PMIX_GROUP_ID "pmix.grp.id" (char*) User-provided group identifier - as the group identifier may be used in PMIx operations, the user is required to ensure that the provided ID is unique within the scope of the host environment (e.g., by including some user-specific or application-specific prefix or suffix to the string).
10 11	PMIX_GROUP_LEADER "pmix.grp.ldr" (bool) This process is the leader of the group.
12 13 14	<pre>PMIX_GROUP_OPTIONAL "pmix.grp.opt" (bool) Participation is optional - do not return an error if any of the specified processes terminate without having joined. The default is false.</pre>
15 16 17	<pre>PMIX_GROUP_NOTIFY_TERMINATION "pmix.grp.notterm" (bool) Notify remaining members when another member terminates without first leaving the group.</pre>
18 19 20	PMIX_GROUP_FT_COLLECTIVE "pmix.grp.ftcoll" (bool) Adjust internal tracking on-the-fly for terminated processes during a PMIx group collective operation.
21 22 23 24 25	PMIX_GROUP_ASSIGN_CONTEXT_ID "pmix.grp.actxid" (bool) Requests that the RM assign a new context identifier to the newly created group. The identifier is an unsigned, size_t value that the RM guarantees to be unique across the range specified in the request. Thus, the value serves as a means of identifying the group within that range. If no range is specified, then the request defaults to PMIX_RANGE_SESSION.
26 27 28 29 30 31 32 33	PMIX_GROUP_LOCAL_ONLY "pmix.grp.lcl" (bool) Group operation only involves local processes. PMIx implementations are <i>required</i> to automatically scan an array of group members for local vs remote processes - if only local processes are detected, the implementation need not execute a global collective for the operation unless a context ID has been requested from the host environment. This can result in significant time savings. This attribute can be used to optimize the operation by indicating whether or not only local processes are represented, thus allowing the implementation to bypass the scan.
34 35	PMIX_GROUP_CONTEXT_ID "pmix.grp.ctxid" (size_t) Context identifier assigned to the group by the host RM.
36 37 38	<pre>PMIX_GROUP_ENDPT_DATA "pmix.grp.endpt" (pmix_byte_object_t)</pre> Data collected during group construction to ensure communication between group members is supported upon completion of the operation.

1 2 3	<pre>PMIX_GROUP_NAMES "pmix.pgrp.nm" (pmix_data_array_t*) Returns an array of char* string names of the process groups in which the given process is a member.</pre>
4 5 6 7 8	Process Mgmt attributes PMIX_OUTPUT_TO_DIRECTORY "pmix.outdir" (char*) Direct output into files of form " <directory>/<jobid>/rank.<rank>/ stdout[err]" - can be assigned to the entire job (by including attribute in the job_info array) or on a per-application basis in the info array for each pmix_app_t.</rank></jobid></directory>
9 0	PMIX_TIMEOUT_STACKTRACES "pmix.tim.stack" (bool) Include process stacktraces in timeout report from a job.
1 2	PMIX_TIMEOUT_REPORT_STATE "pmix.tim.state" (bool) Report process states in timeout report from a job.
3 4 5 6 7 8 9	PMIX_NOTIFY_JOB_EVENTS "pmix.note.jev" (bool) Requests that the launcher generate the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events. Each event is to include at least the namespace of the corresponding job and a PMIX_EVENT_TIMESTAMP indicating the time the event occurred. Note that the requester must register for these individual events, or capture and process them by registering a default event handler instead of individual handlers and then process the events based on the returned status code. Another common method is to register one event handler for all job-related events, with a separate handler for non-job events - see PMIx_Register_event_handler for details.
22 23 24	PMIX_NOTIFY_PROC_TERMINATION "pmix.noteproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.
25 26 27	PMIX_NOTIFY_PROC_ABNORMAL_TERMINATION "pmix.noteabproc" (bool) Requests that the launcher generate the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.
28 29 30	PMIX_LOG_PROC_TERMINATION "pmix.logproc" (bool) Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event whenever a process either normally or abnormally terminates.
31 32 33	PMIX_LOG_PROC_ABNORMAL_TERMINATION "pmix.logabproc" (bool) Requests that the launcher log the PMIX_EVENT_PROC_TERMINATED event only when a process abnormally terminates.
34 35 36 37	PMIX_LOG_JOB_EVENTS "pmix.log.jev" (bool) Requests that the launcher log the PMIX_EVENT_JOB_START, PMIX_LAUNCH_COMPLETE, and PMIX_EVENT_JOB_END events using PMIx_Log, subject to the logging attributes of Section 12.4.3.
88	PMIX_LOG_COMPLETION "pmix.logcomp" (bool)

1 Requests that the launcher log the PMIX_EVENT_JOB_END event for normal or abnormal 2 termination of the spawned job using **PMIx** Log, subject to the logging attributes of Section 12.4.3. The event shall include the returned status code 3 4 (PMIX JOB TERM STATUS) for the corresponding job; the identity (PMIX PROCID) 5 and exit status (PMIX_EXIT_CODE) of the first failed process, if applicable; and a 6 **PMIX_EVENT_TIMESTAMP** indicating the time the termination occurred. 7 PMIX FIRST ENVAR "pmix.envar.first" (pmix envar t*) 8 Ensure the given value appears first in the specified envar using the separator character, 9 creating the envar if it doesn't already exist **Event attributes** 10 11 PMIX EVENT TIMESTAMP "pmix.evtstamp" (time t) 12 System time when the associated event occurred. C.8.3 Added Environmental Variables 14 Tool environmental variables 15 PMIX LAUNCHER RNDZ URI PMIX_LAUNCHER_RNDZ_FILE 16 17 C.8.4 Added Macros PMIX CHECK RESERVED KEYPMIX INFO WAS PROCESSED PMIX INFO PROCESSED 19 20 PMIX_INFO_LIST_START PMIX_INFO_LIST_ADD PMIX_INFO_LIST_XFER PMIX_INFO_LIST_CONVERT PMIX_INFO_LIST_RELEASE 21 C.8.5 **Deprecated APIs** pmix_evhdlr_reg_cbfunc_t Renamed to pmix_hdlr_reg_cbfunc_t 23 24 The pmix_server_client_connected_fn_t server module entry point has been 25 deprecated in favor of pmix_server_client_connected2_fn_t 26 PMIx tool connect to server Replaced by PMIx tool attach to server to allow return of the process identifier of the server to which the tool has attached. 27

C.8.6 Deprecated constants

```
2
             The following constants were deprecated in v4.0:
                                             Renamed to PMIX DEBUGGER RELEASE
 3
             PMIX ERR DEBUGGER RELEASE
 4
             PMIX_ERR_JOB_TERMINATED
                                           Renamed to PMIX_EVENT_JOB_END
 5
             PMIX EXISTS
                             Renamed to PMIX ERR EXISTS
 6
             PMIX ERR PROC ABORTED
                                         Consolidated with PMIX EVENT PROC TERMINATED
 7
             PMIX ERR PROC ABORTING
                                          Consolidated with PMIX EVENT PROC TERMINATED
8
             PMIX ERR LOST CONNECTION TO SERVER
                                                        Consolidated into
9
                 PMIX ERR LOST CONNECTION
10
             PMIX ERR LOST PEER CONNECTION
                                                  Consolidated into
                 PMIX ERR LOST CONNECTION
11
12
             PMIX ERR LOST CONNECTION TO CLIENT
                                                        Consolidated into
13
                 PMIX_ERR_LOST_CONNECTION
14
             PMIX ERR INVALID TERMINATION
                                                 Renamed to PMIX_ERR_JOB_TERM_WO_SYNC
15
             PMIX PROC TERMINATED
                                        Renamed to PMIX EVENT PROC TERMINATED
             PMIX_ERR_NODE_DOWN
                                     Renamed to PMIX_EVENT_NODE_DOWN
16
17
             PMIX_ERR_NODE_OFFLINE
                                         Renamed to PMIX_EVENT_NODE_OFFLINE
18
             PMIX ERR SYS OTHER
                                     Renamed to PMIX EVENT SYS OTHER
19
             PMIX CONNECT REQUESTED
                                          Connection has been requested by a PMIx-based tool -
20
                 deprecated as not required.
                                           A tool or client has connected to the PMIx server -
21
             PMIX PROC HAS CONNECTED
22
                 deprecated in favor of the new pmix_server_client_connected2_fn_t server
23
                 module API
```

C.8.7 Removed constants

The following constants were removed from the PMIx Standard in v4.0 as they are internal to a particular PMIx implementation.

```
27
              PMIX ERR HANDSHAKE FAILED
                                               Connection handshake failed
              PMIX ERR READY FOR HANDSHAKE
                                                   Ready for handshake
28
              PMIX ERR IN ERRNO
                                      Error defined in errno
29
              PMIX ERR INVALID VAL LENGTH
                                                  Invalid value length
30
31
              PMIX_ERR_INVALID_LENGTH
                                             Invalid argument length
32
              PMIX_ERR_INVALID_NUM_ARGS
                                               Invalid number of arguments
33
              PMIX_ERR_INVALID_ARGS
                                           Invalid arguments
              PMIX ERR INVALID NUM PARSED
                                                  Invalid number parsed
34
              PMIX ERR INVALID KEYVALP
                                              Invalid key/value pair
35
36
              PMIX ERR INVALID SIZE
                                           Invalid size
37
              PMIX_ERR_PROC_REQUESTED_ABORT
                                                    Process is already requested to abort
                                                      Failed to connect to the server
38
              PMIX_ERR_SERVER_FAILED_REQUEST
              PMIX_ERR_PROC_ENTRY_NOT_FOUND
                                                    Process not found
39
```

25

```
1
                                          Invalid argument
              PMIX_ERR_INVALID_ARG
2
              PMIX ERR INVALID KEY
                                          Invalid key
 3
              PMIX_ERR_INVALID_KEY_LENGTH
                                                  Invalid key length
 4
                                          Invalid value
              PMIX_ERR_INVALID_VAL
 5
              PMIX ERR INVALID NAMESPACE
                                                 Invalid namespace
6
              PMIX ERR SERVER NOT AVAIL
                                                Server is not available
 7
              PMIX ERR_SILENT
                                    Silent error
8
              PMIX_ERR_PACK_MISMATCH
                                            Pack mismatch
9
              PMIX_ERR_DATA_VALUE_NOT_FOUND
                                                     Data value not found
10
              PMIX ERR NOT IMPLEMENTED
                                               Not implemented
              PMIX_GDS_ACTION_COMPLETE
                                               The GDS action has completed
11
12
              PMIX NOTIFY ALLOC COMPLETE
                                                 Notify that a requested allocation operation is complete
                  - the result of the request will be included in the info array
13
   C.8.8 Deprecated attributes
              The following attributes were deprecated in v4.0:
15
```

```
PMIX_TOPOLOGY "pmix.topo" (hwloc_topology_t)
16
17
                 Renamed to PMIX TOPOLOGY2.
18
            PMIX_DEBUG_JOB "pmix.dbg.job" (char*)
                 Renamed to PMIX_DEBUG_TARGET)
19
20
            PMIX RECONNECT SERVER "pmix.tool.recon" (bool)
                 Renamed to the PMIx_tool_connect_to_server API
21
            PMIX_ALLOC_NETWORK "pmix.alloc.net" (array)
22
23
                 Renamed to PMIX_ALLOC_FABRIC
24
            PMIX ALLOC NETWORK ID "pmix.alloc.netid" (char*)
25
                 Renamed to PMIX ALLOC FABRIC ID
            PMIX_ALLOC_NETWORK_QOS "pmix.alloc.netqos" (char*)
26
27
                 Renamed to PMIX_ALLOC_FABRIC_QOS
28
            PMIX_ALLOC_NETWORK_TYPE "pmix.alloc.nettype" (char*)
29
                 Renamed to PMIX_ALLOC_FABRIC_TYPE
            PMIX_ALLOC_NETWORK_PLANE "pmix.alloc.netplane" (char*)
30
31
                 Renamed to PMIX ALLOC FABRIC PLANE
            PMIX ALLOC NETWORK ENDPTS "pmix.alloc.endpts" (size t)
32
33
                 Renamed to PMIX ALLOC FABRIC ENDPTS
            PMIX_ALLOC_NETWORK_ENDPTS_NODE "pmix.alloc.endpts.nd" (size_t)
34
                 Renamed to PMIX_ALLOC_FABRIC_ENDPTS_NODE
35
            PMIX ALLOC NETWORK_SEC_KEY "pmix.alloc.nsec" (pmix_byte_object_t)
36
37
                 Renamed to PMIX_ALLOC_FABRIC_SEC_KEY
            PMIX PROC DATA "pmix.pdata" (pmix data array t)
38
39
                 Renamed to PMIX PROC INFO ARRAY
            PMIX LOCALITY "pmix.loc" (pmix locality t)
40
```

1 Relative locality of the specified process to the requester, expressed as a bitmask as per the 2 description in the pmix locality t section. This value is unique to the requesting 3 process and thus cannot be communicated by the server as part of the job-level information. 4 Its use has been replaced by the **PMIx Get relative locality** function. C.8.9Removed attributes The following attributes were removed from the PMIx Standard in v4.0 as they are internal to a 6 particular PMIx implementation. Users are referred to the PMIx Load topology API for 7 8 obtaining the local topology description. PMIX_LOCAL_TOPO "pmix.ltopo" (char*) 9 10 XML representation of local node topology. PMIX TOPOLOGY XML "pmix.topo.xml" (char*) 11 XML-based description of topology 12 PMIX_TOPOLOGY_FILE "pmix.topo.file" (char*) 13 Full path to file containing XML topology description 14 15 PMIX TOPOLOGY SIGNATURE "pmix.toposig" (char*) Topology signature string. 16 PMIX_HWLOC_SHMEM_ADDR "pmix.hwlocaddr" (size_t) 17 Address of the HWLOC shared memory segment. 18 19 PMIX_HWLOC_SHMEM_SIZE "pmix.hwlocsize" (size_t) Size of the HWLOC shared memory segment. 20 PMIX HWLOC SHMEM FILE "pmix.hwlocfile" (char*) 21 22 Path to the HWLOC shared memory file. 23 PMIX HWLOC XML V1 "pmix.hwlocxml1" (char*) XML representation of local topology using HWLOC's v1.x format. 24 PMIX_HWLOC_XML_V2 "pmix.hwlocxml2" (char*) 25 XML representation of local topology using HWLOC's v2.x format. 26 PMIX_HWLOC_SHARE_TOPO "pmix.hwlocsh" (bool) 27 28 Share the HWLOC topology via shared memory PMIX HWLOC HOLE KIND "pmix.hwlocholek" (char*) 29 Kind of VM "hole" HWLOC should use for shared memory 30 PMIX_DSTPATH "pmix.dstpath" (char*) 31 32 Path to shared memory data storage (dstore) files. Deprecated from Standard as being implementation specific. 33 PMIX COLLECTIVE_ALGO "pmix.calgo" (char*) 34 Comma-delimited list of algorithms to use for the collective operation. PMIx does not 35 impose any requirements on a host environment's collective algorithms. Thus, the 36

acceptable values for this attribute will be environment-dependent - users are encouraged to

PMIx Standard – Version 5.0 (Draft) – Created on February 16, 2021

check their host environment for supported values.

PMIX_COLLECTIVE_ALGO_REQD "pmix.calreqd" (bool)

PMIX PROC BLOB "pmix.pblob" (pmix byte object t)

If **true**, indicates that the requested choice of algorithm is mandatory.

37

38

39

40 41

1	Packed blob of process data.
2	<pre>PMIX_MAP_BLOB "pmix.mblob" (pmix_byte_object_t)</pre>
3	Packed blob of process location.
4	<pre>PMIX_MAPPER "pmix.mapper" (char*)</pre>
5	Mapping mechanism to use for placing spawned processes - when accessed using
6	PMIx_Get, use the PMIX_RANK_WILDCARD value for the rank to discover the mapping
7	mechanism used for the provided namespace.
8	PMIX_NON_PMI "pmix.nonpmi" (bool)
9	Spawned processes will not call PMIx_Init.
0	<pre>PMIX_PROC_URI "pmix.puri" (char*)</pre>
1	URI containing contact information for the specified process.
2	PMIX_ARCH "pmix.arch" (uint32_t)
3	Architecture flag.

APPENDIX D

Acknowledgements

1 2 3 4	This document represents the work of many people who have contributed to the PMIx community. Without the hard work and dedication of these people this document would not have been possible. The sections below list some of the active participants and organizations in the various PMIx standard iterations.
5	D.1 Version 4.0
6	The following list includes some of the active participants in the PMIx v4 standardization process.
7	Ralph H. Castain and Danielle Sikich
8	Joshua Hursey and David Solt
9	• Dirk Schubert
10	John DelSignore
11	Aurelien Bouteiller
12	Michael A Raymond
13	Howard Pritchard and Nathan Hjelm
14	Brice Goglin
15	Kathryn Mohror and Stephen Herbein
16	 Thomas Naughton and Swaroop Pophale
17	William E. Allcock and Paul Rich
18	Michael Karo
19	Artem Polyakov
20 21	The following institutions supported this effort through time and travel support for the people listed above.
22	• Intel Corporation

23

24

• IBM, Inc.

• Allinea (ARM)

- 1 Perforce
- University of Tennessee, Knoxville
- The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- HPE Co.
- Los Alamos National Laboratory
- 7 INRIA
- Lawrence Livermore National Laboratory
- Oak Ridge National Laboratory
- Argonne National Laboratory
- 11 Altair
- 12 NVIDIA

13 **D.2 Version 3.0**

- The following list includes some of the active participants in the PMIx v3 standardization process.
- Ralph H. Castain, Andrew Friedley, Brandon Yates
- Joshua Hursey and David Solt
 - Aurelien Bouteiller and George Bosilca
- 18 Dirk Schubert

17

- Kevin Harms
- Artem Polyakov
- The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
 - University of Tennessee, Knoxville
- The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- Argonne National Laboratory

- Allinea (ARM)
- NVIDIA

8

11

14

15

18

20

21 22

23

26 27

D.3 Version 2.0

- 4 The following list includes some of the active participants in the PMIx v2 standardization process.
- Ralph H. Castain, Annapurna Dasari, Christopher A. Holguin, Andrew Friedley, Michael Klemm
 and Terry Wilmarth
 - Joshua Hursey, David Solt, Alexander Eichenberger, Geoff Paulsen, and Sameh Sharkawi
 - Aurelien Bouteiller and George Bosilca
 - Artem Polyakov, Igor Ivanov and Boris Karasev
- Gilles Gouaillardet
 - Michael A Raymond and Jim Stoffel
- Dirk Schubert
- Moe Jette
 - Takahiro Kawashima and Shinji Sumimoto
 - Howard Pritchard
- David Beer
- Brice Goglin
 - Geoffroy Vallee, Swen Boehm, Thomas Naughton and David Bernholdt
- Adam Moody and Martin Schulz
 - Ryan Grant and Stephen Olivier
 - Michael Karo
 - The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
 - University of Tennessee, Knoxville
 - The Exascale Computing Project, an initiative of the US Department of Energy
- National Science Foundation
- Mellanox, Inc.

- Research Organization for Information Science and Technology
 HPE Co.
- Allinea (ARM)
- SchedMD, Inc.
- Fujitsu Limited
- Los Alamos National Laboratory
- Adaptive Solutions, Inc.
- 8 INRIA

16

17 18

20

28

- Oak Ridge National Laboratory
- Lawrence Livermore National Laboratory
- Sandia National Laboratory
- 12 Altair

13 **D.4 Version 1.0**

- The following list includes some of the active participants in the PMIx v1 standardization process.
- Ralph H. Castain, Annapurna Dasari and Christopher A. Holguin
 - Joshua Hursey and David Solt
 - Aurelien Bouteiller and George Bosilca
 - Artem Polyakov, Elena Shipunova, Igor Ivanov, and Joshua Ladd
- Gilles Gouaillardet
 - Gary Brown
- Moe Jette
- The following institutions supported this effort through time and travel support for the people listed above.
- Intel Corporation
- IBM, Inc.
- University of Tennessee, Knoxville
- Mellanox, Inc.
 - Research Organization for Information Science and Technology

- Adaptive Solutions, Inc.
- SchedMD, Inc.



Bibliography

- [1] Ralph H. Castain, David Solt, Joshua Hursey, and Aurelien Bouteiller. PMIx: Process management for exascale environments. In *Proceedings of the 24th European MPI Users' Group Meeting*, EuroMPI '17, pages 14:1–14:10, New York, NY, USA, 2017. ACM.
- [2] Balaji P. et al. PMI: A scalable parallel process-management interface for extreme-scale systems. In *Recent Advances in the Message Passing Interface*, EuroMPI '10, pages 31–41, Berlin, Heidelberg, 2010. Springer.
- [3] Khaled Hamidouche, Jian Lin, Mingzhe Li, Jie Zhang, and D.K.Panda. Supporting hybrid MPI+PGAS programming models through unified communication runtime: An MVAPICH2-X approach. In *4th MVAPICH User's Group*, MUG, 2016.
- [4] Geoffroy R. Vallée. MOC MPI Open MP Coordination library. https://github.com/OMPI-X/MOC, 2018. [Online; accessed 20-Dec-2019].
- [5] Geoffroy R. Vallée and David Bernhold. Improving support of MPI+OpenMP applications. In *Proceedings of the 25th European MPI Users' Group Meeting*, EuroMPI, 2018.

Index

General terms and other items not induced in the other indices.

```
application, 6, 95, 107, 305, 307, 311, 553, 556
attribute, 8
client, <u>7</u>, <u>59</u>
clients, 7
clone, 7
clones, <u>7</u>, 68, 71, 180, 182, 183, 185, 208, 211, 564
data realm, 98, 269, 270
data realms, 98
device, 8
devices, 8
Direct Modex, 257, 321
fabric, 7
fabric device, 8
fabric devices, 8
fabric plane, 8, 165, 170, 200, 203, 204, 274, 324
fabric planes, 8
fabrics, 7
host environment, 7
instant on, 8, 112, 256
job, 6, 7, 95, 100–104, 107, 295–299, 301, 305–307, 309, 311, 322, 324, 325, 507, 526, 553, 554,
          556, 567-569
key, 8
namespace, 6
node, 7, 95, 107, 165, 170, 200, 203, 204, 305, 324
package, 7, 105, 303, 568
peer, 7, 106, 301
peers, 7
process, <u>7</u>, 95, 107, 165, 170, 200, 203, 204, 305, 324
```

```
processing unit, 7
rank, <u>7</u>, <u>311</u>
realm, 98
realms, 98
resource manager, 7
RM, <u>7</u>
scheduler, <u>7</u>, <u>273</u>
session, <u>6</u>, 95, 100, 107, 108, 295, 296, 305, 306, 553, 554, 556, 567
thread, 7
threads, 7
workflow, 7
workflows, <u>7</u>, <u>394</u>
```

Index of APIs

```
PMIx Abort, 24, 159, 160, 346, 348, 462, 477, 551
    PMIxClient.abort (Python), 476
PMIx Alloc directive string, 57, 498, 552
    PMIxClient.alloc directive string (Python), 498
PMIx Allocation request, 96, 197, 197, 203, 485, 554, 556, 559
    PMIxClient.allocation request (Python), 484
PMIx_Allocation_request_nb, 200, 203, 205, 552
PMIx Commit, 68, 70, 71, 113, 115, 115, 116, 321, 322, 349, 353, 478, 524, 525, 551
    PMIxClient.commit (Python), 478
PMIx_Compute_distances, 191, 193, 495, 560
    PMIxClient.compute_distances (Python), 494
PMIx_Compute_distances_nb, 192, 560
PMIx_Connect, 179, 180, 182, 183, 185, 229–231, 435, 436, 482, 551, 553
    PMIxClient.connect (Python), 481
PMIx Connect nb, 181, 181, 551
pmix_connection_cbfunc_t, 375, 375
pmix_credential_cbfunc_t, 281, 392, 393
PMIx_Data_copy, 156, 552
PMIx Data copy payload, 157, 552
PMIx Data pack, 152, 153, 293, 552
PMIx Data print, 156, 552
PMIx Data range string, 56, 497, 552
    PMIxClient.data range string (Python), 497
PMIx Data type string, 56, 498, 552
    PMIxClient.data type string (Python), 497
PMIx Data unpack, 154, 552
PMIx_Deregister_event_handler, <u>144</u>, 490, 541, 552, 559
    PMIxClient.deregister_event_handler (Python), 490
pmix_device_dist_cbfunc_t, 193, 193, 561
PMIx_Device_type_string, 58, 500, 560
    PMIxClient.device_type_string (Python), 500
PMIx_Disconnect, 182, 183–185, 231, 435, 436, 482, 551, 553
    PMIxClient.disconnect (Python), 482
PMIx Disconnect nb, 184, 185, 231, 551
pmix dmodex response fn t, 320, 321
PMIx_Error_string, 55, 495, 551
    PMIxClient.error_string (Python), 495
pmix event notification cbfunc fn t, 143, 149, 149, 547, 550
```

```
PMIx_Fabric_deregister, 277, 278, 492, 560
    PMIxClient.fabric deregister (Python), 492
PMIx Fabric deregister nb, 277, 560
PMIx Fabric register, 266, 273, 275, 491, 560
    PMIxClient.fabric register (Python), 491
PMIx Fabric register nb, 275, 560
PMIx Fabric update, 274, 275, 277, 492, 560
    PMIxClient.fabric update (Python), 492
PMIx Fabric update nb, 276, 560
PMIx_Fence, 4, 67, 68, 69, 71, 112, 180, 183, 228, 237, 241, 257, 291, 321, 348, 350, 463, 479.
         524, 525, 551, 564
    PMIxClient.fence (Python), 478
PMIx Fence nb, 53, 69, 348, 350, 463, 551, 559
PMIx_Finalize, 24, 63, 65, 65, 178, 345, 346, 435, 436, 462, 476, 551
    PMIxClient.finalize (Python), 476
PMIx_generate_ppn, 294, 503, 551, 557
    PMIxServer.generate_ppn (Python), 502
PMIx_generate_regex, 292, 294, 306, 502, 551, 557
    PMIxServer.generate_regex (Python), 502
PMIx_Get, 3, 8, 27, 63, 68, 71, 72, 73, 74, 76–78, 81, 82, 85–87, 90, 95, 96, 98–101, 103–108,
         112, 116, 162, 163, 168, 169, 171–173, 187, 189, 190, 203, 212, 218, 225, 227, 229, 233,
         237, 257, 259, 269, 270, 272, 298, 302, 306, 336, 362, 364, 413, 436, 479, 524, 525, 527,
         530, 535, 551, 553, 558, 564, 565, 572, 581
    PMIxClient.get (Python), 479
PMIx Get attribute name, 57, 500, 560
    PMIxClient.get attribute name (Python), 499
PMIx_Get_attribute_string, 57, 499, 560
    PMIxClient.get attribute string (Python), 499
PMIx_Get_cpuset, 190, 494, 560
    PMIxClient.get_cpuset (Python), 493
PMIx_Get_credential, 280, 282, 393, 486, 554, 559
    PMIxClient.get_credential (Python), 486
PMIx_Get_credential_nb, 281
PMIx_Get_nb, 53, 54, 74, 551
PMIx_Get_relative_locality, 187, 189, 302, 337, 493, 527, 560, 580
    PMIxClient.get_relative_locality (Python), 493
PMIx Get version, 10, 60, 476, 551
    PMIxClient.get version (Python), 476
PMIx Group construct, 228, 229, 234, 236, 237, 240, 487, 560
    PMIxClient.group construct (Python), 487
PMIx Group construct nb, 237, 240, 560
PMIx Group destruct, 231, 240, 241, 243, 253, 489, 560
    PMIxClient.group destruct (Python), 489
```

```
PMIx_Group_destruct_nb, 241, 243, 560
PMIx Group invite, 230, 243, 245, 246, 248, 488, 560
    PMIxClient.group invite (Python), 488
PMIx Group invite nb, 246, 560
PMIx_Group_join, 230, 245, 246, 248, 249, 250–252, 489, 560
    PMIxClient.group_join (Python), 488
PMIx Group join nb, 248, 251, 252, 560
PMIx Group leave, 231, 252, 253–255, 489, 560
    PMIxClient.group leave (Python), 489
PMIx_Group_leave_nb, 254, 560
pmix_hdlr_reg_cbfunc_t, 55, 138, 447, 448, 577
pmix_info_cbfunc_t, 52, 54, 54, 85, 192, 201, 209, 211, 216, 218, 238, 247, 251, 334, 376, 384,
         386, 387, 389, 390, 403, 406
PMIx_Info_directives_string, 56, 497, 552
    PMIxClient.info directives string (Python), 497
PMIx_Init, 7, 59, 60, 63, 82, 87, 105, 344, 417, 429, 430, 437, 475, 525, 531, 536, 544, 552, 558,
         581
    PMIxClient.init (Python), 475
PMIx Initialized, 59, 475, 551
    PMIxClient.initialized (Python), 475
pmix_iof_cbfunc_t, 400, 447, 460
    iofcbfunc (Python), 460
PMIx_IOF_channel_string, 57, 498, 554
    PMIxClient.iof channel string (Python), 498
PMIx IOF deregister, 448, 516, 554, 559
    PMIxTool.iof deregister (Python), 516
PMIx_IOF_pull, 363, 380, 415, 419, 420, 422, 424, 446, 448, 515, 531, 535, 540, 554, 559
    PMIxTool.iof pull (Python), 515
PMIx_IOF_push, 363, 380, 415, 419, 421, 424–426, 428, 449, 451, 516, 554, 559, 570
    PMIxTool.iof_push (Python), 516
PMIx_Job_control, 197, 206, 207, 210–212, 388, 431, 485, 554, 559
    PMIxClient.job_ctrl (Python), 485
PMIx Job control nb, 78, 205, 208, 304, 552
PMIx_Job_state_string, 57, 499, 560
    PMIxClient.job_state_string (Python), 499
PMIx_Link_state_string, 58, 500, 560
    PMIxClient.link state string (Python), 500
PMIx Load topology, 186, 493, 560, 580
    PMIxClient.load topology (Python), 492
PMIx_Log, 174, 219, 222, 225, 417, 434, 484, 554, 576, 577
    PMIxClient.log (Python), 484
PMIx Log nb, 222, 225, 552
PMIx Lookup, 118, 123, 125–127, 479, 480, 551
```

```
PMIxClient.lookup (Python), 480
pmix lookup cbfunc t, 130, 130, 356
PMIx Lookup nb, 125, 130, 551
pmix modex cbfunc t, 52, 348, 351, 351, 352
pmix notification fn t, 138, 143, 143, 461
    evhandler (Python), 460
PMIx Notify event, 145, 374, 491, 530, 533, 541, 545, 546, 552, 559
    PMIxClient.notify event (Python), 491
pmix op cbfunc t, 53, 53, 120, 133, 145, 146, 149, 181, 184, 222, 242, 254, 275, 276, 278, 295,
         315, 316, 318, 319, 326, 332, 333, 335, 343–345, 347, 354, 358, 365, 368, 370, 372, 373,
         382, 398, 401, 450
PMIx_Parse_cpuset_string, 189, 337, 494, 560
    PMIxClient.parse cpuset string (Python), 494
PMIx_Persistence_string, 56, 496, 552
    PMIxClient.persistence_string (Python), 496
PMIx_Proc_state_string, 55, 496, 552
    PMIxClient.proc_state_string (Python), 495
PMIx_Process_monitor, 197, 213, 218, 486, 554, 559
    PMIxClient.monitor (Python), 485
PMIx_Process_monitor_nb, 216, 218, 552
PMIx_Progress, 62, <u>65</u>, 290, 292, 441, 501, 560, 569
    PMIxClient.progress (Python), 501
PMIx Publish, 118, 120–123, 355, 480, 551
    PMIxClient.publish (Python), 479
PMIx Publish nb, 120, 123, 551
PMIx_Put, 27, 67–71, 95, 98, <u>113</u>, 113–116, 178, 237, 246, 321, 322, 349, 353, 478, 524, 525, 551
    PMIxClient.put (Python), 477
PMIx_Query_info, 8, 80, 85, 89, 90, 92, 95, 227, 229, 269, 270, 407, 411, 429, 430, 484, 530, 535,
         537, 539, 565
    PMIxClient.query (Python), 483
PMIx_Query_info_nb, 78, 85, 85, 96, 178, 306, 327, 540, 552, 553
PMIx_Register_attributes, 326, 508, 559, 560
    PMIxServer.register_attributes (Python), 508
PMIx_Register_event_handler, 78, 137, 174, 416, 435, 490, 528, 533, 537, 540, 545, 546, 549, 552,
         559, 576
    PMIxClient.register_event_handler (Python), 490
pmix release cbfunc t, 52, 52
PMIx Resolve nodes, 79, 483, 551
    PMIxClient.resolve nodes (Python), 483
PMIx_Resolve_peers, 79, 106, 301, 483, 526, 551
    PMIxClient.resolve peers (Python), 482
PMIx Scope string, 56, 496, 552
    PMIxClient.scope string (Python), 496
```

```
pmix_server_abort_fn_t, 346, 463
    clientaborted (Python), 462
pmix server alloc fn t, 383, 470
    allocate (Python), 470
pmix_server_client_connected2_fn_t, 53, 279, 318, 342, 343, 343-345, 462, 560, 577, 578
    clientconnected2 (Python), 461
pmix_server_client_finalized_fn_t, 345, 346, 462
    clientfinalized (Python), 462
PMIx server collect inventory, 334, 336, 510, 554
    PMIxServer.collect_inventory (Python), 509
pmix_server_connect_fn_t, 178, 365, 367, 369, 466
    connect (Python), 466
PMIx server define process set, 227, 339, 511, 560
    PMIxServer.define_process_set (Python), 510
PMIx_server_delete_process_set, 227, 340, 511, 560
    PMIxServer.delete_process_set (Python), 511
PMIx_server_deliver_inventory, 335, 510, 554
    PMIxServer.deliver inventory (Python), 510
PMIx_server_deregister_client, 319, 506, 551
    PMIxServer.deregister client (Python), 506
pmix_server_deregister_events_fn_t, 371, 468
    deregister events (Python), 468
PMIx server deregister nspace, 315, 319, 505, 551
    PMIxServer.deregister nspace (Python), 504
PMIx server deregister resources, 316, 505, 512, 561
    PMIxServer.deregister resources (Python), 505, 512
pmix_server_disconnect_fn_t, 367, 369, 467
    disconnect (Python), 467
pmix_server_dmodex_req_fn_t, 107, 116, 117, 351, 351, 464, 554, 556
    dmodex (Python), 464
PMIx_server_dmodex_request, 320, 321, 322, 507, 551
    PMIxServer.dmodex_request (Python), 507
pmix_server_fabric_fn_t, 266, 273, 405, 475, 560
    fabric (Python), 474
pmix_server_fencenb_fn_t, 348, 350, 351, 463, 556
    fence (Python), 463
PMIx server finalize, 291, 502, 551
    PMIxServer.finalize (Python), 501
PMIx server generate cpuset string, 190, 337, 504, 561
    PMIxServer.generate_cpuset_string (Python), 503
PMIx server generate locality string, 186, 187, 336, 503, 560
    PMIxServer.generate locality string (Python), 503
pmix server get cred fn t, 392, 396, 472
```

```
get_credential (Python), 471
pmix server grp fn t, 402, 474, 560
    group (Python), 474
PMIx server init, 59, 287, 291, 327, 341, 408, 409, 413, 501, 541, 551, 560
    PMIxServer.init (Python), 501
PMIx_server_IOF_deliver, <u>333</u>, 423, 509, 554
    PMIxServer.iof deliver (Python), 509
pmix server iof fn t, 397, 473
    iof pull (Python), 473
pmix_server_job_control_fn_t, <u>386</u>, 471
    job_control (Python), 470
pmix_server_listener_fn_t, 374
pmix_server_log_fn_t, 381, 470
    log (Python), 469
pmix_server_lookup_fn_t, 355, 465
    lookup (Python), 465
pmix_server_module_t, 288, 290, 327, 328, 341, 341, 342, 501
pmix_server_monitor_fn_t, 389, 471
    monitor (Python), 471
pmix_server_notify_event_fn_t, 144, 148, 373, 374, 468
    notify_event (Python), 468
pmix server publish fn t, 353, 464
    publish (Python), 464
pmix server query fn t, 376, 469
    query (Python), 468
PMIx server register client, 279, 317, 318, 344, 346, 506, 551
    PMIxServer.register_client (Python), 506
pmix server register events fn t, 369, 467
    register_events (Python), 467
PMIx_server_register_nspace, 10, 53, 293, 294, 295, 296, 305, 306, 309, 316, 333, 337, 504, 551,
         553, 567
    PMIxServer.register_nspace (Python), 504
PMIx_server_register_resources, 297, 300, 301, 315, 505, 512, 561
    PMIxServer.register_resources (Python), 505, 511
PMIx_server_setup_application, 322, 325, 326, 332, 333, 336, 508, 552, 556
    PMIxServer.setup_application (Python), 507
PMIx server setup fork, 319, 507, 551
    PMIxServer.setup fork (Python), 506
PMIx server setup local support, 331, 509, 552
    PMIxServer.setup_local_support (Python), 508
pmix_server_spawn_fn_t, 177, 360, 418, 466
    spawn (Python), 466
pmix server stdin fn t, 401, 473
```

```
iof_push (Python), 473
pmix server tool connection fn t, 279, 378, 408, 469
    tool connected (Python), 469
pmix server unpublish fn t, 358, 465
    unpublish (Python), 465
pmix server validate cred fn t, 394, 472
    validate credential (Python), 472
pmix setup application cbfunc t, 323, 325
PMIx Spawn, 102, 104, 105, 160, 160, 166, 171, 175, 200, 203, 302, 304, 320, 360, 361, 363, 365,
         385, 413, 414, 418, 419, 421, 422, 428–433, 436, 437, 466, 481, 528, 530, 532, 533, 536,
         539, 542, 551, 557, 568
    PMIxClient.spawn (Python), 481
pmix spawn cbfunc t, 166, 177, 177, 360, 421
PMIx_Spawn_nb, 166, 175, 177, 178, 551
PMIx_Store_internal, 113, 114, 114, 477, 551
    PMIxClient.store_internal (Python), 477
PMIx_tool_attach_to_server, 410, 413, 441, 443, 514, 535, 561, 577
    PMIxTool.attach to server (Python), 514
PMIx tool connect to server, 554, 579
pmix tool connection cbfunc t, 379, 380, 381
PMIx_tool_disconnect, <u>442</u>, 513, 561
    PMIxTool.disconnect (Python), 513
PMIx tool finalize, 441, 513, 552
    PMIxTool.finalize (Python), 513
PMIx tool get servers, 445, 514, 561
    PMIxTool.get servers (Python), 514
PMIx_tool_init, 59, 407, 410, 412–414, 423, 438, 441, 513, 528, 533, 537, 552
    PMIxTool.init (Python), 512
PMIx_tool_set_server, 409, 444, 445, 515, 561
    PMIxTool.set_server (Python), 514
PMIx_Unpublish, 131, 133, 134, 481, 551
    PMIxClient.unpublish (Python), 480
PMIx_Unpublish_nb, 133, 551
PMIx_Validate_credential, 283, 487, 554, 559
    PMIxClient.validate_credential (Python), 486
PMIx Validate credential nb, 284
pmix validation cbfunc t, 285, 395, 396
pmix value cbfunc t, 53, 53
pmix evhdlr reg cbfunc t
    (Deprecated), 577
pmix server client connected fn t
    (Deprecated), 342, 577
PMIx tool connect to server
```



Index of Support Macros

```
PMIX APP CONSTRUCT, 176
PMIX APP CREATE, 176
PMIX APP DESTRUCT, 176
PMIX APP FREE, 177
PMIX APP INFO CREATE, 177, 554, 556
PMIX APP RELEASE, 176
PMIX ARGV APPEND, 46
PMIX ARGV APPEND UNIQUE, 47
PMIX ARGV COPY, 49
PMIX_ARGV_COUNT, 49
PMIX_ARGV_FREE, 48
PMIX_ARGV_JOIN, 49
PMIX_ARGV_PREPEND, 47
PMIX_ARGV_SPLIT, 48
PMIX_BYTE_OBJECT_CONSTRUCT, 43
PMIX_BYTE_OBJECT_CREATE, 43
PMIX BYTE OBJECT DESTRUCT, 43
PMIX_BYTE_OBJECT_FREE, 44
PMIX BYTE OBJECT LOAD, 44
PMIX CHECK KEY, 16
PMIX CHECK NSPACE, 18
PMIX CHECK PROCID, 22
PMIX CHECK RANK, 19
PMIX CHECK RESERVED KEY, 17, 577
PMIX COORD CONSTRUCT, 262
PMIX COORD CREATE, 262
PMIX_COORD_DESTRUCT, 262
PMIX_COORD_FREE, 262
PMIX_CPUSET_CONSTRUCT, 338
PMIX CPUSET CREATE, 338
PMIX_CPUSET_DESTRUCT, 338
PMIX_CPUSET_FREE, 339
PMIX_DATA_ARRAY_CONSTRUCT, 45
PMIX DATA ARRAY CREATE, 45
PMIX DATA ARRAY DESTRUCT, 45
PMIX DATA ARRAY FREE, 46
PMIX DATA BUFFER CONSTRUCT, 151, 153, 155
PMIX DATA BUFFER CREATE, 151, 153, 155
```

```
PMIX_DATA_BUFFER_DESTRUCT, 151
PMIX DATA BUFFER LOAD, 152
PMIX DATA BUFFER RELEASE, 151
PMIX DATA BUFFER UNLOAD, 152, 293
PMIX DEVICE DIST CONSTRUCT, 195
PMIX_DEVICE_DIST_CREATE, 195
PMIX DEVICE DIST DESTRUCT, 195
PMIX DEVICE DIST FREE, 196
PMIX ENDPOINT CONSTRUCT, 260
PMIX_ENDPOINT_CREATE, 260
PMIX_ENDPOINT_DESTRUCT, 260
PMIX_ENDPOINT_FREE, 261
PMIX ENVAR CONSTRUCT, 41
PMIX_ENVAR_CREATE, 42
PMIX_ENVAR_DESTRUCT, 13, 41
PMIX_ENVAR_FREE, 42
PMIX_ENVAR_LOAD, 42
PMIX FABRIC CONSTRUCT, 269
PMIX GEOMETRY CONSTRUCT, 263
PMIX GEOMETRY CREATE, 264
PMIX GEOMETRY DESTRUCT, 264
PMIX GEOMETRY FREE, 264
PMIx Heartbeat, 218, 552
PMIX INFO CONSTRUCT, 32
PMIX INFO CREATE, 33, 38, 40
PMIX INFO DESTRUCT, 33
PMIX_INFO_FREE, 33
PMIX INFO_IS_END, 40, 554, 556
PMIX_INFO_IS_OPTIONAL, 39
PMIX INFO IS REQUIRED, 38, 39
PMIX_INFO_LIST_ADD, 35, 577
PMIX_INFO_LIST_CONVERT, 37, 577
PMIX INFO LIST RELEASE, 37, 577
PMIX_INFO_LIST_START, 35, 36, 37, 577
PMIX_INFO_LIST_XFER, 36, 577
PMIX_INFO_LOAD, 33
PMIX INFO OPTIONAL, 39
PMIX INFO PROCESSED, 40, 577
PMIX INFO REQUIRED, 37, 39
PMIX_INFO_TRUE, 35
PMIX INFO WAS PROCESSED, 40, 577
PMIX INFO XFER, 34, 306
PMIX LOAD KEY, 17
```

```
PMIX_LOAD_NSPACE, 18
PMIX LOAD PROCID, 22, 22
PMIX MULTICLUSTER NSPACE CONSTRUCT, 23
PMIX MULTICLUSTER NSPACE PARSE, 23
PMIX PDATA CONSTRUCT, 127
PMIX_PDATA_CREATE, 128
PMIX PDATA DESTRUCT, 127
PMIX PDATA FREE, 128
PMIX PDATA LOAD, 128
PMIX_PDATA_RELEASE, 128
PMIX_PDATA_XFER, 129
PMIX_PROC_CONSTRUCT, 20
PMIX PROC CREATE, 21
PMIX_PROC_DESTRUCT, 20
PMIX_PROC_FREE, 21, 79
PMIX_PROC_INFO_CONSTRUCT, 25
PMIX_PROC_INFO_CREATE, 26
PMIX PROC INFO DESTRUCT, 25
PMIX PROC INFO FREE, 26
PMIX PROC INFO RELEASE, 26
PMIX PROC LOAD, 21
PMIX PROC RELEASE, 21
PMIX QUERY CONSTRUCT, 93
PMIX QUERY CREATE, 94
PMIX QUERY DESTRUCT, 93
PMIX QUERY FREE, 94
PMIX_QUERY_QUALIFIERS_CREATE, 94, 554, 556
PMIX OUERY RELEASE, 94
PMIX_REGATTR_CONSTRUCT, 329
PMIX REGATTR CREATE, 330
PMIX_REGATTR_DESTRUCT, 330
PMIX_REGATTR_FREE, 330
PMIX_REGATTR_LOAD, 331
PMIX_REGATTR_XFER, 331
PMIX_SETENV, 50
PMIX SYSTEM EVENT, 141
PMIX TOPOLOGY CONSTRUCT, 188
PMIX TOPOLOGY CREATE, 188
PMIX TOPOLOGY DESTRUCT, 188
PMIX_TOPOLOGY_FREE, 188
PMIX VALUE CONSTRUCT, 29
PMIX VALUE CREATE, 29
PMIX VALUE DESTRUCT, 29, 73, 77, 564
```

PMIX_VALUE_FREE, 30 PMIX_VALUE_GET_NUMBER, 32 PMIX_VALUE_LOAD, 30 PMIX_VALUE_RELEASE, 29 PMIX_VALUE_UNLOAD, 31 PMIX_VALUE_XFER, 31

Index of Data Structures

```
pmix alloc directive t, 52, 57, 198, 201, 205, 205, 384, 456, 498
pmix app t, 46, 47, 50, 161–163, 166–168, 172, 173, 175, 175–177, 360, 361, 363, 414, 417, 419,
         429, 432, 437, 457, 531, 532, 536, 539, 554, 556, 576
pmix bind envelope t, 190, 190, 458, 561
pmix byte object t, 43, 43, 44, 51, 280, 281, 283, 285, 333, 394, 395, 401, 449, 455
pmix coord t, 52, 261, 261–263, 458, 561
pmix coord view t, 265, 458, 561
pmix cpuset t, 52, 191, 192, 336, 337, 338, 338, 339, 457, 561
pmix data array t, 27, 37, 44, 44–46, 51, 83, 84, 88, 90, 91, 96, 106, 199, 202, 204, 229, 232, 267,
         268, 270–272, 274, 296, 297, 299–301, 309, 311, 312, 323, 377, 386, 406, 430, 438, 456,
         532, 536, 539, 554, 556, 572, 574, 575
pmix_data_buffer_t, 150, 150–154, 158
pmix_data_range_t, 51, 56, 122, 122, 146, 373, 455, 497
pmix_data_type_t, 30, 32, 34, 36, 45, 50, 50, 51, 56, 129, 153, 155–157, 331, 454, 497
pmix device distance t, 52, 191, 193, 194, 194–196, 303, 458, 561, 574
pmix_device_type_t, 52, 58, 193, 193, 194, 272, 458, 500, 561
pmix endpoint t, 52, 259, 259–261, 272, 457, 572
pmix_envar_t, 13, 41, 41, 42, 52, 456, 542
pmix fabric operation t, 266, 266, 405
pmix fabric t, 259, 266, 266, 269, 270, 273–278, 406, 457, 561, 571
pmix geometry t, 52, 258, 263, 263, 264, 271, 458, 561, 571, 573
pmix_group_operation_t, 403, 405, 405, 561
pmix group opt t, 249, 251, 252, 252, 488, 561
pmix info directives t, 37, 37, 38, 51, 56, 456, 497
pmix info t, 4, 5, 8, 16, 17, 32, 32–40, 51, 54, 60, 63, 65, 80, 84, 90, 92–94, 96, 119, 121–124,
         143, 146, 149, 177, 191, 192, 198, 199, 201, 202, 204–206, 208, 211, 213, 214, 218, 221,
         224, 226, 234, 236, 238, 240, 242, 244, 247, 249, 251, 253, 254, 266, 268, 271, 272, 280,
         281, 283, 285, 288, 290, 295–297, 299, 300, 305, 306, 309, 311, 312, 323, 329, 331,
         333–335, 340, 343, 363, 373, 379, 380, 383, 385, 386, 389, 390, 397, 398, 400, 406, 414,
         417, 419, 429, 437, 439, 443, 445, 446, 448, 449, 456, 459, 531, 532, 536, 539, 552, 554,
         556, 565–568, 572, 573
pmix_iof_channel_t, 52, 57, 333, 398, 400, 426, 426, 446, 456, 498
pmix_job_state_t, 27, 27, 52, 57, 457, 499, 561
pmix key t, 8, 16, 16, 72, 113, 331, 454
pmix link state t, 52, 58, 259, 265, 265, 268, 272, 457, 500, 561, 573
pmix_locality_t, 52, 187, 189, 189, 457, 561, 579, 580
pmix_nspace_t, 17, 17, 18, 22, 23, 177, 454, 455
pmix pdata t, 123, 124, 127, 127–130, 456
```

```
pmix_persistence_t, 51, 56, <u>122</u>, 122, 455, 496
pmix_proc_info_t, <u>24</u>, 24–26, 51, 82, 83, 87, 88, 90, 91, 377, 430, 438, 455, 532, 536, 539
pmix_proc_state_t, <u>23</u>, 23, 51, 55, 455, 495
pmix_proc_t, 19, <u>20</u>, 20–22, 51, 63, 67, 69, 70, 74, 91, 106, 129, 139, 140, 142, 143, 146, 147, 153, 154, 159, 160, 229, 232–234, 238, 244, 247, 250, 301, 317, 319, 320, 331, 333, 339, 343–345, 347, 348, 352, 354, 356, 358, 360, 365, 368, 373, 376, 381, 382, 384, 387, 390, 392, 395, 398, 400, 401, 403–405, 439, 441–443, 445, 455, 574, 575
pmix_query_t, 52, 82, 87, 90, <u>92</u>, 92–95, 376, 378, 457, 554, 556, 565
pmix_rank_t, <u>19</u>, 19, 20, 22, 51, 455
pmix_regattr_t, 52, 96, 327, <u>328</u>, 328–331, 457, 559, 561, 567
pmix_scope_t, 51, 56, <u>114</u>, 114, 455, 496
pmix_status_t, <u>14</u>, 14, 31, 32, 36, 37, 46, 47, 50, 51, 54, 55, 138, 141, 143, 146, 149, 193, 322, 326, 370, 372, 373, 381, 394, 397, 454, 468, 495
pmix_topology_t, 52, 186, <u>187</u>, 187, 188, 191, 192, 561
pmix_value_t, 8, <u>27</u>, 27–32, 51, 54, 73, 74, 77, 113, 456, 564
```

Index of Constants

```
PMIX ALLOC DIRECTIVE, 52
PMIX ALLOC EXTEND, 205
PMIX ALLOC EXTERNAL, 205
PMIX ALLOC NEW, 205
PMIX ALLOC REAQUIRE, 205
PMIX_ALLOC_RELEASE, 205
PMIX APP, 51
PMIX APP WILDCARD, 13
PMIX BOOL, 51
PMIX BUFFER, 51
PMIX_BYTE, 51
PMIX_BYTE_OBJECT, 51
PMIX_COMMAND, 51
PMIX_COMPRESSED_BYTE_OBJECT, 52
PMIX_COMPRESSED_STRING, 52
PMIX_COORD, 52
PMIX COORD LOGICAL VIEW, 265
PMIX_COORD_PHYSICAL_VIEW, 265
PMIX COORD VIEW UNDEF, 265
PMIX CPUBIND PROCESS, 190
PMIX CPUBIND THREAD, 190
PMIX DATA ARRAY, 51
PMIX DATA RANGE, 51
PMIX DATA TYPE, 51
PMIX DATA TYPE MAX, 52
PMIX DEBUG WAITING FOR NOTIFY, 436
PMIX_DEBUGGER_RELEASE, 436
PMIX_DEVICE_DIST, 52
PMIX DEVTYPE, 52
PMIX DEVTYPE BLOCK, 194
PMIX_DEVTYPE_COPROC, 194
PMIX_DEVTYPE_DMA, 194
PMIX_DEVTYPE_GPU, 194
PMIX DEVTYPE NETWORK, 194
PMIX DEVTYPE OPENFABRICS, 194
PMIX DEVTYPE UNKNOWN, 194
PMIX DOUBLE, 51
PMIX ENDPOINT, 52
```

```
PMIX_ENVAR, 52
PMIX_ERR_BAD_PARAM, 15
PMIX ERR COMM FAILURE, 15
PMIX ERR CONFLICTING CLEANUP DIRECTIVES, 211
PMIX ERR DUPLICATE KEY, 121
PMIX_ERR_EVENT_REGISTRATION, 140
PMIX ERR EXISTS, 14
PMIX ERR EXISTS OUTSIDE SCOPE, 14
PMIX ERR INIT, 15
PMIX_ERR_INVALID_CRED, 14
PMIX_ERR_INVALID_OPERATION, 15
PMIX_ERR_IOF_COMPLETE, 427
PMIX ERR IOF FAILURE, 427
PMIX_ERR_JOB_ABORTED, 435
PMIX_ERR_JOB_ABORTED_BY_SIG, 435
PMIX_ERR_JOB_ABORTED_BY_SYS_EVENT, 436
PMIX_ERR_JOB_ALLOC_FAILED, 171
PMIX_ERR_JOB_APP_NOT_EXECUTABLE, 171
PMIX ERR JOB CANCELED, 435
PMIX ERR JOB FAILED TO LAUNCH, 171
PMIX_ERR_JOB_FAILED_TO_MAP, 171
PMIX ERR JOB KILLED BY CMD, 435
PMIX ERR JOB NO EXE SPECIFIED, 171
PMIX ERR JOB NON ZERO TERM, 436
PMIX_ERR_JOB_SENSOR_BOUND_EXCEEDED, 436
PMIX ERR JOB TERM WO SYNC, 436
PMIX_ERR_LOST_CONNECTION, 15
PMIX ERR NO PERMISSIONS, 14
PMIX_ERR_NOMEM, 15
PMIX ERR NOT FOUND, 15
PMIX_ERR_NOT_SUPPORTED, 15
PMIX_ERR_OUT_OF_RESOURCE, 15
PMIX ERR PACK FAILURE, 14
PMIX_ERR_PARAM_VALUE_NOT_SUPPORTED, 15
PMIX_ERR_PARTIAL_SUCCESS, 15
PMIX_ERR_PROC_CHECKPOINT, 212
PMIX_ERR_PROC_MIGRATE, 212
PMIX_ERR_PROC_RESTART, 212
PMIX ERR PROC TERM WO SYNC, 435
PMIX_ERR_REPEAT_ATTR_REGISTRATION, 328
PMIX ERR RESOURCE BUSY, 15
PMIX ERR TIMEOUT, 14
PMIX ERR TYPE MISMATCH, 14
```

```
PMIX_ERR_UNKNOWN_DATA_TYPE, 14
PMIX ERR UNPACK FAILURE, 14
PMIX ERR UNPACK INADEQUATE SPACE, 14
PMIX ERR UNPACK READ PAST END OF BUFFER, 14
PMIX ERR UNREACH, 15
PMIX_ERR_WOULD_BLOCK, 14
PMIX ERROR, 14
PMIX EVENT ACTION COMPLETE, 149
PMIX EVENT ACTION DEFERRED, 149
PMIX_EVENT_JOB_END, 435
PMIX_EVENT_JOB_START, 435
PMIX_EVENT_NO_ACTION_TAKEN, 149
PMIX EVENT NODE DOWN, 141
PMIX_EVENT_NODE_OFFLINE, 141
PMIX_EVENT_PARTIAL_ACTION_TAKEN, 149
PMIX_EVENT_PROC_TERMINATED, 435
PMIX_EVENT_SESSION_END, 435
PMIX EVENT SESSION START, 435
PMIX_EVENT_SYS_BASE, 141
PMIX EVENT SYS OTHER, 141
PMIX EXTERNAL ERR BASE, 15
PMIX FABRIC REQUEST INFO, 266
PMIX FABRIC UPDATE ENDPOINTS, 259
PMIX FABRIC UPDATE INFO, 266
PMIX FABRIC UPDATE PENDING, 259
PMIX FABRIC UPDATED, 259
PMIX_FLOAT, 51
PMIX FWD ALL CHANNELS, 426
PMIX_FWD_NO_CHANNELS, 426
PMIX FWD STDDIAG CHANNEL, 426
PMIX_FWD_STDERR_CHANNEL, 426
PMIX_FWD_STDIN_CHANNEL, 426
PMIX FWD STDOUT CHANNEL, 426
PMIX_GEOMETRY, 52
PMIX GLOBAL, 114
PMIX_GROUP_ACCEPT, 252
PMIX GROUP CONSTRUCT, 405
PMIX GROUP CONSTRUCT ABORT, 232
PMIX GROUP CONSTRUCT COMPLETE, 232
PMIX_GROUP_CONTEXT_ID_ASSIGNED, 232
PMIX GROUP DECLINE, 252
PMIX GROUP DESTRUCT, 405
PMIX GROUP INVITE ACCEPTED, 232
```

```
PMIX_GROUP_INVITE_DECLINED, 232
PMIX GROUP INVITE FAILED, 232
PMIX GROUP INVITED, 231
PMIX GROUP LEADER FAILED, 232
PMIX GROUP LEADER SELECTED, 232
PMIX_GROUP_LEFT, 231
PMIX GROUP MEMBER FAILED, 231
PMIX GROUP MEMBERSHIP UPDATE, 232
PMIX INFO, 51
PMIX_INFO_ARRAY_END, 38
PMIX_INFO_DIR_RESERVED, 38
PMIX_INFO_DIRECTIVES, 51
PMIX INFO REOD, 38
PMIX_INFO_REQD_PROCESSED, 38
PMIX_INT, 51
PMIX_INT16, 51
PMIX_INT32, 51
PMIX INT64, 51
PMIX INT8, 51
PMIX INTERNAL, 114
PMIX IOF CHANNEL, 52
PMIX JCTRL CHECKPOINT, 212
PMIX JCTRL CHECKPOINT COMPLETE, 212
PMIX JCTRL PREEMPT ALERT, 212
PMIX JOB STATE, 52
PMIX JOB STATE AWAITING ALLOC, 27
PMIX_JOB_STATE_CONNECTED, 27
PMIX JOB STATE LAUNCH UNDERWAY, 27
PMIX_JOB_STATE_RUNNING, 27
PMIX JOB STATE SUSPENDED, 27
PMIX_JOB_STATE_TERMINATED, 27
PMIX_JOB_STATE_TERMINATED_WITH_ERROR, 27
PMIX_JOB_STATE_UNDEF, 27
PMIX_JOB_STATE_UNTERMINATED, 27
PMIX KVAL, 51
PMIX_LAUNCH_COMPLETE, 435
PMIX LAUNCHER READY, 422
PMIX LINK DOWN, 265
PMIX LINK STATE, 52
PMIX LINK STATE UNKNOWN, 265
PMIX LINK UP, 265
PMIX LOCAL, 114
PMIX LOCALITY NONLOCAL, 189
```

```
PMIX_LOCALITY_SHARE_CORE, 189
PMIX LOCALITY SHARE HWTHREAD, 189
PMIX LOCALITY SHARE L1CACHE, 189
PMIX LOCALITY SHARE L2CACHE, 189
PMIX LOCALITY SHARE L3CACHE, 189
PMIX_LOCALITY_SHARE_NODE, 189
PMIX LOCALITY SHARE NUMA, 189
PMIX LOCALITY SHARE PACKAGE, 189
PMIX LOCALITY UNKNOWN, 189
PMIX_LOCTYPE, 52
PMIX_MAX_KEYLEN, 13
PMIX_MAX_NSLEN, 13
PMIX MODEL DECLARED, 63
PMIX_MODEL_RESOURCES, 63
PMIX_MONITOR_FILE_ALERT, 218
PMIX_MONITOR_HEARTBEAT_ALERT, 218
PMIX_OPENMP_PARALLEL_ENTERED, 63
PMIX OPENMP PARALLEL EXITED, 63
PMIX OPERATION IN PROGRESS, 15
PMIX OPERATION SUCCEEDED, 15
PMIX PDATA, 51
PMIX PERSIST, 51
PMIX PERSIST APP, 122
PMIX PERSIST FIRST READ, 122
PMIX PERSIST INDEF, 122
PMIX PERSIST INVALID, 122
PMIX_PERSIST_PROC, 122
PMIX_PERSIST_SESSION, 122
PMIX_PID, 51
PMIX POINTER, 51
PMIX_PROC, 51
PMIX_PROC_CPUSET, 52
PMIX PROC INFO, 51
PMIX_PROC_RANK, 51
PMIX_PROC_STATE, 51
PMIX_PROC_STATE_ABORTED, 24
PMIX PROC STATE ABORTED BY SIG, 24
PMIX PROC STATE CALLED ABORT, 24
PMIX PROC STATE CANNOT RESTART, 24
PMIX_PROC_STATE_COMM_FAILED, 24
PMIX PROC STATE CONNECTED, 24
PMIX PROC STATE ERROR, 24
PMIX PROC STATE FAILED TO LAUNCH, 24
```

```
PMIX_PROC_STATE_FAILED_TO_START, 24
PMIX PROC STATE HEARTBEAT FAILED, 24
PMIX PROC STATE KILLED BY CMD, 24
PMIX PROC STATE LAUNCH UNDERWAY, 24
PMIX PROC STATE MIGRATING, 24
PMIX_PROC_STATE_PREPPED, 24
PMIX PROC STATE RESTART, 24
PMIX PROC STATE RUNNING, 24
PMIX PROC STATE SENSOR BOUND EXCEEDED, 24
PMIX_PROC_STATE_TERM_NON_ZERO, 24
PMIX_PROC_STATE_TERM_WO_SYNC, 24
PMIX_PROC_STATE_TERMINATE, 24
PMIX PROC STATE TERMINATED, 24
PMIX_PROC_STATE_UNDEF, 24
PMIX_PROC_STATE_UNTERMINATED, 24
PMIX_PROCESS_SET_DEFINE, 228
PMIX_PROCESS_SET_DELETE, 228
PMIX OUERY, 52
PMIX_QUERY_PARTIAL_SUCCESS, 89
PMIX RANGE CUSTOM, 122
PMIX RANGE GLOBAL, 122
PMIX RANGE INVALID, 122
PMIX RANGE LOCAL, 122
PMIX RANGE NAMESPACE, 122
PMIX RANGE PROC LOCAL, 122
PMIX RANGE RM, 122
PMIX_RANGE_SESSION, 122
PMIX RANGE UNDEF, 122
PMIX_RANK_INVALID, 19
PMIX RANK LOCAL NODE, 19
PMIX_RANK_LOCAL_PEERS, 19
PMIX_RANK_UNDEF, 19
PMIX_RANK_VALID, 19
PMIX_RANK_WILDCARD, 19
PMIX REGATTR, 52
PMIX REGEX, 52
PMIX REMOTE, 114
PMIX SCOPE, 51
PMIX SCOPE UNDEF, 114
PMIX SIZE, 51
PMIX STATUS, 51
PMIX STRING, 51
PMIX SUCCESS, 14
```

```
PMIX_TIME, 51
PMIX TIMEVAL, 51
PMIX TOPO, 52
PMIX UINT, 51
PMIX UINT16, 51
PMIX_UINT32, <u>51</u>
PMIX UINT64, 51
PMIX_UINT8, 51
PMIX UNDEF, 51
PMIX_VALUE, 51
PMIX CONNECT REQUESTED
   Deprecated, 578
PMIX ERR DATA VALUE NOT FOUND
   Deprecated, 557
   Removed, 579
PMIX_ERR_DEBUGGER_RELEASE
   Deprecated, 578
PMIX_ERR_HANDSHAKE_FAILED
   Deprecated, 557
   Removed, 578
PMIX_ERR_IN_ERRNO
   Deprecated, 557
   Removed, 578
PMIX_ERR_INVALID_ARG
   Deprecated, 557
   Removed, 579
PMIX ERR INVALID ARGS
   Deprecated, 557
   Removed, 578
PMIX_ERR_INVALID_KEY
   Deprecated, 557
   Removed, 579
PMIX_ERR_INVALID_KEY_LENGTH
   Deprecated, 557
    Removed, 579
PMIX_ERR_INVALID_KEYVALP
    Deprecated, 557
   Removed, 578
PMIX_ERR_INVALID_LENGTH
   Deprecated, 557
   Removed, <u>578</u>
PMIX ERR INVALID NAMESPACE
   Deprecated, 557
```

Removed , <u>579</u>
PMIX_ERR_INVALID_NUM_ARGS
Deprecated, <u>557</u>
Removed, <u>578</u>
PMIX_ERR_INVALID_NUM_PARSED
Deprecated, <u>557</u>
Removed, <u>578</u>
PMIX_ERR_INVALID_SIZE
Deprecated, <u>557</u>
Removed , <u>578</u>
PMIX_ERR_INVALID_TERMINATION
Deprecated, <u>578</u>
PMIX_ERR_INVALID_VAL
Deprecated, <u>557</u>
Removed , <u>579</u>
PMIX_ERR_INVALID_VAL_LENGTH
Deprecated, <u>557</u>
Removed, <u>578</u>
PMIX_ERR_JOB_TERMINATED
Deprecated, <u>578</u>
PMIX_ERR_LOST_CONNECTION_TO_CLIENT
Deprecated, <u>578</u>
PMIX_ERR_LOST_CONNECTION_TO_SERVER
Deprecated, <u>578</u>
PMIX_ERR_LOST_PEER_CONNECTION
Deprecated, <u>578</u>
PMIX_ERR_NODE_DOWN
Deprecated, <u>578</u>
PMIX_ERR_NODE_OFFLINE
Deprecated, <u>578</u>
PMIX_ERR_NOT_IMPLEMENTED
Deprecated, <u>557</u>
Removed , <u>579</u>
PMIX_ERR_PACK_MISMATCH
Deprecated, <u>557</u>
Removed , <u>579</u>
PMIX_ERR_PROC_ABORTED
Deprecated, <u>578</u>
PMIX_ERR_PROC_ABORTING
Deprecated, <u>578</u>
PMIX_ERR_PROC_ENTRY_NOT_FOUND
Deprecated, <u>557</u>
Removed, 578

```
PMIX_ERR_PROC_REQUESTED_ABORT
    Deprecated, 557
    Removed, 578
PMIX_ERR_READY_FOR_HANDSHAKE
    Deprecated, 557
    Removed, <u>578</u>
PMIX ERR SERVER FAILED REQUEST
    Deprecated, <u>557</u>
    Removed, 578
PMIX_ERR_SERVER_NOT_AVAIL
    Deprecated, 557
    Removed, 579
PMIX ERR SILENT
    Deprecated, 557
    Removed, 579
PMIX_ERR_SYS_OTHER
    Deprecated, 578
PMIX_EXISTS
    Deprecated, 578
PMIX_GDS_ACTION_COMPLETE
    Deprecated, <u>557</u>
    Removed, 579
PMIX_INFO_ARRAY
    Deprecated, 552
PMIX_MODEX
    Deprecated, 552
PMIX_NOTIFY_ALLOC_COMPLETE
    Deprecated, 557
    Removed, 579
PMIX_PROC_HAS_CONNECTED
    Deprecated, 578
PMIX_PROC_TERMINATED
    Deprecated, 578
```

Index of Environmental Variables

PMIX_LAUNCHER_RNDZ_FILE, 413, 577 PMIX_LAUNCHER_RNDZ_URI, 413, 537, 577

Index of Attributes

```
PMIX ACCESS GRPIDS, 122, 568
PMIX ACCESS PERMISSIONS, 119, 121, 121, 568
PMIX ACCESS USERIDS, 122, 568
PMIX ADD ENVAR, 164, 169, 175, 542
PMIX ADD HOST, 162, 167, 171, 362
PMIX ADD HOSTFILE, 162, 167, 172, 362
PMIX ALL CLONES PARTICIPATE, 68, 71, 71, 180, 182, 183, 185, 564
PMIX ALLOC BANDWIDTH, 164, 170, 199, 202, 204, 204, 323, 324, 386
PMIX ALLOC CPU LIST, 164, 170, 199, 202, 204, 385
PMIX_ALLOC_FABRIC, 199, 202, 204, 323, 385, 579
PMIX_ALLOC_FABRIC_ENDPTS, 165, 170, 199, 200, 202, 203, 204, 204, 323, 324, 385, 579
PMIX_ALLOC_FABRIC_ENDPTS_NODE, 165, 170, 200, 203, 204, 324, 579
PMIX_ALLOC_FABRIC_ID, 199, 202, 204, 204, 323, 385, 579
PMIX_ALLOC_FABRIC_PLANE, 165, 170, 199, 202, 203, 204, 204, 323, 324, 386, 579
PMIX ALLOC FABRIC OOS, 164, 170, 199, 202, 203, 204, 204, 323, 324, 386, 579
PMIX_ALLOC_FABRIC_SEC_KEY, 199, 200, 202, 203, 204, 204, 323, 386, 579
PMIX ALLOC FABRIC TYPE, 165, 170, 199, 202, 203, 204, 204, 323, 324, 385, 386, 579
PMIX ALLOC ID, 200, 203, 385, 556, 557, 568
PMIX ALLOC MEM SIZE, 164, 170, 199, 202, 204, 385
PMIX ALLOC NODE LIST, 164, 170, 199, 202, 203, 385
PMIX ALLOC NUM CPU LIST, 164, 170, 199, 202, 203, 385
PMIX ALLOC NUM CPUS, 164, 170, 198, 202, 203, 385
PMIX ALLOC NUM NODES, 164, 170, 198, 201, 203, 385
PMIX ALLOC QUEUE, 83, 88, 90, 164, 169, 203, 377, 568
PMIX ALLOC REQ ID, 198, 201, 203, 556
PMIX ALLOC TIME, 164, 169, 198, 202, 204, 385
PMIX_ALLOCATED_NODELIST, 100, 297
PMIX_ANL_MAP, 101, 102, 298
PMIX APP ARGV, 103, 299, 568
PMIX APP INFO, 73, 76, 81, 86, 98, 103, 107, 299, 300, 526
PMIX_APP_INFO_ARRAY, 296, 299, 305, 305, 311, 567
PMIX_APP_MAP_REGEX, 104, 299
PMIX_APP_MAP_TYPE, 104, 299
PMIX APP RANK, 104, 302
PMIX APP SIZE, 103, 299, 310
PMIX APPEND ENVAR, 164, 169, 175, 542
PMIX APPLDR, 103, 299, 311
PMIX APPNUM, 73, 76, 81, 86, 99, 103, 104, 107, 296, 299–301, 305, 311, 526, 567
```

```
PMIX_ATTR_UNDEF, 5
PMIX AVAIL PHYS MEMORY, 92, 106, 301
PMIX BINDTO, 162, 168, 172, 298, 362
PMIX CLEANUP EMPTY, 207, 210, 213
PMIX CLEANUP IGNORE, 207, 210, 213
PMIX_CLEANUP_LEAVE_TOPDIR, 207, 210, 213
PMIX CLEANUP RECURSIVE, 207, 210, 213
PMIX CLIENT ATTRIBUTES, 82, 87, 92, 96, 429, 559, 566
PMIX CLIENT AVG MEMORY, 84, 89, 92
PMIX_CLIENT_FUNCTIONS, 82, 87, 91, 92, 96, 565, 566
PMIX_CLUSTER_ID, 99, 297
PMIX_CMD_LINE, 102, 568
PMIX COLLECT DATA, 68, 70, 71, 112, 349
PMIX_COLLECT_GENERATED_JOB_INFO, 68, 70, 71, 71, 257, 349, 564
PMIX COLLECTIVE ALGO, 553
PMIX_CONNECT_MAX_RETRIES, 413, 440
PMIX_CONNECT_RETRY_DELAY, 413, 440
PMIX CONNECT SYSTEM FIRST, 411, 413, 439, 444
PMIX_CONNECT_TO_SYSTEM, 411, 413, 439, 443
PMIX COSPAWN APP, 165, 170, 437
PMIX CPU LIST, 163, 169, 173, 364
PMIX CPUS PER PROC, 163, 168, 173, 364
PMIX CPUSET, 105, 190, 303, 337
PMIX CPUSET BITMAP, 105, 303, 569
PMIX CRED TYPE, 282, 393
PMIX CREDENTIAL, 105, 379
PMIX_CRYPTO_KEY, 282, 299
PMIX DAEMON MEMORY, 84, 89, 92
PMIX_DATA_SCOPE, 73, 76, 78
PMIX DEBUG_DAEMONS_PER_NODE, 363, 431, 432, 437, 438, 532, 536, 539, 571
PMIX_DEBUG_DAEMONS_PER_PROC, 363, 431, 432, 437, 438, 532, 536, 539, 570
PMIX_DEBUG_STOP_IN_INIT, 417, 429, 432, 437, 531, 536
PMIX DEBUG STOP ON EXEC, 417, 428, 430, 436, 531, 536
PMIX_DEBUG_TARGET, 363, 430–432, 437, 437, 438, 532, 536, 537, 539, 570, 571, 579
PMIX_DEBUG_WAIT_FOR_NOTIFY, 417, 429, 436, 437, 532
PMIX DEBUGGER DAEMONS, 363, 431, 432, 437, 528, 532, 536, 539
PMIX DEVICE DISTANCES, 196, 272, 303, 574
PMIX DEVICE ID, 196, 257, 258, 268, 271, 272, 317, 572–574
PMIX DEVICE TYPE, 196, 574
PMIX DISPLAY MAP, 162, 167, 172, 362
PMIX EMBED BARRIER, 65, 65
PMIX ENUM VALUE, 329, 329, 559, 567
PMIX EVENT ACTION TIMEOUT, 142, 148
```

```
PMIX_EVENT_AFFECTED_PROC, 140, 142, 147, 435, 532
PMIX EVENT AFFECTED PROCS, 140, 142, 147, 435
PMIX EVENT BASE, 62, 290, 441
PMIX EVENT CUSTOM RANGE, 139, 142, 147
PMIX EVENT DO NOT CACHE, 142, 147
PMIX EVENT HDLR AFTER, 139, 141, 550
PMIX EVENT HDLR APPEND, 139, 141, 550
PMIX EVENT HDLR BEFORE, 139, 141, 550
PMIX EVENT HDLR FIRST, 139, 141, 549
PMIX_EVENT_HDLR_FIRST_IN_CATEGORY, 139, 141, 549
PMIX_EVENT_HDLR_LAST, 139, 141, 549
PMIX_EVENT_HDLR_LAST_IN_CATEGORY, 139, 141, 550
PMIX EVENT HDLR NAME, 139, 141, 549
PMIX_EVENT_HDLR_PREPEND, 139, 141
PMIX_EVENT_NON_DEFAULT, 142, 147
PMIX_EVENT_PROXY, 142, 147
PMIX_EVENT_RETURN_OBJECT, 139, 142
PMIX EVENT SILENT TERMINATION, 165, 170, 174
PMIX EVENT TERMINATE JOB, 142, 147
PMIX EVENT TERMINATE NODE, 142, 147
PMIX EVENT TERMINATE PROC, 142, 147
PMIX EVENT TERMINATE SESSION, 142, 147
PMIX EVENT TEXT MESSAGE, 142, 147
PMIX EVENT TIMESTAMP, 142, 174, 416–418, 434, 435, 531, 537, 540, 576, 577
PMIX EXEC AGENT, 421, 422, 433, 570
PMIX EXIT CODE, 104, 174, 417, 418, 434, 531, 537, 540, 577
PMIX_EXTERNAL_PROGRESS, 61, 290, 292, 441, 569
PMIX FABRIC COORDINATES, 271, 571
PMIX_FABRIC_COST_MATRIX, 267, 269, 571
PMIX FABRIC DEVICE, 257, 268, 271, 271, 572
PMIX_FABRIC_DEVICE_ADDRESS, 258, 268, 271, 573
PMIX_FABRIC_DEVICE_BUS_TYPE, 258, 268, 271, 573
PMIX FABRIC DEVICE COORDINATES, 258, 271, 573
PMIX FABRIC DEVICE DRIVER, 258, 268, 271, 573
PMIX_FABRIC_DEVICE_FIRMWARE, 258, 268, 271, 573
PMIX_FABRIC_DEVICE_INDEX, 258, 271, 406, 573
PMIX FABRIC DEVICE MTU, 259, 268, 271, 573
PMIX FABRIC DEVICE NAME, 257, 258, 268, 271, 317, 573
PMIX FABRIC DEVICE PCI DEVID, 258, 269, 272, 272, 573, 574
PMIX FABRIC DEVICE SPEED, 259, 268, 271, 573
PMIX FABRIC DEVICE STATE, 259, 268, 272, 573
PMIX FABRIC DEVICE TYPE, 259, 268, 272, 573
PMIX FABRIC DEVICE VENDOR, 258, 268, 271, 573
```

```
PMIX_FABRIC_DEVICE_VENDORID, 258, 271, 573
PMIX FABRIC DEVICES, 257, 271
PMIX FABRIC DIMS, 267, 270, 571
PMIX FABRIC ENDPT, 272, 572
PMIX FABRIC GROUPS, 267, 269, 571
PMIX FABRIC IDENTIFIER, 267, 270, 274, 406, 571
PMIX FABRIC INDEX, 266, 270, 270, 571
PMIX FABRIC NUM DEVICES, 267, 270, 571
PMIX FABRIC PLANE, 267, 268, 270, 270, 271, 274, 406, 572
PMIX_FABRIC_SHAPE, 267, 270, 572
PMIX_FABRIC_SHAPE_STRING, 268, 270, 572
PMIX_FABRIC_SWITCH, 270, 272, 572
PMIX FABRIC VENDOR, 267, 270, 274, 406, 571
PMIX_FIRST_ENVAR, 164, 169, 175, 577
PMIX_FORKEXEC_AGENT, 421, 422, 433, 570
PMIX_FWD_STDDIAG, 415, 419, 422, 556
PMIX_FWD_STDERR, 363, 380, 415, 419, 422, 424, 531, 535, 540
PMIX FWD STDIN, 362, 380, 414, 419, 421, 424
PMIX FWD STDOUT, 363, 380, 415, 419, 421, 424, 531, 535, 539
PMIX GET POINTER VALUES, 73, 74, 76, 77, 564
PMIX GET REFRESH CACHE, 73, 76, 77, 116, 564
PMIX GET STATIC VALUES, 72–74, 77, 77, 564
PMIX GLOBAL RANK, 104, 302, 527
PMIX GROUP ASSIGN CONTEXT ID, 233, 235, 239, 245, 248, 404, 405, 575
PMIX_GROUP_CONTEXT_ID, 233, 404, 575
PMIX GROUP ENDPT DATA, 233, 404, 575
PMIX GROUP_FT_COLLECTIVE, 233, 235, 239, 245, 248, 575
PMIX GROUP ID, 232, 232, 404, 575
PMIX_GROUP_LEADER, 233, 235, 236, 239, 246, 250, 575
PMIX GROUP LOCAL ONLY, 233, 235, 239, 404, 575
PMIX_GROUP_MEMBERSHIP, 233, 236, 404
PMIX_GROUP_NAMES, 233, 576
PMIX GROUP NOTIFY TERMINATION, 233, 235, 236, 239, 241, 245, 248, 575
PMIX_GROUP_OPTIONAL, 233, 235, 236, 239, 244, 248, 404, 575
PMIX_GRPID, 82, 87, 119, 120, 124, 126, 132, 133, 198, 201, 206, 209, 214, 217, 220, 223, 280,
        282, 284, 285, 354, 355, 357, 359, 361, 371, 377, 379, 381, 382, 385, 388, 391, 393, 396,
        397, 399, 402
PMIX HOMOGENEOUS SYSTEM, 290, 292, 567
PMIX HOST, 161, 167, 171, 361
PMIX_HOST_ATTRIBUTES, 82, 87, 92, 96, 430, 559, 566
PMIX HOST FUNCTIONS, 82, 87, 91, 92, 96, 565, 566
PMIX HOSTFILE, 161, 167, 171, 362
PMIX HOSTNAME, 73, 76, 81, 83, 84, 86, 88, 89, 91, 92, 99, 106, 106, 257, 258, 268, 269, 272,
```

```
296, 300–303, 305, 317, 377, 430, 438, 526, 527, 532, 536, 567, 574
PMIX HOSTNAME ALIASES, 106, 300, 569
PMIX HOSTNAME KEEP FQDN, 100, 298, 569
PMIX IMMEDIATE, 72, 76, 77, 107, 116
PMIX INDEX ARGV, 163, 168, 173, 364
PMIX IOF BUFFERING SIZE, 399, 416, 420, 427, 447, 450
PMIX_IOF_BUFFERING_TIME, 399, 416, 420, 427, 447, 450
PMIX IOF CACHE SIZE, 399, 415, 420, 427, 447, 450
PMIX IOF COMPLETE, 400, 426, 427, 428, 451, 460, 570
PMIX_IOF_COPY, 424, 428, 570
PMIX_IOF_DROP_NEWEST, 399, 416, 420, 427, 447, 450
PMIX_IOF_DROP_OLDEST, 399, 415, 420, 427, 447, 450
PMIX IOF PUSH STDIN, 425, 427, 451, 570
PMIX_IOF_REDIRECT, 424, 428, 570
PMIX IOF TAG OUTPUT, 416, 420, 425, 427, 447
PMIX_IOF_TIMESTAMP_OUTPUT, 416, 420, 425, 427, 447
PMIX_IOF_XML_OUTPUT, 416, 420, 425, 427, 448
PMIX JOB CONTINUOUS, 163, 169, 173, 364
PMIX JOB CTRL CANCEL, 207, 210, 212, 388
PMIX JOB CTRL CHECKPOINT, 208, 210, 212, 388
PMIX JOB CTRL CHECKPOINT EVENT, 208, 210, 212, 389
PMIX JOB CTRL CHECKPOINT METHOD, 208, 211, 212, 389
PMIX JOB CTRL CHECKPOINT SIGNAL, 208, 211, 212, 389
PMIX JOB CTRL CHECKPOINT TIMEOUT, 208, 211, 212, 389
PMIX JOB CTRL ID, 206, 207, 209, 210, 212, 212, 388
PMIX JOB CTRL KILL, 207, 210, 212, 388
PMIX_JOB_CTRL_PAUSE, 207, 210, 212, 388
PMIX JOB CTRL PREEMPTIBLE, 208, 211, 213, 389
PMIX_JOB_CTRL_PROVISION, 208, 211, 213, 389
PMIX JOB CTRL PROVISION IMAGE, 208, 211, 213, 389
PMIX_JOB_CTRL_RESTART, 207, 210, 212, 388
PMIX_JOB_CTRL_RESUME, 207, 210, 212, 388
PMIX JOB CTRL SIGNAL, 207, 210, 213, 388
PMIX JOB CTRL TERMINATE, 207, 210, 213, 388
PMIX JOB INFO, 73, 76, 81, 86, 98, 101
PMIX JOB INFO ARRAY, 295, 297, 305, 305, 306, 309, 554, 566
PMIX JOB NUM APPS, 102, 298, 309
PMIX JOB RECOVERABLE, 163, 169, 173, 364
PMIX JOB SIZE, 102, 297, 309, 310, 526, 553, 556
PMIX JOB TERM STATUS, 174, 417, 418, 434, 435, 436, 531, 537, 540, 577
PMIX JOBID, 101, 295–297, 305, 309, 435, 567
PMIX LAUNCH DIRECTIVES, 535
PMIX LAUNCHER, 408, 412, 414
```

```
PMIX_LAUNCHER_DAEMON, 420, 422, 569
PMIX LAUNCHER RENDEZVOUS FILE, 409, 413, 569
PMIX LOCAL CPUSETS, 106, 301, 313
PMIX LOCAL PEERS, 106, 106, 301, 312, 526
PMIX LOCAL PROCS, 106, 301
PMIX_LOCAL_RANK, 105, 302, 431-433, 438, 527, 570, 571
PMIX LOCAL SIZE, 107, 300, 526
PMIX LOCALITY STRING, 187, 189, 302, 337, 527
PMIX LOCALLDR, 106, 300
PMIX_LOG_COMPLETION, 174, 417, 434, 576
PMIX_LOG_EMAIL, 221, 224, 226, 383
PMIX_LOG_EMAIL_ADDR, 221, 224, 226, 383
PMIX LOG EMAIL MSG, 221, 224, 226, 383
PMIX_LOG_EMAIL_SENDER_ADDR, 221, 224, 226
PMIX_LOG_EMAIL_SERVER, 221, 224, 226
PMIX_LOG_EMAIL_SRVR_PORT, 221, 224, 226
PMIX_LOG_EMAIL_SUBJECT, 221, 224, 226, 383
PMIX LOG GENERATE TIMESTAMP, 221, 224, 225
PMIX LOG GLOBAL DATASTORE, 221, 224, 226
PMIX LOG GLOBAL SYSLOG, 220, 223, 225
PMIX_LOG_JOB_EVENTS, <u>174</u>, 417, 434, 576
PMIX LOG JOB RECORD, 221, 224, 226
PMIX LOG LOCAL SYSLOG, 220, 223, 225
PMIX LOG MSG, 226, 383
PMIX LOG ONCE, 220, 223, 226
PMIX LOG PROC ABNORMAL TERMINATION, 174, 576
PMIX_LOG_PROC_TERMINATION, 174, 576
PMIX LOG SOURCE, 221, 224, 225
PMIX_LOG_STDERR, 220, 223, 225, 382
PMIX LOG STDOUT, 220, 223, 225, 382
PMIX_LOG_SYSLOG, 220, 223, 225, 382
PMIX_LOG_SYSLOG_PRI, 220, 223, 225
PMIX LOG TAG OUTPUT, 221, 224, 225
PMIX LOG TIMESTAMP, 221, 224, 225
PMIX_LOG_TIMESTAMP_OUTPUT, 221, 224, 225
PMIX_LOG_XML_OUTPUT, 221, 224, 225
PMIX MAPBY, 162, 168, 171, 172, 298, 362
PMIX MAX PROCS, 100, 100–103, 296–299, 301, 328, 526, 556
PMIX MAX RESTARTS, 163, 169, 173, 364
PMIX MAX VALUE, 329, 329, 559, 567
PMIX MERGE STDERR STDOUT, 163, 168, 172, 363
PMIX MIN VALUE, 329, 329, 559, 567
PMIX MODEL AFFINITY POLICY, 62, 64, 544
```

```
PMIX_MODEL_CPU_TYPE, 62, 64, 544
PMIX MODEL LIBRARY NAME, 62, 64, 300, 324, 544
PMIX MODEL LIBRARY VERSION, 62, 64, 300, 325, 544
PMIX MODEL NUM CPUS, 62, 64, 544
PMIX MODEL NUM THREADS, 62, 64, 544
PMIX MODEL PHASE NAME, 64, 142, 544, 545
PMIX MODEL PHASE TYPE, 64, 142, 544
PMIX MONITOR APP CONTROL, 214, 217, 218, 391
PMIX MONITOR CANCEL, 214, 217, 218, 391
PMIX_MONITOR_FILE, 215, 217, 219, 391
PMIX_MONITOR_FILE_ACCESS, 215, 217, 219, 391
PMIX_MONITOR_FILE_CHECK_TIME, 215, 217, 219, 392
PMIX MONITOR FILE DROPS, 215, 217, 219, 392
PMIX_MONITOR_FILE_MODIFY, 215, 217, 219, 391
PMIX MONITOR FILE SIZE, 215, 217, 219, 391
PMIX_MONITOR_HEARTBEAT, 215, 217, 218, 391
PMIX_MONITOR_HEARTBEAT_DROPS, 215, 217, 219, 391
PMIX MONITOR HEARTBEAT TIME, 215, 217, 219, 391
PMIX MONITOR ID, 214, 217, 218, 391
PMIX NO OVERSUBSCRIBE, 163, 169, 173, 364
PMIX NO PROCS ON HEAD, 163, 168, 173, 364
PMIX NODE INFO, 73, 76, 81, 86, 99, 106, 301
PMIX NODE INFO ARRAY, 296, 300, 305, 306, 310, 312, 316, 317, 567
PMIX NODE LIST, 100, 102, 104, 526
PMIX NODE MAP, 100, 102, 103, 298, 309–311, 324, 325, 556
PMIX NODE MAP RAW, 101, 569
PMIX_NODE_RANK, 105, 302, 432
PMIX NODE SIZE, 106, 300
PMIX_NODEID, 73, 76, 81, 84, 86, 89, 92, 99, 106, 106, 258, 269, 272, 296, 300–302, 305, 317,
        526, 567, 574
PMIX_NOHUP, 416, 420, 422, 569
PMIX_NOTIFY_COMPLETION, 174, 417, 434, 531, 536, 540
PMIX NOTIFY JOB EVENTS, 173, 416, 434, 576
PMIX NOTIFY PROC ABNORMAL TERMINATION, 174, 576
PMIX NOTIFY_PROC_TERMINATION, 174, 576
PMIX_NPROC_OFFSET, 101, 298
PMIX NSDIR, 102, 105, 301, 303
PMIX NSPACE, 82–84, 87–92, 101, 295–297, 305, 310, 377, 378, 430, 435, 438, 532, 536, 539,
        565-567
PMIX NUM ALLOCATED NODES, 100, 568
PMIX NUM NODES, 98, 100, 102, 103, 309, 310, 526, 568
PMIX NUM SLOTS, 100, 101, 103
PMIX OPTIONAL, 72, 75, 77, 116
```

```
PMIX_OUTPUT_TO_DIRECTORY, 173, 576
PMIX OUTPUT TO FILE, 163, 168, 173, 363
PMIX PACKAGE RANK, 105, 303, 568
PMIX PARENT ID, 104, 361
PMIX PERSISTENCE, 119, 121, 121, 354, 455
PMIX PERSONALITY, 162, 167, 171, 362
PMIX PPR, 162, 167, 172, 362
PMIX PREFIX, 161, 167, 172, 361
PMIX PRELOAD BIN, 162, 167, 172, 362
PMIX_PRELOAD_FILES, 162, 167, 172, 362
PMIX_PREPEND_ENVAR, 164, 169, 175, 542
PMIX_PRIMARY_SERVER, 414, 444, 569
PMIX PROC INFO, 81, 86, 99
PMIX_PROC_INFO_ARRAY, 296, 301, 305, 311, 567, 579
PMIX_PROC_MAP, 101, 101, 102, 104, 298, 309, 310, 324, 325, 526, 556
PMIX_PROC_MAP_RAW, 101, 569
PMIX_PROC_PID, 84, 89, 105
PMIX PROC STATE STATUS, 84, 89, 436
PMIX_PROC_TERM_STATUS, 435, 436
PMIX PROCDIR, 105, 303
PMIX PROCID, 81–83, 86–88, 91, 104, 174, 296, 305, 378, 417, 418, 434, 531, 537, 540, 567, 577
PMIX PROGRAMMING MODEL, 62, 64, 300, 324, 544
PMIX PSET MEMBERS, 228, 229, 574
PMIX PSET NAME, 228, 229, 574
PMIX PSET NAMES, 227, 229, 299, 574
PMIX QUERY ALLOC STATUS, 83, 88, 91, 378
PMIX_QUERY_ATTRIBUTE_SUPPORT, 82, 87, 91, 95, 429, 565
PMIX OUERY AUTHORIZATIONS, 84, 89, 91
PMIX_QUERY_AVAIL_SERVERS, 91, 411, 565
PMIX OUERY DEBUG SUPPORT, 83, 88, 91, 377, 531
PMIX_QUERY_GROUP_MEMBERSHIP, 232, 575
PMIX_QUERY_GROUP_NAMES, 232, 574
PMIX_QUERY_JOB_STATUS, 83, 88, 90, 377
PMIX_QUERY_LOCAL_ONLY, 91, 378
PMIX_QUERY_LOCAL_PROC_TABLE, 83, 88, 90, 377, 430, 438, 532, 536, 537
PMIX_QUERY_MEMORY_USAGE, 83, 88, 91, 378
PMIX QUERY NAMESPACE INFO, 90, 565
PMIX QUERY NAMESPACES, 83, 88, 90, 377, 430, 540
PMIX QUERY NUM GROUPS, 232, 574
PMIX_QUERY_NUM_PSETS, 91, 229, 574
PMIX QUERY PROC TABLE, 83, 88, 90, 377, 430, 438, 536, 537, 539
PMIX QUERY PSET MEMBERSHIP, 91, 229, 574
PMIX QUERY PSET NAMES, 91, 229, 574
```

```
PMIX_QUERY_QUALIFIERS, 84, 90, 90, 565
PMIX QUERY QUEUE LIST, 83, 88, 90, 377
PMIX QUERY QUEUE STATUS, 83, 88, 90, 377
PMIX QUERY REFRESH CACHE, 81, 85, 86, 90, 95
PMIX QUERY REPORT AVG, 83, 88, 91, 378
PMIX_QUERY_REPORT_MINMAX, 83, 88, 91, 378
PMIX QUERY RESULTS, 84, 90, 565
PMIX QUERY SPAWN SUPPORT, 83, 88, 91, 377, 531
PMIX QUERY SUPPORTED KEYS, 90, 565
PMIX_QUERY_SUPPORTED_QUALIFIERS, 90, 565
PMIX_RANGE, 119, 121, 121, 124, 126, 132, 134, 139, 215, 232, 354, 357, 359, 374, 404, 405,
       455, 574
PMIX RANK, 82, 83, 87, 88, 91, 104, 165, 170, 296, 301, 305, 378, 433, 437, 526, 567
PMIX_RANKBY, 162, 168, 172, 298, 362
PMIX_REGISTER_CLEANUP, 207, 210, 213
PMIX_REGISTER_CLEANUP_DIR, 207, 210, 213
PMIX_REGISTER_NODATA, 295, 305
PMIX REINCARNATION, 105, 302, 569
PMIX REPORT BINDINGS, 163, 169, 173, 364
PMIX REQUESTOR IS CLIENT, 361, 365
PMIX_REQUESTOR_IS_TOOL, 361, 365, 540
PMIX REQUIRED KEY, 352, 353, 568
PMIX RM NAME, 100, 297
PMIX RM VERSION, 100, 297
PMIX SEND HEARTBEAT, 215, 217, 219
PMIX SERVER ATTRIBUTES, 82, 87, 92, 96, 559, 566
PMIX_SERVER_ENABLE_MONITORING, 290, 292
PMIX SERVER FUNCTIONS, 82, 87, 91, 92, 96, 565, 566
PMIX_SERVER_GATEWAY, 288, 292
PMIX SERVER HOSTNAME, 297, 413
PMIX_SERVER_INFO_ARRAY, 92, 92, 565
PMIX_SERVER_NSPACE, 288, 292, 297, 411, 439, 443
PMIX SERVER PIDINFO, 410, 413, 439, 443
PMIX_SERVER_RANK, 288, 292, 297
PMIX_SERVER_REMOTE_CONNECTIONS, 289, 291
PMIX_SERVER_SCHEDULER, 269, 273, 288, 292, 566, 571
PMIX SERVER SESSION SUPPORT, 288, 292, 566
PMIX SERVER SHARE TOPOLOGY, 290, 291, 566
PMIX SERVER START TIME, 292, 566
PMIX SERVER SYSTEM SUPPORT, 288, 292, 408
PMIX SERVER TMPDIR, 288, 290, 292, 408-410
PMIX SERVER TOOL SUPPORT, 279, 288, 290, 291
PMIX SERVER URI, 84, 89, 410, 411, 413, 439, 443
```

```
PMIX_SESSION_ID, 99, 99, 101, 108, 295, 296, 305, 309, 435, 567
PMIX SESSION INFO, 73, 76, 81, 86, 98, 100, 108, 296, 298, 324
PMIX SESSION INFO ARRAY, 295, 296, 305, 306, 309, 554
PMIX SET ENVAR, 163, 169, 175, 542
PMIX SET SESSION CWD, 161, 167, 172, 361
PMIX_SETUP_APP_ALL, 323, 326
PMIX SETUP APP ENVARS, 323, 326, 531, 535
PMIX SETUP APP NONENVARS, 323, 326
PMIX SINGLE LISTENER, 61, 289, 291
PMIX_SOCKET_MODE, 61, 289, 291, 440
PMIX_SPAWN_TOOL, 165, 170, 173, 419, 535
PMIX_SPAWNED, 105, 302, 361
PMIX STDIN TGT, 162, 168, 172, 362
PMIX_SWITCH_PEERS, 272, 272, 572
PMIX SYSTEM TMPDIR, 288, 292, 408, 410
PMIX_TAG_OUTPUT, 162, 168, 172, 363
PMIX_TCP_DISABLE_IPV4, 61, 64, 289, 440
PMIX TCP DISABLE IPV6, 61, 64, 289, 440
PMIX TCP IF EXCLUDE, 61, 64, 289, 440
PMIX TCP IF INCLUDE, 61, 64, 289, 440
PMIX TCP IPV4 PORT, 61, 64, 289, 440
PMIX TCP IPV6 PORT, 61, 64, 289, 440
PMIX TCP REPORT URI, 61, 63, 289, 440
PMIX TCP URI, 63, 410, 411, 439, 443
PMIX TDIR RMCLEAN, 100, 299
PMIX THREADING MODEL, 62, 64, 544
PMIX_TIME_REMAINING, 78, 84, 89, 91, 378
PMIX_TIMEOUT, 4, 68, 71, 74, 77, 78, 107, 116, 117, 119, 121, 124, 126, 132, 134, 180, 182,
        183, 185, 231, 235, 237, 240, 241, 243, 245, 248, 250, 252, 281, 282, 284, 286, 349, 353,
        355, 357, 359, 364, 366, 369, 393, 396, 414, 446, 537, 571
PMIX_TIMEOUT_REPORT_STATE, 173, 576
PMIX_TIMEOUT_STACKTRACES, 173, 576
PMIX TIMESTAMP OUTPUT, 162, 168, 172, 363
PMIX_TMPDIR, 100, 102, 301
PMIX_TOOL_ATTACHMENT_FILE, 410, 411, 413, 439, 443, 569
PMIX_TOOL_ATTRIBUTES, 82, 87, 92, 96, 559, 566
PMIX TOOL CONNECT OPTIONAL, 413, 569
PMIX TOOL DO NOT CONNECT, 410, 413, 439, 441
PMIX TOOL FUNCTIONS, 82, 87, 91, 92, 96, 565, 566
PMIX_TOOL_NSPACE, 379, 409, 412, 439, 441
PMIX TOOL RANK, 379, 409, 412, 439, 441
PMIX TOPOLOGY2, 290, 291, 566, 579
PMIX UNIV SIZE, 8, 99, 296, 309, 553, 554, 556
```

```
PMIX_UNSET_ENVAR, 164, 169, 175, 542
PMIX USERID, 82, 87, 119, 120, 124, 126, 132, 133, 198, 201, 206, 209, 214, 217, 220, 223, 280,
       282, 284, 285, 354–357, 359, 361, 370, 377, 379, 381, 382, 384, 388, 391, 393, 395, 397,
       399, 402
PMIX USOCK DISABLE, 61, 289, 291
PMIX VERSION INFO, 380, 381
PMIX WAIT, 76, 78, 124, 126, 357
PMIX WAIT FOR CONNECTION, 414, 446, 537, 571
PMIX WDIR, 161, 167, 172, 299, 361
PMIX ALLOC NETWORK
   Deprecated, 579
PMIX ALLOC NETWORK ENDPTS
   Deprecated, 579
PMIX_ALLOC_NETWORK_ENDPTS_NODE
   Deprecated, 579
PMIX_ALLOC_NETWORK_ID
   Deprecated, 579
PMIX_ALLOC_NETWORK_PLANE
   Deprecated, 579
PMIX_ALLOC_NETWORK_QOS
   Deprecated, 579
PMIX ALLOC_NETWORK_SEC_KEY
   Deprecated, 579
PMIX ALLOC NETWORK TYPE
   Deprecated, 579
PMIX ARCH
   Deprecated, 558
   Removed, 581
PMIX COLLECTIVE ALGO
   Deprecated, 558
   Removed, 580
PMIX_COLLECTIVE_ALGO_REQD
   Deprecated, 555
   Removed, 580
PMIX_DEBUG_JOB
   Deprecated, 579
PMIX DSTPATH
   Deprecated, 558
   Removed, 580
PMIX ERROR GROUP ABORT
   Deprecated, 553
   Removed, 555
PMIX ERROR GROUP COMM
```

Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_ERROR_GROUP_GENERAL
Deprecated, <u>553</u>
Removed, 555
PMIX_ERROR_GROUP_LOCAL
Deprecated, 553
Removed , <u>555</u>
PMIX_ERROR_GROUP_MIGRATE
Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_ERROR_GROUP_NODE
Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_ERROR_GROUP_RESOURCE
Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_ERROR_GROUP_SPAWN
Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_ERROR_HANDLER_ID
Deprecated, <u>553</u>
Removed, 555
PMIX_ERROR_NAME
Deprecated, <u>553</u>
Removed , <u>555</u>
PMIX_HWLOC_HOLE_KIND
Deprecated, <u>558</u>
Removed, <u>580</u>
PMIX_HWLOC_SHARE_TOPO
Deprecated, <u>558</u>
Removed , <u>580</u>
PMIX_HWLOC_SHMEM_ADDR
Deprecated, <u>558</u>
Removed , <u>580</u>
PMIX_HWLOC_SHMEM_FILE
Deprecated, <u>558</u>
Removed , <u>580</u>
PMIX_HWLOC_SHMEM_SIZE
Deprecated, <u>558</u>
Removed , <u>580</u>
PMIX_HWLOC_XML_V1
Deprecated 558

Removed, **580** PMIX_HWLOC_XML_V2 Deprecated, 558 Removed, 580 PMIX_LOCAL_TOPO Deprecated, <u>558</u> Removed, 580 PMIX LOCALITY Deprecated, 579 PMIX_MAP_BLOB Deprecated, 558 **Removed**, **581** PMIX MAPPER Deprecated, 558 Removed, 581 PMIX_NON_PMI Deprecated, 558 **Removed**, <u>581</u> PMIX_PROC_BLOB Deprecated, <u>558</u> **Removed**, <u>**580**</u> PMIX PROC DATA Deprecated, 579 PMIX PROC URI Deprecated, 558 Removed, 581 PMIX_RECONNECT_SERVER Deprecated, 579 PMIX_TOPOLOGY Deprecated, 579 PMIX_TOPOLOGY_FILE Deprecated, 558 Removed, 580 PMIX_TOPOLOGY_SIGNATURE Deprecated, 559 **Removed**, **580** PMIX_TOPOLOGY_XML Deprecated, 559 Removed, 580